

Quantum Stress Focusing in Descriptive Chemistry

Jianmin Tao^{1,2}, Giovanni Vignale², and I. V. Tokatly^{3,4}

¹*Theoretical Division and CNLS, Los Alamos National Laboratory, Los Alamos, New Mexico 87545*

²*Department of Physics, University of Missouri-Columbia, Columbia, Missouri 65211*

³*European Theoretical Spectroscopy Facility (ETSF),*

Dpto. Fisica Materiales, Universidad del Pais Vasco, 20018 Donostia, Spain

⁴*Moscow Institute of Electronic Technology, Zelenograd, 124498 Russia*

(Dated: August 22, 2021)

We show that several important concepts of descriptive chemistry, such as atomic shells, bonding electron pairs and lone electron pairs, may be described in terms of *quantum stress focusing*, i.e. the spontaneous formation of high-pressure regions in an electron gas. This description subsumes previous mathematical constructions, such as the Laplacian of the density and the electron localization function, and provides a new tool for visualizing chemical structure. We also show that the full stress tensor, defined as the derivative of the energy with respect to a local deformation, can be easily calculated from density functional theory.

PACS numbers: 71.15.Mb, 31.15.Ew, 71.45.Gm

Atomic shell structure, electron pair domains, π -electron subsystems, etc., are common concepts in descriptive chemistry and play a significant role in modern electronic structure theory. These concepts help us to visualize the bonding between atoms in terms of small groups of localized electrons (e.g. two electrons of opposite spin in a simple covalent bond) and therefore play an important role in predicting new molecular structures and in describing structural changes due to chemical reactions.

A precise quantitative description of small groups of localized electrons has been sought for a long time [1, 2], but none of the solutions proposed so far is completely satisfactory. The natural candidate – the electronic density $n(\mathbf{r})$ – has a clear physical meaning, but fails to reveal quantum mechanical features such as atomic shell structure [3] or the localization of electron pairs of opposite spin in a covalent bond. The Laplacian $\nabla^2 n$ of the density [1, 4] provides a better way to visualize molecular geometry, but lacks a clear physical significance and fails [5] to reveal the atomic shell structure of heavy atoms. Recently, a very useful indicator of electron localization has been constructed [5] from the curvature of the (spherically averaged) conditional pair probability function $P_{\sigma\sigma}(\mathbf{r}, \mathbf{r}')$ (the probability of finding an electron of spin σ at \mathbf{r} given that there is another electron of the same spin orientation at \mathbf{r}') evaluated at $\mathbf{r} = \mathbf{r}'$. In the simplest approximation this curvature is proportional to

$$D_{\sigma}(\mathbf{r}) = \tau_{\sigma} - \frac{|\nabla n_{\sigma}|^2}{8n_{\sigma}}, \quad (1)$$

where $\tau_{\sigma}(\mathbf{r}) = \sum_l \frac{1}{2} |\nabla \psi_{l\sigma}(\mathbf{r})|^2$ is the non-interacting kinetic energy density of σ -spin electrons (atomic units $m = \hbar = e^2 = 1$ are used throughout), $\psi_{l\sigma}(\mathbf{r})$ are the occupied Kohn-Sham orbitals of spin σ , and n_{σ} is the σ -spin electron density ($n = n_{\uparrow} + n_{\downarrow}$). From D_{σ} one

constructs the *electron localization function* (ELF)[5]

$$\eta_{\sigma}(\mathbf{r}) = \frac{1}{1 + (D_{\sigma}/\tau_{\sigma}^{\text{TF}})^2}, \quad (2)$$

where $\tau_{\sigma}^{\text{TF}} = (3/10)(6\pi^2)^{2/3}n_{\sigma}^{5/3}$ is the Thomas-Fermi kinetic energy density of σ -spin electrons. The ELF provides excellent visualization of atomic shells as well as a quantitative description of valence shell electron pair repulsion theory [6] of bonding and it has been recently extended to excited and time-dependent states [7]. Nevertheless, it has two defects: (1) it remains a mathematical construction of dubious physical significance [8] and (2) it is difficult to calculate ELF beyond [9] the lowest-order approximation [Eq. (1)] and for this reason it can hardly be applied to strongly interacting systems.

In this paper we propose a more physical way of looking at atomic shells and bonds based on the idea of *quantum stress focusing*, by which we mean the spontaneous formation of regions of high and low pressure in the electron gas. The existence of such regions is nontrivial in view of the fact that the electrostatic potential created by the nuclei has no maxima or minima (Earnshaw's theorem).

To understand how pressure maxima can arise we must recall a few basic concepts from the mechanics of continuum media. First, we introduce the stress tensor [10, 11], $p_{ij}(\mathbf{r})$, – a symmetric rank-2 tensor with the property that p_{ij} is the i -th component of the force per unit area acting on an infinitesimal surface perpendicular to the j -th axis [12]. The divergence of this tensor, $\sum_j \partial_j p_{ij}(\mathbf{r})$ (∂_j being the derivative with respect to r_j , the j -th component of \mathbf{r}), is the i -th component of the force per unit volume exerted on an infinitesimal element of the electron gas by the surrounding electrons. For convenience, in the following we will exclude from the stress tensor the electrostatic Hartree contribution, which is then treated as an external field on equal footing with the field of the nuclei.




FIG. 1: Indicators of electron localization as functions of the radial distance r constructed respectively from the non-interacting and interacting pressures p^S and p [Eq. (9)] for the Ar, Zn, and Xe atoms. The XC part of the pressure is evaluated with the GGA functional of Ref. [16]. The maxima of the pressure reveal electronic shells, indicated as usual by the capital letters K,L,M,...

Next, we separate p_{ij} into a hydrostatic pressure part, which is isotropic, and a shear part, which is traceless:

$$p_{ij}(\mathbf{r}) = \delta_{ij}p(\mathbf{r}) + \pi_{ij}(\mathbf{r}), \quad \text{Tr } \pi_{ij} = 0. \quad (3)$$

Here $p(\mathbf{r}) \equiv \frac{1}{3}\text{Tr } p_{ij}(\mathbf{r})$ is the quantum pressure, i.e. the derivative of the internal energy with respect to a local deformation that changes the volume of a small element of the electron liquid without changing its shape. Similarly, the shear stress $\pi_{ij}(\mathbf{r})$ is the derivative of the internal energy with respect to a local deformation that changes the shape of a small element of the liquid, without changing its volume. In a quantum system, these local deformations are implemented through a local change in the metrics (see Eq. (11) below and Ref. 11 for details).

In the ground state of an electronic system the forces arising from the divergence of p_{ij} must exactly balance the external force exerted by the nuclei. In other words, the stresses satisfy the equilibrium condition

$$-n(\mathbf{r})\partial_i v(\mathbf{r}) = \partial_i p(\mathbf{r}) + \sum_j \partial_j \pi_{ij}(\mathbf{r}), \quad (4)$$

where $v(\mathbf{r})$ is the external potential due to the nuclei plus the Hartree potential.

Eq. (4) is not very useful if we don't have explicit expressions for p and π_{ij} . However, certain approximations can be made. For example, replacing the exact quantum pressure by the quasi-classical Fermi pressure $p^{\text{TF}}(\mathbf{r}) = \frac{2}{5}(3\pi^2)^{2/3}n^{5/3}$ and neglecting the shear term yields the well-known Thomas-Fermi equation for the equilibrium density. Because the electrostatic potential $v(\mathbf{r})$ in an atom does not admit maxima and minima, we immediately see that this approximation (as any approximation that neglects π) cannot yield local maxima or minima in the pressure. In the special case of the spherical Thomas-Fermi atom this implies that the density and the pressure are both monotonically decreasing functions of the radial distance r : the shell structure is absent.

The situation changes radically when the shear stress is included. Now it is possible for the hydrostatic force $\partial_i p$ to vanish because the electrostatic force $n\partial_i v$ can be balanced by the shear force $\sum_j \partial_j \pi_{ij}$. It is therefore possible to have maxima or minima in the pressure. We may picture the regions of high pressure as regions which are hard to compress, because of the high energy cost of bringing the particles closer together against the “exchange-correlation hole”. These “maximally compressed regions” quite naturally correspond to the shells and bonds of descriptive chemistry.

We now show that regions of maximum and minimum pressure do occur in spherical atoms, with peaks corresponding to the K,L,M... shells of the standard shell model. To see this we don't need to go any further than the lowest-order approximation for the stress tensor, which has the form:

$$p_{ij}^S = \frac{1}{2} \sum_{l\sigma} (\partial_i \psi_{l\sigma}^* \partial_j \psi_{l\sigma} + \partial_j \psi_{l\sigma}^* \partial_i \psi_{l\sigma}) - \frac{1}{4} \delta_{ij} \nabla^2 n, \quad (5)$$

where the sum runs over the occupied Kohn-Sham orbitals. For an atom of spherical symmetry this further simplifies to

$$p_{ij}^S = p^S \delta_{ij} + \pi^S \left(\frac{r_i r_j}{r^2} - \frac{\delta_{ij}}{3} \right), \quad (6)$$

where p^S is the noninteracting pressure given by

$$p^S = \frac{1}{3} \sum_{l\sigma} |\nabla \psi_{l\sigma}|^2 - \frac{1}{4} \nabla^2 n, \quad (7)$$

and

$$\pi^S = \sum_{l\sigma} (|\partial_r \psi_{l\sigma}|^2 - r^{-2} |\partial_\theta \psi_{l\sigma}|^2). \quad (8)$$




FIG. 2: Non-interacting pressure (p^S) and shear stress (π^S) pressure in Ar. The peaks in p^S identify the position of the shells and the peaks in π^S define the boundary between the shells. Inset: distribution of stresses in the atom. The grey scale indicates the pressure distribution with dark (light) regions corresponding to high (low) value of the pressure indicator L (Eq. 9). The arrows indicate the direction of the shear force $(2/3)\nabla\pi + (2/r)\pi$. Observe how the shells are “squeezed” by shear forces pointing in opposite directions.

To graphically represent the noninteracting pressure p^S , we define the dimensionless quantity $\tilde{p}^S = p^S/p^{\text{TF}}$. Since this ratio diverges both at a nucleus (with a positive sign) and in the density tail (with a negative sign) [13], we find it convenient to plot the function

$$L(\mathbf{r}) = \frac{1}{2} \left(1 + \frac{\tilde{p}^S}{\sqrt{1 + (\tilde{p}^S)^2}} \right) \quad (9)$$

which has values in the range $(0, 1)$, with $L = 1$ corresponding to $\tilde{p}^S = \infty$ and $L = 0$ corresponding to $\tilde{p}^S = -\infty$. Figures 1a–1c show conclusively the existence of peaks and troughs of the noninteracting pressure (solid curves), each of which defines a spherical surface on which the gradient of p^S vanishes. Since p^{TF} is a monotonically decreasing function, the oscillatory behavior of these graphs is entirely due to p^S : in particular, the maxima and minima of L are very close to the maxima and minima of p^S . As discussed above, we interpret the peaks in pressure as quantum shells. Figure 2 shows the behavior of p^S and π^S as functions of r , and the inset depicts schematically the distribution of shear forces in the atom. Observe that the minima of the shear stress are in correspondence with the maxima of the pressure, and viceversa. This is natural, because the gradients of p and π , i.e., approximately, the bulk force and the shear force must have opposite signs and largely cancel in order to balance the relatively weak nuclear attraction. The fact that the shell is located at the minimum of the shear stress implies that the shear force has opposite signs on the two sides of the shell, thus “locking” the shell into position.

Two more points should be made about Eq. (7) for the pressure. The first is that the Laplacian of the density

appears in it prominently, as a universal component of the pressure: this explains a posteriori the partial success of the Laplacian as an indicator of shell structure. More interestingly, the ELF (Eq. 2) is also closely related to the pressure. Indeed, the non-interacting pressure includes a “bosonic” contribution, p_0 , which is obtained from Eq. (7) by putting all the electrons in the lowest energy orbital $\psi_{0\sigma}$:

$$p_{0\sigma} = (1/3)[|\nabla n_\sigma|^2/(4n_\sigma) - (3/4)\nabla^2 n_\sigma]. \quad (10)$$

The excess pressure $p_{\text{ex}\sigma} \equiv p_\sigma^S - p_{0\sigma}(\mathbf{r})$ is called “Pauli pressure” (since it is generated by the Pauli exclusion principle, which forces the occupation of higher energy orbitals) and is easily seen to coincide with D_σ , the curvature of the conditional probability function (Eq. (1)) and main ingredient of the ELF. Physically, high electronic pressure means that it is difficult to bring the particles closer together, which implies that the XC hole surrounding the electron is very “deep”, i.e. the probability of finding another electron of the same spin around the reference electron is low. This leads to a high value of the ELF.

One of the attractive features of our proposal is the relative ease with which strong electron-electron interactions can be included in the calculation of the stress tensor. Already p^S includes some interaction effects through the Kohn-Sham orbitals [14]. To include additional exchange-correlation (XC) effects we observe that in density functional theory (DFT) the XC energy is a functional not only of the density n , but also, tacitly, of the metrics g_{ij} of the space[11]: $E_{\text{xc}} = E_{\text{xc}}[n, g_{ij}]$.

In conventional applications of DFT, one works with fixed Euclidean metrics $g_{ij} = \delta_{ij}$, so there is no need to emphasize the dependence on the metrics. Here, however, we are interested in small deformations, which can be described by the coordinate transformation [15] $\boldsymbol{\xi}(\mathbf{r}) = \mathbf{r} - \mathbf{u}(\mathbf{r})$, where \mathbf{u} is an infinitesimal nonlinear function of \mathbf{r} . The transformation from \mathbf{r} to $\boldsymbol{\xi}$ changes the density from $n(\mathbf{r})$ to, up to first order in \mathbf{u} , $\tilde{n}(\boldsymbol{\xi}) = n(\boldsymbol{\xi}) + u_i \partial_i n(\boldsymbol{\xi})$ (notice that i here are cartesian indices with the convention that repeated indices are summed over), and the metric tensor from the Euclidean value δ_{ij} to

$$g_{ij} \equiv (\partial r_\alpha / \partial \xi_i)(\partial r_\alpha / \partial \xi_j) = \delta_{ij} + \partial_i u_j + \partial_j u_i. \quad (11)$$

Since the XC energy cannot depend upon the arbitrary choice of coordinates we must have $E_{\text{xc}}[n, \delta_{ij}] = E_{\text{xc}}[\tilde{n}, g_{ij}]$, which for an arbitrary infinitesimal transformation implies

$$n \partial_i \frac{\delta E_{\text{xc}}}{\delta n} = \partial_j \left\{ \delta_{ij} n \frac{\delta E_{\text{xc}}}{\delta n} - 2 \frac{\delta E_{\text{xc}}}{\delta g_{ij}} \right\}, \quad (12)$$

where the derivative with respect to n is taken at constant g_{ij} and viceversa. Since the left-hand side of this equation is the XC force density, the right-hand side must

be the divergence of the XC stress tensor. This leads to the result

$$p_{ij}^{\text{xc}} = \delta_{ij} n v_{\text{xc}} - 2 \frac{\delta E_{\text{xc}}}{\delta g_{ij}}, \quad (13)$$

where v_{xc} is the XC potential defined by $v_{\text{xc}} \equiv \delta E_{\text{xc}} / \delta n$, and the functional derivative is evaluated at $g_{ij} = \delta_{ij}$. This important result shows that we may calculate the XC contribution to the stress tensor from a knowledge of the XC energy as a functional of density and metrics. It turns out that semi-local XC functionals [16, 17] are of a form that can be easily generalized to include a nontrivial metrics.

For example, consider the generalized gradient approximation (GGA) for a spin-unpolarized system. The standard form of this functional is $E_{\text{xc}}[n] = \int d\mathbf{r} e_{\text{xc}}(n, s)$, where $s = |\nabla n| / (2k_F n)$ is the reduced density gradient. Going to curvilinear coordinates we immediately obtain the generalized form

$$E_{\text{xc}}[n, g_{ij}] = \int d\xi \sqrt{g(\xi)} e_{\text{xc}}(\tilde{n}, \tilde{s}), \quad (14)$$

where $g \equiv \det(g_{ij})$ is the determinant of the metric tensor, $\tilde{n}(\xi) \equiv n(\mathbf{r}(\xi))$ is the density in the new coordinates, and $\tilde{s} = \sqrt{g^{ij} \partial_i \tilde{n} \partial_j \tilde{n}} / (2k_F \tilde{n})$, where $\tilde{k}_F = (3\pi^2 \tilde{n})^{1/3}$ and $g^{ij} = (g^{-1})_{ij}$. Using the identity $\delta g = g g^{ij} \delta g_{ij} = -g g_{ij} \delta g^{ij}$, we evaluate the functional derivative of $E_{\text{xc}}[\tilde{n}, g_{ij}]$ with respect to g_{ij} , and then substitute it into Eq. (13). We finally obtain

$$p_{ij}^{\text{xc}} = \delta_{ij} (n v_{\text{xc}} - e_{\text{xc}}) - \frac{\partial_i n \partial_j n}{2k_F n |\nabla n|} \frac{\partial e_{\text{xc}}}{\partial s}. \quad (15)$$

The trace of this yields the XC pressure

$$p^{\text{xc}} = n v_{\text{xc}} - e_{\text{xc}} - \frac{s}{3} \frac{\partial e_{\text{xc}}}{\partial s}, \quad (16)$$

which exactly recovers the uniform-gas limit [10].

In Figs. 1a–1c we have also plotted the normalized pressure $L(r)$ including the XC correction (dashed curves), which is calculated by the GGA of Ref. [16]. In the core region of the atom, where the density is high, p^{xc} is utterly negligible. In the valence region, the XC contribution becomes relatively important, so the difference is noticeable. In the density tail, both p^{S} and p^{xc} decay exponentially, causing the difference to be small. It is possible, however, and indeed quite likely, that XC contributions become more important in strongly correlated systems, where the zeroth-order description provided by the Kohn-Sham orbitals begins to break down. This remains a subject for future investigations.

In conclusion, we have found that the analysis of the quantum stress field reveals important features of the electronic structure of atoms. Although we have considered only atoms so far, there is every reason to expect

that stress focusing will also occur in molecules in correspondence of electron pair domains, such as the ones that are commonly associated with single and multiple covalent bonds and with the so-called lone-pair regions of the molecule. In general, the local pressure – the trace of the stress tensor – is expected to provide an excellent quantitative description of electron localization. More information may emerge from the complete study of the stress tensor (its eigenvalues and principal axes) and its topology – a study that is just beginning to be undertaken.

We acknowledge valuable discussions with C.A. Ullrich and P.L. de Boeij. This work was supported by DOE under Grant No. DE-FG02-05ER46203, and by DOE under Contract No. DE-AC52-06NA25396 and Grant No. LDRD-PRD X9KU at LANL (J.T).

-
- [1] R.F. W. Bader, *Atoms in Molecules - A Quantum Theory* (Oxford University Press, Oxford, 1990).
 - [2] R.J. Gillespie and I. Hargittai, *The Vsepr Model of Molecular Geometry* (Allyn & Bacon, 1992).
 - [3] P.W. Ayers and R.G. Parr, *Int. J. Quantum Chem.* **95**, 877 (2003).
 - [4] R.F.W. Bader and H. Essen, *J. Chem. Phys.* **80**, 1943 (1984).
 - [5] A.D. Becke and K.E. Edgecombe, *J. Chem. Phys.* **92**, 5397 (1990).
 - [6] R.J. Gillespie, *Molecular Geometry* (Van Nostrand Reinhold, London, 1972).
 - [7] T. Burnus, M.A.L. Marques, and E.K.U. Gross, *Phys. Rev. A* **71**, 010501(R) (1985).
 - [8] A. Savin, *J. Mol. Struct. (Theochem)* **727**, 127 (2005).
 - [9] E. Matito, B. Silvi, M. Duran, and M. Solá, *J. Chem. Phys.* **125**, 024301 (2006).
 - [10] O.H. Nielsen and R.M. Martin, *Phys. Rev. B* **32**, 3780 (1985).
 - [11] I.V. Tokatly, *Phys. Rev. B* **71**, 165104 (2005); **71**, 165105 (2005); **75**, 125105 (2007).
 - [12] $p_{ij}(\mathbf{r})$ is formally defined as the derivative of the internal energy with respect to a local strain $u_{ij}(\mathbf{r})$, arising from a deformation in which each particle is displaced from \mathbf{r}_n to $\mathbf{r}_n + \mathbf{u}(\mathbf{r}_n)$, with $u_{ij} \equiv (\partial_i u_j + \partial_j u_i) / 2$. This deformation corresponds to a local change in metrics [see Eq. (11)] which modifies the Hamiltonian according to the formulas given in Ref. [11].
 - [13] The positive divergence at a nucleus is caused by the Laplacian of the density, which diverges as $1/r$ for $r \rightarrow 0$. The negative divergence in the density tail ($r \rightarrow \infty$) reflects the negative value of p^{S} in the non-classical regions where the wave function decays exponentially: $p^{\text{S}} \xrightarrow{r \rightarrow \infty} -4n |e_{\text{max}}^{\text{KS}}| / 3$, where $e_{\text{max}}^{\text{KS}}$ is the highest occupied Kohn-Sham orbital energy of the atom.
 - [14] W. Kohn and L.J. Sham, *Phys. Rev.* **140**, A1133 (1965).
 - [15] J. Tao, G. Vignale, and I.V. Tokatly, *Phys. Rev. B* **76**, 195126 (2007).
 - [16] J.P. Perdew, K. Burke, and M. Ernzerhof, *Phys. Rev. Lett.* **77**, 3865 (1996).
 - [17] J. Tao, J.P. Perdew, V.N. Staroverov, and G.E. Scuseria,

Phys. Rev. Lett. **91**, 146401 (2003).