Superconductivity as the effect of Bose-Einstein condensation and the relationship of superconductor critical temperature and its electronic specific heat

B. V. Vasiliev

1 Should superconductivity be considered as Bose-Einstein condensation?

The phenomenon of the Bose-Einstein condensation has some peculiarities.

This condensate is an ordered state of bosons. Therefore, the evaporation of condensate into the normal state should be classified as the order-disorder transition with its characteristic features.

In addition, the condensate of electrically charged particles can be destroyed both by heating and by the application of a sufficiently strong magnetic field. Therefore, between the critical temperature and the critical magnetic field of the condensate in this case there is a relationship, which must manifests itself in superconductors, if the superconductivity arises from the Bose-Einstein condensation.

Let consider these questions more detail.

1.1 The Bose-Einstein distribution

In normal metals, all energy levels up to the Fermi level at T = 0 are filled by electrons. In a superconductor, electrons near the Fermi level, are combined in pairs. Let us consider the two-level system in which at T=0 these pairs occupy the energy level, which is lying on Δ_0 below the Fermi-energy. This level with energy $\mathcal{E}_F - \Delta_0$ is basic for bosons - carriers of superconductivity. It is filled by N_0 particles in a singlet state with zero total momentum and zero spin.

Additionally, there is the level with energy $\mathcal{E}_F + \Delta_0$. It is filled by N_1 bosons in the excited triplet state with spin S = 1.¹

The population of these levels is determined by the Bose-Einstein distribution:

$$N_j = \frac{1}{e^{(\varepsilon_j - \mu)/kT} - 1}.$$
(1)

Where ε_j is energy of *j*-th level, μ is the chemical potential.

¹The question of the pairing of electrons in the triplet state with spin 1 has been discussed in the literature repeatedly before. See, eg, [1].

This distribution is characterized by the fact that at T = 0 when $\varepsilon = 0$, all particles fall into the Bose-Einstein condensate at the ground state

$$\lim_{kT \to 0} \frac{1}{e^{(-\mu)/kT} - 1} = N_0.$$
⁽²⁾

It is satisfied at the condition

$$\mu = -\frac{kT}{N_0},\tag{3}$$

i.e. at

$$\mu \cong 0. \tag{4}$$

The destruction of superconductivity at $T \to T_c$ occurs due to the fact that bosons b_0 break, turning in a pair of fermions (electrons):

$$b_0 \to 2e.$$
 (5)

Thus, the system consisting of a superconducting condensate of bosons, is not closed. Its density depends on temperature.

1.2 The temperature dependence of the energetic distribution of bosons

Let us assume that at a given temperature $T < T_c$ in accordance with Eq.(1), there are N_0 particles on the basic level in the singlet state and N_1 in the excited state.

It is important to note that the level of the Fermi-energy lies exactly between the basic and excited levels of bosons, so there should be a reaction in which these bosons split into electrons:

$$b_0 + b_1 \rightleftharpoons 4e. \tag{6}$$

These bosons can not be included in the condensate if they are participating in this reaction, because virtually they are fermions. The Bose-Einstein condensate can be formed only by the particles which make up the difference between the populations of levels $N_0 - N_1$. In dimensionless form, this difference defines the order parameter:

$$\Psi = \frac{N_0}{N_0 + N_1} - \frac{N_1}{N_0 + N_1}.$$
(7)

In the theory of superconductivity, by definition, the order parameter is determined by the value of the energy gap

$$\Psi = \Delta_T / \Delta_0 \tag{8}$$

At taking a counting of energy from the level ε_0 , we obtain

$$\frac{\Delta_T}{\Delta_0} = \frac{N_0 - N_1}{N_0 + N_1} \approx \frac{e^{2\Delta_T/kT} - 1}{e^{2\Delta_T/kT} + 1} = th(2\Delta_T/kT).$$
(9)



Figure 1: The temperature dependence of the value of gap in the energetic spectrum of bosons calculated on Eq.(10).

Passing to dimensionless variables $\delta\equiv\frac{\Delta_T}{\Delta_0}$, $t\equiv\frac{kT}{kT_c}~~\beta\equiv\frac{\Delta_0}{kT_c}$ we have

$$\delta = \frac{e^{\beta\delta/t} - 1}{e^{\beta\delta/t} + 1} = th(\beta\delta/t).$$
(10)

This equation describes the temperature dependence of the energy gap in the spectrum of bose-particles. It coincides in form with other equations describing other physical phenomena, which are also characterized by the existence of the temperature dependence of order parameters [2],[3]. For example, such as the concentration of the superfluid component in liquid helium or the spontaneous magnetization of ferromagnetic materials. This equation is common for all order-disorder transitions (the phase transitions of type II in the Landau classification).

The solution of this equation, obtained by the iteration method, is shown in Fig.(1). This decision is very accurately coincides with the solution of the integral equation of the BCS, which was built on the account of the phonon spectrum, and is in a quite satisfactory agreement with the measurement data.

After numerical integrating we can obtain the averaging value of the gap:

$$\langle \Delta \rangle = \Delta_0 \int_0^1 \delta dt = 0.852 \ \Delta_0 \ . \tag{11}$$

1.3 The relationship between the critical parameters of boson condensate

1.3.1 The energy of ground state

At the heating up to the critical temperature, the condensate particles acquire sufficient energy to break the linking between pairs.

The motion of an electron (the electric charge e and mass m_e) with the kinetic energy \mathcal{E}_{kin} is accompanied by the magnetic field energy \mathcal{E}_H . At $v \ll c$ the magnetic energy [4]:

$$\mathcal{E}_H \approx \alpha \mathcal{E}_{kin} \approx \alpha \frac{m_e v^2}{2}$$
 (12)

Where $\alpha = \frac{e^2}{hc}$ is the fine structure constant. Due to the fact that we are interested by the description of the behavior of electrons in metals, it is necessary to take into account that in this case, the electron mass may differ from the free electron mass value m_e .

Under critical conditions, electrons have a critical velocity v_c and the critical momentum $p_c = m_e v_c$.

According to quantum mechanics, the momentum of a particle is associated with the phase of the wave function of particle ϑ with the relation:

$$p = \hbar \nabla \vartheta. \tag{13}$$

We will assume that the condition for the condensate existence is the equation of phases of the wave functions at the boundaries of the region in which the particle is localized:

$$\lambda \nabla \vartheta = 2\pi. \tag{14}$$

Where

$$\lambda = n^{-1/3},\tag{15}$$

n is the pairs density into the condensate $(n_0 = \lambda_0^{-3})$ is the density at T = 0.

Under this assumption the condition of existence of the condensate would be consistent with the equality of the linear size of the volume in which the particle is localized, and its de Broglie wave:

$$p_c \lambda_0 = 2\pi\hbar. \tag{16}$$

1.3.2 The relationship between the critical parameters of a superconductor

From the last equalities we can receive relation between the boson energy and the localization length of its particles (at T = 0):

$$\Delta_0 = \alpha \frac{p_c^2}{2m_2} = \frac{\alpha}{2m_2} \left(\frac{2\pi\hbar}{\lambda_0}\right)^2.$$
 (17)



Figure 2: The comparison of the critical energy densities \mathcal{E}_T (Eq.(19)) and \mathcal{E}_H (Eq.(20)) for the type II superconductors.

Where $m_2 \approx 2m_e$ is the boson mass. Hence the particle density of the boson condensate at T = 0:

$$n_0 = \left(\frac{m_e}{\pi^2 \alpha \hbar^2} \Delta_0\right)^{3/2}.$$
 (18)

To convert the Bose-condensate into the normal state we must give its particles (in the unit of its volume) the energy \mathcal{E}_T . In view of Eq.(11):

$$\mathcal{E}_T \approx n_0 \langle \Delta_0 \rangle \approx 0.85 \left(\frac{m_e}{\pi^2 \alpha \hbar^2}\right)^{3/2} \Delta_0^{5/2},$$
 (19)

On the other hand, we can get the normal state of an electrically charged condensate at an applying of a magnetic field with the density of energy:

$$\mathcal{E}_H = \frac{H_c^2}{8\pi}.\tag{20}$$

At the equating \mathcal{E}_T and \mathcal{E}_H , we obtain:

$$\Delta_0 = \left(\frac{\alpha \pi^2 \hbar^2}{m_e}\right)^{3/5} \left(\frac{H_c^2}{0.85\ 8\pi}\right)^{2/5}.$$
(21)

The comparison of the critical energy densities \mathcal{E}_T and \mathcal{E}_H for type II superconductors are shown in Fig.(2). The obtained agreement between energies \mathcal{E}_T (Eq.(19)) and \mathcal{E}_H (Eq.(20)) can be considered as quite satisfactory for type

II superconductors [5],[6]. Especially at taking into account that, at the calculations we used the approximate value of the magnetic energy of the moving electron Eq.(12). A similar comparison of data for type-I superconductors gives the results differ in several times. The correction this calculation, apparently, has not make sense. The purpose of these calculations was to show that the description of superconductivity as the effect of the Bose-Einstein condensation is in accordance with the available experimental data. And this goal can be considered quite reached.

2 The critical temperature of superconductor and its electronic specific heat

3 The electron states density and specific heat

Let us consider the process of heating the electron gas in a superconductor. At a heating, the electrons from levels slightly below the Fermi-energy are raised to higher levels. As a result, the levels closest to the Fermi level, from which at low temperature electrons was forming bosons, become vacant.

At critical temperature T_c , all electrons from the levels of energy bands from $\mathcal{E}_F - \Delta$ to \mathcal{E}_F are moved to higher levels (and the gap collapses). At this temperature superconductivity is destroyed completely.

This band of energy can be filled by N_{Δ} particles:

$$N_{\Delta} = 2 \int_{\mathcal{E}_F - \Delta}^{\mathcal{E}_F} F(\mathcal{E}) D(\mathcal{E}) d\mathcal{E}.$$
 (22)

Where $F(\mathcal{E}) = \frac{1}{e^{\frac{\mathcal{E}-\mu}{\tau}}+1}$ is the Fermi-Dirac function, $D(\mathcal{E})$ is number of states per an unit energy interval, deuce front of the integral arises from the fact that there are two electron at each energy level.

To find the density of states $D(\mathcal{E})$, one needs to find the difference in energy of the system at T = 0 and finite temperature:

$$\Delta \mathcal{E} = \int_0^\infty F(\mathcal{E})\mathcal{E}D(\mathcal{E})d\mathcal{E} - \int_0^{\mathcal{E}_F} \mathcal{E}D(\mathcal{E})d\mathcal{E}.$$
 (23)

After calculations [3], the electron level density can be expressed through the Fermi-energy:

$$D(E_F) = \frac{dn_e}{d\mathcal{E}_F} = \frac{3n_e}{2\mathcal{E}_F} = \frac{3\gamma}{k^2\pi^2},\tag{24}$$

where

$$\gamma = \frac{\pi^2 k^2 n_e}{2\mathcal{E}_F} \tag{25}$$

is the Sommerfeld constant.

To consider the interaction in the electron gas, it is commonly accepted to establish an effective electron mass m_{\star} , and to record the Fermi energy in the form

$$\mathcal{E}_F = (3\pi^2)^{2/3} \frac{\hbar^2}{2m_\star} n_e^{2/3}.$$
 (26)

In this case the Sommerfeld constant:

$$\gamma = \left(\frac{\pi}{3}\right)^{3/2} \left(\frac{k}{\hbar}\right)^2 m_\star n_e^{1/3} \tag{27}$$

and thus

$$\mathcal{E}_F \simeq \left(\frac{3\hbar^3\gamma}{2^{1/2}k^2m_\star^{3/2}}\right)^2. \tag{28}$$

Following such arguments, we can find the number of electrons, which populate the levels in the range from $\mathcal{E}_F - \Delta$ to \mathcal{E}_F . For an unit volume of substance Eq.(22) can be rewritten as:

$$n_{\Delta} = 2kT \cdot D(\mathcal{E}_F) \int_{-\frac{\Delta_0}{kT_c}}^0 \frac{dx}{(e^x + 1)}.$$
 (29)

At taking into account that for superconductors $\frac{\Delta_0}{kT_c} = 1.76$, as a result of numerical integration we obtain

$$\int_{-\frac{\Delta_0}{kT_c}}^{0} \frac{dx}{(e^x + 1)} = \left[x - \ln(e^x + 1)\right]_{-1.76}^{0} \approx 1.22.$$
(30)

Thus, the density of electrons, which throw up above the Fermi level in a metal at temperature $T = T_c$ is

$$n_e(T_c) \approx 2.44 \left(\frac{3\gamma}{k^2 \pi^2}\right) k T_c.$$
(31)

Where the Sommerfeld constant γ is related to the volume unit of the metal.²

4 The Sommerfeld constant and critical temperature superconductors

4.1 The type-I superconductors

The values of the Sommerfeld constant, calculated for the free electron gas Eq.(27), can be considered as consistent on order of magnitude with the experimentally measured values for metals, which are type-I superconductors (see Table (4.1.1)).

 $^{^2 {\}rm The}$ values of the electronic specific heat of superconductors of type I recalculated to the volume unit are shown in the middle column Tab.(4.1.4).

Table (4.1.1).

superconductor	$\gamma_{calc}/\gamma_{measured}$
Cd	1.34
Zn	1.11
Ga	1.65
Al	0.66
Tl	0.87
In	0.72
Sn	0.77
Hg	0.54
Pb	0.47

Therefore, in a rough approximation, the effective mass of the electron in these metals can be considered approximately equal to the free electron mass:

$$\frac{m_{\star}}{m_e} \approx 1. \tag{32}$$

This is a consequence of the fact that all metals - type-I superconductors - have completely filled inner shells (see. Table(4.1.2)).

Table (4.1.2).

superconductors	electron shells
Al	$2d^{10} \ 3s^2 \ 3p^1$
Zn	$3d^{10} \ 4s^2$
Ga	$3d^{10} \ 4s^2 \ 4p^1$
Cd	$4d^{10} 5s^2$
In	$4d^{10} 5s^2 5p^1$
Sn	$4d^{10} 5s^2 5p^2$
Hg	$5d^{10} \ 6s^2$
Tl	$5d^{10} \ 6s^2 \ 6p^1$
Pb	$5d^{10} \ 6s^2 \ 6p^2$

For this reason, the electrons from the inner shells should not affect the process of thermal excitation of free electrons and their movement.

These calculations make it possible to link directly the critical temperature superconductor with the experimentally measurable parameter of a solid-state - its electronic specific heat.

The density of superconducting carriers at T = 0 has been calculated earlier (Eq.(18)).

The comparison of the values n_0 and $n_e(T_c)$ is given in the Table (4.1.3) in Fig.(3). (The necessary data for superconductors are taken from the tables [5], [6]).

Table (4.1.3).



Figure 3: The comparison of the number of superconducting carriers at T = 0 with the number of thermally activated electrons at $T = T_c$.

superconductor	n_0	$n_e(T_c)$	$2n_0/n_e(T_c)$
Cd	$6.11 \cdot 10^{17}$	$1.48 \cdot 10^{18}$	0.83
Zn	$1.29 \cdot 10^{18}$	$3.28\cdot10^{18}$	0.78
${ m Ga}$	$1.85 \cdot 10^{18}$	$2.96\cdot 10^{18}$	1.25
Al	$2.09\cdot 10^{18}$	$8.53\cdot10^{18}$	0.49
Tl	$6.03\cdot10^{18}$	$1.09\cdot 10^{19}$	1.10
In	$1.03\cdot 10^{19}$	$1.94\cdot 10^{19}$	1.06
Sn	$1.18\cdot 10^{19}$	$2.14\cdot10^{19}$	1.10
Hg	$1.39\cdot 10^{19}$	$2.86\cdot10^{19}$	0.97
Pb	$3.17\cdot 10^{19}$	$6.58\cdot10^{19}$	0.96

From the data obtained above, one can see that the condition of destruction of superconductivity after heating for superconductors of type I can really be written as the equation:

$$n_e(T_c) = 2n_0 \tag{33}$$

Eq.(33) gives us the possibility to express the critical temperature of the superconductor through its Sommerfeld constant :

$$\Delta_0 \simeq C \gamma^2, \tag{34}$$

where the constant

$$C \simeq 35 \frac{\pi^2}{k} \left[\frac{\alpha \hbar^2}{k m_e} \right]^3 \approx 6.5 \cdot 10^{-22} \frac{K^4 cm^6}{erg}.$$
 (35)



Figure 4: The comparison of the calculated values of critical temperature superconductors with measurement data. On abscissa the measured values of the critical temperature superconductors of type I are shown, on the vertical axis the function $C\gamma^2$ defined by Eq.(34) is shown.

or at Eq.(28),

$$\Delta_0 \simeq 8\pi^2 \alpha^3 \mathcal{E}_F. \tag{36}$$

The comparison of the temperature calculated by Eq.(34) (corresponding to complete evaporation of electrons with energies in the range from $\mathcal{E}_F - \Delta_0$ up to \mathcal{E}_F) and the experimentally measured critical temperature superconductors is given in Table (4.1.4) and in Fig.(4).

superconductors	T_c (measur),K	$\gamma, \frac{erg}{cm^3K^2}$	$T_c(\text{calc}), \mathbf{K}$	$\frac{T_c(calc)}{T_c(meas)}$
			Eq.(34)	. ,
Cd	0.517	532	0.77	1.49
Zn	0.85	718	1.41	1.65
${ m Ga}$	1.09	508	0.70	0.65
Tl	2.39	855	1.99	0.84
In	3.41	1062	3.08	0.90
Sn	3.72	1070	3.12	0.84
Hg	4.15	1280	4.48	1.07
Pb	7.19	1699	7.88	1.09

Table (4.1.4).

4.2 The estimation of properties of type-II superconductors

The situation is different in the case of type-II superconductors.

In this case the measurements show that these metals have the electronic specific heat on an order of magnitude greater than the calculations based on free electron gas give.

The peculiarity of these metals associated with the specific structure of their ions. They are transition metals with unfilled inner d-shell (see Table4.2).

It can be assumed that this increasing of the electronic specific heat of these metals should be associated with a characteristic interaction of free electrons with the electrons of the unfilled d-shell.

superconductors	electron shells
Ti	$3d^2 \ 4s^2$
V	$3d^3 \ 4s^2$
Zr	$4d^2 5s^2$
Nb	$4d^3 5s^2$
Mo	$4d^4 5s^2$
Tc	$4d^{5} 5s^{2}$
Ru	$4d^{6} 5s^{2}$
La	$5d^{1} 6s^{2}$
Hf	$5d^2 \ 6s^2$
Ta	$5d^3 \ 6s^2$
W	$5d^4 \ 6s^2$
Re	$5d^{5} 6s^{2}$
Os	$5d^{6} 6s^{2}$
Ir	$5d^{7} 6s^{2}$

Table (4.2)

An electron of conductivity at the moving with velocity **v** has the kinetic energy

$$\mathcal{E}_k = \frac{m_e v^2}{2}.\tag{37}$$

In a contact with d-electron shell, the electron of conductivity creates on it a magnetic field

$$H \approx \frac{e}{r_c^2} \frac{v}{c}.$$
 (38)

The magnetic moment of d-electron is approximately equal to the Bohr magneton, so the energy of their interaction will be approximately equal to:

$$\mathcal{E}_{\mu} \approx \frac{e^2}{2r_c} \frac{v}{c}.$$
(39)

This leads to the fact that an electron of conductivity with its movement would be to spend energy on the orientation of the magnetic moments of d-electrons. It should increase its effective mass to:

$$m_{\star} \approx m_e \left(1 + \frac{\mathcal{E}_{\mu}}{\mathcal{E}_k} \right) \approx m_e \frac{\mathcal{E}_{\mu}}{\mathcal{E}_k}.$$
 (40)

Thus, the electronic specific heat in the transition metals should be composed from two parts. The first term - the same as in type-I superconductors. It is the heating of collectivized electrons - the increasing of their kinetic energy. The second term is associated with the excitation of additional potential energy of the moving collectivized electron, i.e. interaction with the magnetic moments of electrons unfilled d-shell. ³

The interaction with d-electrons increases the effective mass of free electrons. Therefore, in considering this process should take into account the factor:

$$\frac{\mathcal{E}_k}{\mathcal{E}_\mu + \mathcal{E}_k} \approx \frac{1}{\alpha^{3/2}} \sqrt{\frac{2\Delta_0}{m_e c^2}}.$$
(41)

At taking into account the effective mass of electron instead Eq.(36) for the type II superconductors we become

$$\Delta_0 \simeq 8\pi^2 \alpha^3 \mathcal{E}_F \left(\frac{\mathcal{E}_k}{\mathcal{E}_\mu + \mathcal{E}_k}\right) \tag{42}$$

or

$$\Delta_0 \simeq C\gamma^2 \left(\frac{\mathcal{E}_k}{\mathcal{E}_\mu + \mathcal{E}_k}\right) \simeq \frac{2}{m_e c^2} \left(\frac{6\pi \alpha^{3/4} \hbar^3}{k^2 m_e^{3/2}}\right)^4 \gamma^4.$$
(43)

The comparing of the results of these calculations with the measurement data (Fig.(5)) shows that for the majority of type II superconductors the estimation Eq.(43) can be considered quite satisfactory.

4.3 Alloys and high-temperature superconductors

To understand the mechanism of high temperature superconductivity is important to establish whether the high-Tc ceramics are the I or II type superconductors, or they are a special class of superconductors.

To address this issue, you can use the established relation of critical parameters with the electronic specific heat and the fact that the specific heat of superconductors I and II types are differing considerably, because in the I type superconductors the energy of heating spends to increase the kinetic energy of the electron gas, while in the type II superconductors it is spending additionally on the polarization of electrons of the unfilled d-shell.

There are some difficulty on this way - one d'not known confidently the Fermi-energy and the density of the electron gas in high-temperature superconductors. However, the density of atoms in metal crystals does not differ too much. It facilitates the solution of the problem of a distinguishing of I and II types superconductors at using of Eq.(34).

³Although estimates show that the second mechanism is stronger, to see its work is not simple. Only at temperature below 0.5K, this mechanism leads to the square-root dependence of electronic specific heat on temperature: $c_{el} \sim \sqrt{T}$. But simulation shows that at higher temperature the Debye cubic lattice term will mask it, and the total heat capacity dependence of transition metals are similar to the linear in T.



Figure 5: The comparison of the calculated values of critical temperatures for type II superconductors (Eq.(43)) with measurement data.

For the I type superconductors at using this equation we get the quite satisfactory estimation of the critical temperature (as was done above (see Fig.(4)). For the type-II superconductors this assessment gives overestimated value due to the fact that their specific heat has additional term associated with the polarization of d-electrons.

Indeed, such analysis gives possibility to share all of superconductors into two groups, as is evident from the figure (6).

It is generally assumed to consider alloys Nb_3Sn and V_3Si as the type-II superconductors. The fact seems quite normal that they are placed in close surroundings of Nb. Some excess of the calculated critical temperature over the experimentally measured value for ceramics $Ta_2Ba_2Ca_2Cu_3O_{10}$ can be attributed to the fact that the measured heat capacity may make other conductive electrons, but nonsuperconducting elements (layers) of ceramics. It is not a news that it, as well as ceramics $YBa_2Cu_3O_7$, belongs to the type II superconductors. However, ceramic $(LaSr)_2CuO_4$ and $Bi_2Sr_2CaCu_2O_x$, according to this figure should be regarded as type-I superconductors, which is somewhat unexpected.

5 Conclusion

The above analysis shows that the critical temperature of the superconductor is related to the Sommerfeld constant and for type-I superconductors the critical temperature is proportional to the first degree of its Fermi energy. Estimates for Figure 6: The comparison of the calculated parameter $C\gamma^2$ with the measurement critical temperatures of elementary superconductors and some superconducting compounds.

type II superconductors lead to a quadratic dependence of the critical temperature of the Fermi energy, but the relationship of the critical temperature and critical field is the same for different types of superconductors [7]. While the above analysis does not detect any effect of electron-phonon interaction on the phenomenon of superconductivity. That and the fact that the superconductivity in metals should be considered as a phenomenon of Bose-Einstein condensation in a system of electron gas indicate that superconductivity is the effect of electronic interactions. In our opinion, for the phenomenon of superconductivity should be responsible ordering zero-point oscillations in the metal electron gas [7].

References

- [1] Chervonko E.: Acta Phys. Pol.**32**, n.3, p.335-358 (1967)
- [2] Landau L.D. and Lifshits E.M.: Statistical Physics, 1, 3rd edition, Oxford:Pergamon, (1980)
- [3] Kittel Ch. : Introduction to Solid State Physics, Wiley (2005)
- [4] Abragam-Becker : Teorie der Elektizität, Band 1, Leupzig-Berlin, (1932)
- [5] Pool Ch.P.Jr : Handbook of Superconductivity, Academic Press, (2000)
- [6] Ketterson J.B., Song S.N. Superconductivity, CUP, (1999)
- [7] Vasiliev B.V. ArXiv 1008.2691