

Common Signal Analysis

Chengpu Wang Independent researcher 631-974-1078 Chengpu@gmail.com

1 Abstract

A common signal is defined for any two signals which have non-zero correlation. A mathematical method is provided to extract the best obtainable common signal between the two signals. This analysis is extended to extracting common signal among three signals.

2 Introduction

When two signals have non-zero correlation [1], it is commonly believed that these two signals have similarity between them. However, so far there is no clear definition about what the similarity actually means. This paper defines the similarity as common signal between the two signals, and provides a mathematical way to extract it.

3 Common Signal Analysis between Two Signals

3.1 Definition of Common Signal

Let α be a constant. Let $\sigma^2()$, $\text{Cov}()$ and $\gamma()$ be variance, covariance and correlation functions. Assume A , B_1 , and B_2 are three mutually independent random variables. Define

$\beta_1^2 \equiv \frac{\sigma^2(B_1)}{\sigma^2(A)}$ and $\beta_2^2 \equiv \frac{\sigma^2(B_2)}{\sigma^2(\alpha A)} = \frac{\sigma^2(B_2)}{\alpha^2 \sigma^2(A)}$. Define $\sigma^2 \equiv \sigma^2(A)$. Define sgn as sign of value x .

Equation 3-3 [2] gives the correlation γ_{12} between two signals $S_1 \equiv A + B_1$ and $S_2 \equiv \alpha A + B_2$.

Equation 3-1: $\sigma_1^2 \equiv \sigma^2(S_1) = \sigma^2(A + B_1) = (1 + \beta_1^2)\sigma^2;$

Equation 3-2: $\sigma_2^2 \equiv \sigma^2(S_2) = \sigma^2(\alpha A + B_2) = (1 + \beta_2^2)\alpha^2 \sigma^2;$

Common Signal Analysis

$$\text{Equation 3-3: } \gamma_{12} = \frac{\text{Cov}(S_1, S_2)}{\sigma_1 \sigma_2} = \frac{\alpha \sigma^2}{\sigma_1 \sigma_2} = \frac{\$ \alpha}{\sqrt{1 + \beta_1^2} \sqrt{1 + \beta_2^2}} ;$$

Equation 3-3 can also be interpreted reversely: if two signals S_1 and S_2 are correlated by a non-zero γ_{12} , each signal can be viewed as containing a completely uncorrelated part and a completely correlated part. The completely correlated part is defined as the common signal between the two signals S_1 and S_2 . In this context, α measures relative strength of the common signal between S_1 and S_2 , while β_1 and β_2 measure the background strength within S_1 and S_2 respectively. The question is how to extract the common signal.

3.2 Best Obtainable Common Signal

The correlation between A and S_1 or S_2 are γ_1 or γ_2 respectively.

$$\text{Equation 3-4: } \gamma_1 \equiv \frac{\text{Cov}(S_1, A)}{\sigma_1 \sigma} = \frac{\sigma}{\sigma_1} = \sqrt{\frac{1}{1 + \beta_1^2}} ;$$

$$\text{Equation 3-5: } \gamma_2 \equiv \frac{\text{Cov}(S_2, A)}{\sigma_2 \sigma} = \frac{\alpha \sigma}{\sigma_2} = \$ \alpha \sqrt{\frac{1}{1 + \beta_2^2}} = \frac{\gamma_{12}}{\gamma_1} ;$$

Compose a new signal $S_- \equiv \alpha S_1 - S_2 = \alpha B_1 - B_2$, which contains no common signal A . Compose another new signal $S_a \equiv S_1 - \chi_1 S_-$ and choose χ_1 to maximize the correlation γ_a between A and S_a . The optimal result χ_1 , γ_a and S_a are shown by Equation 3-7.

$$\text{Equation 3-6: } 1/\gamma_a^2 \equiv \frac{\sigma^2(S_a)\sigma^2(A)}{\text{Cov}(S_a, A)^2} = 1 + (1 - \alpha\chi_1)^2 \beta_1^2 + \alpha^2 \chi_1^2 \beta_2^2 ;$$

$$\text{Equation 3-7: } \chi_1 = \frac{\beta_1^2}{\beta_1^2 + \beta_2^2} \frac{1}{\alpha} ;$$

$$\gamma_a^2 = \gamma_{best}^2 \equiv \frac{\beta_1^2 + \beta_2^2}{\beta_1^2 + \beta_2^2 + \beta_1^2 \beta_2^2} \geq \gamma_1^2, \gamma_2^2 \quad S_a = S_{best} \equiv \frac{\beta_2^2 S_1 + \beta_1^2 S_2 / \alpha}{\beta_1^2 + \beta_2^2} ;$$

S_{best} can also be shown to have minimal correlation with S_- .

Common Signal Analysis

Similarly, compose a new signal $S_b \equiv S_2 + \chi_2 S_-$ and choose χ_2 to maximize the correlation γ_b between X and S_b . The optimal result χ_1 and S_a are shown by shown by Equation 3-9.

$$\text{Equation 3-8: } 1/\gamma_b^2 \equiv \frac{\sigma^2(S_b)\sigma^2(X)}{\text{Cov}(S_b, X)^2} = 1 + \chi_2^2 \beta_1^2 + (1 - \chi_2)^2 \beta_2^2 ;$$

$$\text{Equation 3-9: } \chi_2 = \frac{\beta_2^2}{\beta_1^2 + \beta_2^2} ; \quad \gamma_b = \gamma_{best} \quad S_b = \alpha S_{best} ;$$

Because the optimal S_a and S_b are completely correlated, they are the best obtainable common signals between the two correlated signals S_1 and S_2 in terms of a linear combination of S_1 and S_2 .

3.3 Common Signal Extraction

In addition to S_1 and S_2 , only γ_{12} , σ_1 and σ_2 are measurable. $\gamma_1 = \sigma/\sigma_1$ is used as an indeterminate variable whose range is $[|\gamma_{12}|, 1]$. α , β_1 and β_2 can be expressed using γ_1 , γ_{12} , σ_1 and σ_2 so that Equation 3-7 is translated into Equation 3-10 and Equation 3-11. To accommodate when S_1 and S_2 may not be directly comparable, Equation 3-11 is in the format of analyzing two unit-less signal S_1/σ_1 and S_2/σ_2 , with result S_{best} in the unit of S_1 .

$$\text{Equation 3-10: } \gamma_{best}^2 = \frac{\gamma_{12}^2 - 2\gamma_1^2 \gamma_{12}^2 + \gamma_1^4}{\gamma_1^2 (1 - \gamma_{12}^2)} ;$$

$$\text{Equation 3-11: } \frac{S_{best}}{\sigma_1} = \frac{\frac{S_1}{\sigma_1} \gamma_1^2 (\gamma_1^2 - \gamma_{12}^2) + \frac{S_2}{\sigma_2} \gamma_{12} \gamma_1^2 (1 - \gamma_1^2)}{\gamma_1^2 (1 - \gamma_{12}^2) + \gamma_{12}^2 (1 - \gamma_1^2)} ;$$

Additional condition is required to find the best obtainable common signal, such as a prior knowledge of either γ_1 or γ_2 , or σ in unit of either S_1 or S_2 , or α , or the ratio between β_1^2 and β_2^2 . For example, when $\sigma = \sigma_1$, $\gamma_1 = 1$, $\gamma_2 = \gamma_{12}$, $\gamma_{best} = 1$ and $S_{best} = S_1$. If there is prior knowledge of characteristics of the common signal instead, a series of S_{best} can be generated for different γ_1 , and the selected S_{best} determines γ_1 . If there is no ground to judge which of S_1 and S_2 contains

Common Signal Analysis

more common signal, assume $\gamma_1 = \gamma_2$, and the solution is Equation 3-12. Equation 3-12 is also the solution for minimizing γ_{best}^2 , when the uncertainty of γ_1 has least effect on the result.

$$\text{Equation 3-12: } |\gamma_1| = |\gamma_2| = \sqrt{|\gamma_{12}|} \leq \gamma_{best} = \sqrt{\frac{2|\gamma_{12}|}{|\gamma_{12}|+1}} : \frac{S_{best}}{\sigma_1} = \frac{1}{2} \left(\frac{S_1}{\sigma_1} + \gamma_{12} \frac{S_2}{\sigma_2} \right);$$

In Equation 3-12 S_{best} is a surprisingly simple weighted average of S_1 and S_2 . It can be explained well in two extreme cases when S_1 and S_2 are directly comparable:

- When signal strengths are same, S_{best} gives heavier weight for signal which has less background strength.
- When background strengths are same, S_{best} scales S_1 and S_2 according to their signal strengths.

3.4 Validation

A sine waveform is chosen to be the common signal A. A cosine waveform of twice the periodicity of A is chosen to be B_1 , which is the background for signal S_1 . A white noise is chosen to be B_2 , which is the background for signal S_2 . The white noise B_2 tends to have small but non-zero correlation with either the common signal A or the background B_1 , and it is one of the major source when the result is deviate from ideal behavior. Equation 3-12 is used to extract γ_{best} and S_{best} regardless what α , β_1 and β_2 are used to generate the signals. Table 1 shows that the correlation γ_{best} to the true common signal A of S_{best} in most case is better than the corresponding values γ_1 and γ_2 . Figure 1 shows one of the exceptional case in which γ_{best} is worse than γ_1 , when $\alpha = 2$, $\beta_1 = 0.5$, $\beta_2 = 2$. It shows that contrary to smaller γ_{best} , S_{best} is visually close to A than S_1 , e.g., no more double positive peaks, and smaller negative peaks. It is observed that S_{best} generally has better or at least comparable visual correlation to the true common signal A than S_1 or S_2 .

4 Common Signal Analysis among Three Signals

4.1 Ideal Extraction

For each signal, assume $j=1,2,3$, B_j is the background, σ_j is the deviation, α_j is the signal strength, and β_j is the background strength. Let $\alpha_1 = 1$. Assume A is the common signal, so that by definition $\text{Cov}(A, B_j) = 0$

$$\text{Equation 4-1: } \sigma_j^2 \equiv \sigma^2(S_j) = \sigma^2(\alpha_j A + B_j) = (1 + \beta_j^2) \alpha_j^2 \sigma^2 ;$$

$$\text{Equation 4-2: } \gamma_j \equiv \frac{\text{Cov}(S_j, A)}{\sigma_j \sigma} = \frac{\alpha_j \sigma}{\sigma_j} = \alpha_j \sqrt{\frac{1}{1 + \beta_j^2}} ;$$

Three signals can be composed according to Equation 4-3, each of which contains no common signal. However, only two of them are independent. So the signal S_a to be optimized for highest correlation with common signal A is given by Equation 4-4 and simplified as Equation 4-5.

$$\text{Equation 4-3: } N_{12} \equiv \alpha_2 S_1 - \alpha_1 S_2 ; \quad N_{13} \equiv \alpha_3 S_1 - \alpha_1 S_3 ; \quad N_{23} \equiv \alpha_3 S_2 - \alpha_2 S_3 ;$$

$$\text{Equation 4-4: } S_a \equiv S_1 - \chi_2 N_{12} - \chi_3 N_{13} = (\alpha_1 - \chi_2 \alpha_2 - \chi_3 \alpha_3) S_1 + \chi_2 S_2 + \chi_3 S_3 ;$$

$$\text{Equation 4-5: } S_a = A + (\alpha_1 - \chi_2 \alpha_2 - \chi_3 \alpha_3) B_1 + \chi_2 B_2 + \chi_3 B_3 ;$$

Using assumption of Equation 4-6, Equation 4-9 and Equation 4-10 show that both signal strength set $\{\alpha_2, \alpha_3\}$ and background strength set $\{\beta_1^2, \beta_2^2, \beta_3^2\}$ are completely solved by the correlation set $\{\gamma_{12}, \gamma_{13}, \gamma_{23}\}$ (which is given by Equation 4-7) when Equation 4-8 is satisfied.

$$\text{Equation 4-6: } i \neq j : \quad \text{Cov}(B_i, B_j) = 0 ;$$

$$\text{Equation 4-7: } i \neq j : \quad \gamma_{ij} = \frac{\text{Cov}(S_i, S_j)}{\sigma_i \sigma_j} = \frac{\alpha_i \alpha_j}{\sqrt{1 + \beta_i^2} \sqrt{1 + \beta_j^2}} ;$$

$$\text{Equation 4-8: } \gamma_1^2 = \left| \frac{\gamma_{12} \gamma_{13}}{\gamma_{23}} \right| \leq 1 ; \quad \gamma_2^2 = \left| \frac{\gamma_{12} \gamma_{23}}{\gamma_{13}} \right| \leq 1 ; \quad \gamma_3^2 = \left| \frac{\gamma_{13} \gamma_{23}}{\gamma_{12}} \right| \leq 1 ;$$

Common Signal Analysis

Equation 4-9:
$$\beta_j^2 = \frac{1}{\gamma_j^2} - 1;$$

Equation 4-10:
$$\alpha_2 = \gamma_{12} \left| \frac{\gamma_2 \sigma_2}{\gamma_1 \sigma_1} \right|; \quad \alpha_3 = \gamma_{13} \left| \frac{\gamma_3 \sigma_3}{\gamma_1 \sigma_1} \right|;$$

The optimal signal and its correlation to the common signal A are provided by Equation 4-11 and Equation 4-12.

Equation 4-11:
$$S_{best} \equiv \frac{\beta_2^2 \beta_3^2 S_1 / \alpha_1 + \beta_1^2 \beta_3^2 S_2 / \alpha_2 + \beta_1^2 \beta_2^2 S_3 / \alpha_3}{\beta_1^2 \beta_2^2 + \beta_1^2 \beta_3^2 + \beta_2^2 \beta_3^2};$$

Equation 4-12:
$$\gamma_{best}^2 \equiv 1 - \frac{\beta_1^2 \beta_2^2 \beta_3^2}{\beta_1^2 \beta_2^2 + \beta_1^2 \beta_3^2 + \beta_2^2 \beta_3^2 + \beta_1^2 \beta_2^2 \beta_3^2} \geq \gamma_1^2, \gamma_2^2, \gamma_3^2;$$

Like in the two-signal case, other optimized constructions of linear combination of S_1 , S_2 and S_3 also result in Equation 4-11 and Equation 4-12, which are symmetric for each signal in the set.

When Equation 4-8 is satisfied, all correlations can be attributed to the common signal among three signals, and there is a unique and determinate solution for the best obtainable common signal S_{best} among signal set $\{S_1, S_2, S_3\}$.

4.2 Non-Ideal Extraction

When Equation 4-8 cannot be satisfied, Equation 4-6 can not be satisfied either, and each γ_{ij} corresponds to an indeterminate variable $Cov(B_i, B_j)$. There are three more measurements $\{\sigma_1, \sigma_2, \sigma_3\}$, but five more indeterminate variables $\{\alpha_2, \alpha_3\}$ and $\{\beta_1^2, \beta_2^2, \beta_3^2\}$. In addition, $\{B_1, B_2, B_3\}$ set as a whole shall not contribute to the extracted common signal. How to translate the last requirement into mathematical formula is not clear at the moment. It is even possible that no common signal exists for the set, and a new standard is required to judge for this condition.

For a set of N signals, if Equation 4-6 still holds, then there will be $N(N-1)/2$ count of Equation 4-7 but only N count of β_j , so that $\{\beta_j\}$ set is over-determinate. Thus Equation 4-6 can

not be satisfied generally when $N > 3$, and non-ideal extraction is needed for obtaining common signal from the signal set.

5 Summary and Discussion

The common signal is defined between two signals which have non-zero correlation. It is also defined among three signals whose correlations satisfy Equation 4-8. When it is defined, it can be approached by the best obtainable common signal, which is an optimal linear combination of the original signal set. The best obtainable common signal is under-determinate for the two signal set, and ideally determinate for the three signal set.

The common signal has not been well defined in other cases. If common signal is an intrinsic property of the signal set in these cases, the best obtainable common signal should not depend on the sequence of extracting it. Perhaps a common signal can be defined and extracted using this principle in non-ideal cases.

Applying ideal extraction repeatedly may obtain the common signal among a set of 3^n signals under ideal conditions. Another approach when $N > 3$ is to see if the $N(N-1)/2$ count of Equation 4-7 degenerate into N independent equations using solutions similar to Equation 4-8, Equation 4-9 and Equation 4-10 which are obtained from a subset of Equation 4-7. If so, ideal extraction may be still possible.

6 Reference

- [1] Michael J. Evans and Jeffrey S. Rosenthal, Probability and Statistics: The Science of Uncertainty (W. H. Freeman 2003)
- [2] Chengpu Wang, Precision Arithmetic, <http://arxiv.org/abs/cs/0606103>, 2007.
- [3] John R. Taylor, Introduction to Error Analysis: The Study of Output precisions in Physical Measurements (University Science Books, 1997)

7 Tables and Figures

α	β_1	β_2	γ_1	γ_2	γ_{best}
2	1	1	0.7071	0.7652	0.8119
2	0.5	0.5	0.8944	0.9218	0.9393
2	2	2	0.4472	0.5106	0.5773
2	0.5	2	0.8944	0.5106	0.8936
2	2	0.5	0.4472	0.9218	0.8131
1	2	0.5	0.4472	0.9218	0.8852

Table 1: γ_{best} vs. γ_1 and γ_2 for different α , β_1 and β_2 .




Figure 1: The true and best obtainable common signals vs. the original signals.