

Operads of Wiring Diagrams

Donald Yau

THE OHIO STATE UNIVERSITY AT NEWARK, NEWARK, OH, USA

E-mail address: `yau.22@osu.edu`

Key words and phrases. Wiring diagrams, undirected wiring diagrams, operads, colored operads, operad algebras, finite presentation, propagator algebra, discrete systems, open dynamical systems, relational algebra.

ABSTRACT. Wiring diagrams and undirected wiring diagrams are graphical languages for describing interconnected processes and their compositions. These objects have enormous potentials for applications in many different disciplines, including computer science, cognitive neuroscience, dynamical systems, network theory, and circuit diagrams. It is known that the collection of wiring diagrams is an operad and likewise for undirected wiring diagrams.

This monograph is a comprehensive study of the combinatorial structure of various operads of wiring diagrams and undirected wiring diagrams. Our first main objective is to prove a finite presentation theorem for each operad of wiring diagrams, describing each one in terms of just a few operadic generators and a small number of generating relations. For example, the operad of wiring diagrams has 8 generators and 28 generating relations, while the operad of undirected wiring diagrams has 6 generators and 17 generating relations.

Our second main objective is to prove a corresponding finite presentation theorem for algebras over each operad of wiring diagrams. As applications we provide finite presentations for the propagator algebra, the algebra of discrete systems, the algebra of open dynamical systems, and the (typed) relational algebra. We also provide a partial verification of Spivak's conjecture regarding the quotient-freeness of the relational algebra.

Our third main objective is to construct explicit operad maps among the several operads of wiring diagrams. In particular, there is a surjective operad map from the operad of all wiring diagrams, including delay nodes, to the operad of undirected wiring diagrams.

This monograph is intended for graduate students, mathematicians, scientists, and engineers interested in operads and wiring diagrams. Assuming no prior knowledge of categories, operads, and wiring diagrams, this monograph is self-contained and can be used as a supplement in a graduate course and for independent study. There are over 100 graphical illustrations and a final chapter with a list of problems.

Contents

List of Notations	xi
Chapter 1. Introduction	1
§1.1. What are Wiring Diagrams?	1
§1.2. Purposes of this Monograph	3
§1.3. Audience and Features	5
§1.4. Chapter Summaries	6
Part 1. Wiring Diagrams	
Chapter 2. Wiring Diagrams	13
§2.1. Colored Operads	13
§2.2. Defining Wiring Diagrams	19
§2.3. Operad Structure	25
Chapter 3. Generators and Relations	33
§3.1. Generating Wiring Diagrams	34
§3.2. Internal Wasted Wires	38
§3.3. Elementary Relations	40
Chapter 4. Decomposition of Wiring Diagrams	55
§4.1. Factoring Wiring Diagrams	56
§4.2. Unary Wiring Diagrams	61
§4.3. Unary Wiring Diagrams with No Loop Elements	65
Chapter 5. Finite Presentation	79

§5.1. Stratified Presentation	80
§5.2. Finite Presentation for Wiring Diagrams	83
§5.3. Finite Presentation for Normal Wiring Diagrams	89
§5.4. Finite Presentation for Strict Wiring Diagrams	91
Chapter 6. Finite Presentation for Algebras over Wiring Diagrams	95
§6.1. Operad Algebras	96
§6.2. Algebras over the Operad of Wiring Diagrams	98
§6.3. Finite Presentation for the Propagator Algebra	107
§6.4. Algebras over the Operad of Normal Wiring Diagrams	118
§6.5. Finite Presentation for the Algebra of Discrete Systems	119
§6.6. Algebras over the Operad of Strict Wiring Diagrams	122
§6.7. Finite Presentation for the Algebra of Open Dynamical Systems	123
Part 2. Undirected Wiring Diagrams	
Chapter 7. Undirected Wiring Diagrams	131
§7.1. Defining Undirected Wiring Diagrams	131
§7.2. Pushouts	135
§7.3. Operad Structure	137
Chapter 8. Generators and Relations	145
§8.1. Generating Undirected Wiring Diagrams	146
§8.2. Elementary Relations	148
§8.3. Wasted Cables	156
Chapter 9. Decomposition of Undirected Wiring Diagrams	161
§9.1. A Sample Decomposition	161
§9.2. Factoring Undirected Wiring Diagrams	166
§9.3. The Inner Undirected Wiring Diagram	167
§9.4. The Outer Undirected Wiring Diagram	170
§9.5. Iterated Splits	173
§9.6. Iterated Loops	176
Chapter 10. Finite Presentation for Undirected Wiring Diagrams	179
§10.1. Stratified Presentation	180
§10.2. Elementary Equivalences	182
Chapter 11. Algebras of Undirected Wiring Diagrams	189
§11.1. Finite Presentation for Algebras	190

§11.2. Finite Presentation for the Relational Algebra	197
§11.3. Spivak's Conjecture: Rigidity of the Relational Algebra	200
§11.4. Finite Presentation for the Typed Relational Algebra	203
Part 3. Maps Between Operads of Wiring Diagrams	
Chapter 12. Map from Normal to Undirected Wiring Diagrams	209
§12.1. Operad Maps	210
§12.2. Normal to Undirected Wiring Diagrams	213
§12.3. Examples of the Operad Map	219
§12.4. Image of the Operad Map	223
§12.5. Map from Strict to Undirected Wiring Diagrams	228
Chapter 13. Map from Wiring Diagrams to Undirected Wiring Diagrams	233
§13.1. Wiring Diagrams to Undirected Wiring Diagrams	234
§13.2. Examples of the Operad Map	240
§13.3. Surjectivity of the Operad Map	242
Chapter 14. Problems	249
Bibliography	253
Index	255

List of Notations

	Notation	Page	Description
Ch. 2	S	13	a class
	$\text{Prof}(S)$	14	the collection of S -profiles
	$\underline{s} = (s_1, \dots, s_n)$	14	an S -profile of length n
	$\text{Prof}^{\geq n}(S)$	14	S -profiles of length at least n
	Σ_n	14	the symmetric group on n letters
	$(O, \mathbb{1}, \gamma)$	14	an S -colored operad
	$O_{\underline{c}}^{(d)}$	14	the $\binom{d}{\underline{c}}$ -entry of O
	$\underline{c}\sigma$	14	the right permutation of \underline{c} by σ
	$\mathbb{1}_c$	14	the c -colored unit
	γ	14	operadic composition
	$\sigma\langle k_1, \dots, k_n \rangle$	16	block permutation
	$\tau_1 \oplus \dots \oplus \tau_n$	16	block sum
	$(O, \mathbb{1}, \circ)$	17	an S -colored operad
	\circ_i	17	\circ_i -composition in an operad
	$\sigma \circ_i \tau$	18	\circ_i -composition of permutations
	Fin	20	the category of finite sets and functions
	Fin_S	20	the category of S -finite sets
	$(X^{\text{in}}, X^{\text{out}})$	21	an S -box
	X^{in}	21	the set of inputs of an S -box X
	X^{out}	21	the set of outputs of an S -box X
	Box_S	21	the collection of S -boxes
	v	21	value assignment
	\emptyset	21	the empty S -box
	DN	22	the set of delay nodes
	Dm	22	the set of demand wires

	Sp	22	the set of supply wires
	$s : \text{Dm} \longrightarrow \text{Sp}$	22	the supplier assignment
	φ_-^w	23	the set of external wasted wires of φ
	φ_+^w	23	the set of internal wasted wires of φ
	$\text{WD}(\frac{Y}{X})$	23	the $(\frac{Y}{X})$ -entry of WD
	WD	23	the collection of wiring diagrams
	$\mathbb{1}_Y$	25	the Y -colored unit in WD
Ch. 3	ϵ	34	the empty wiring diagram
	δ_d	34	a 1-delay node
	$\tau_{X,Y}$	35	a name change
	$\theta_{X,Y}$	35	a 2-cell
	$\lambda_{X,x}$	35	a 1-loop
	σ_{X,x_1,x_2}	36	an in-split
	σ^{Y,y_1,y_2}	37	an out-split
	$\omega_{Y,y}$	38	a 1-wasted wire
	$\omega^{X,x}$	39	a 1-internal wasted wire
	$\varphi_1 \circ \dots \circ \varphi_k$	40	(iterated) \circ_1
	$ T $	41	the cardinality of a finite set
Ch. 4	π^{lp}	61	the set of loop elements in π
	π_+^{sp}	61	the set of internally supplied elements in π
	π_-^{sp}	61	the set of externally supplied elements in π
Ch. 5	$ \Psi $	80	the composition of a simplex Ψ
	(ψ_1, \dots, ψ_n)	81	an n -simplex in WD
	WD_\bullet	89	the collection of normal wiring diagrams
	WD_0	91	the collection of strict wiring diagrams
Ch. 6	A_c	96	the c -colored entry of an algebra A
	μ	96	the structure map of an algebra
	$\mu_\zeta \circ_i \mu_\zeta$	97	\circ_i -composition of structure maps
	∂	107	truncation
	Hist^k	107	the set of k -historical propagators
	P_X	108	the set of 1-historical propagators of type X
	$(-)_x_+$	108	take only the $v(x_+)$ -entry
	$(-)\setminus_{x_+}$	108	remove the $v(x_+)$ -entry
	$\text{DS}(X)$	119	the collection of X -discrete systems
	\underline{x}_I	124	take only the entries indexed by I
	$\underline{x}\setminus_I$	124	remove the entries indexed by I
	G_X	124	the X -colored entry of the algebra of open dynamical systems

Ch. 7	$\cdot \longrightarrow \cdot \longleftarrow \cdot$	132	a cospan
	UWD	133	the collection of undirected wiring diagrams
	$X_{[i,j]}$	138	$X_i \sqcup \cdots \sqcup X_j$ or \emptyset
	C_φ	138	the set of cables in φ
Ch. 8	ϵ	146	the empty cell
	ω_*	146	a 1-output wire
	τ_f	146	an undirected name change
	$\theta_{(X,Y)}$	147	an undirected 2-cell
	$\lambda_{(X,x_\pm)}$	147	a loop
	$\sigma_{(X,x_1,x_2)}$	148	a split
Ch. 9	$C_\psi^{(m,n)}$	162	the set of (m,n) -cables
	$C_\psi^{(0,0)}$	162	the set of wasted cables
	$C_\psi^{(\geq m,n)}$	162	the set of $(\geq m,n)$ -cables
	$C_\psi^{(m,\geq n)}$	162	the set of $(m,\geq n)$ -cables
	$C_\psi^{(\geq m,\geq n)}$	162	the set of $(\geq m,\geq n)$ -cables
Ch. 10	(ψ_1, \dots, ψ_n)	180	an n -simplex in UWD
Ch. 11	A^X	197	the set of functions $X \longrightarrow A$
	$\wp(X)$	197	the power set of X
	$\text{Rel}_A(X)$	197	$\wp(A^X)$
	Rel_A	198	the relational algebra of A
	Rel	204	the typed relational algebra
Ch. 12	\bar{Y}	215	$Y^{\text{in}} \sqcup Y^{\text{out}}$
	χ	216	the operad map $\text{WD}_\bullet \longrightarrow \text{UWD}$
	χ^0	229	the operad map $\text{WD}_0 \longrightarrow \text{UWD}$
Ch. 13	ρ	236	the operad map $\text{WD} \longrightarrow \text{UWD}$

Introduction

1.1. What are Wiring Diagrams?

Wiring diagrams form a kind of graphical language that describes operations or processes with multiple inputs and multiple outputs and how such operations are wired together to form a larger and more complicated operation. Some visual examples of wiring diagrams are in (2.2.14.1), Chapter 3, and Example 4.2.3. The first type of wiring diagrams that we are going to study in this monograph was first introduced in [RS13], with variants studied in [Spi15, Spi15b, VSL14]. In [Spi15, Spi15b] wiring diagrams without delay nodes (Def. 5.3.1), which we call *normal* wiring diagrams, were used to study mode-dependent networks, discrete systems, and dynamical systems. In [VSL14] wiring diagrams without delay nodes and whose supplier assignments are bijections (Def. 5.4.1), which we call *strict* wiring diagrams, were used to study open dynamical systems.

Wiring diagrams are by nature directed, in the sense that every operation has a finite set of inputs and a finite set of outputs, each element of which is allowed to carry a value of some kind. There is also an undirected version of wiring diagrams [Spi13, Spi14]. Unlike a wiring diagram, in an undirected wiring diagram, each operation is a finite set, each element of which is again allowed to carry a value. Some visual examples of undirected wiring diagrams are in (7.1.6.1), Example 7.3.7, and Chapters 8 and 9. For those familiar with operad theory, the distinction between wiring diagrams and undirected wiring diagrams is similar to that between operads and cyclic operads. Just as cyclic operads are not simpler than operads, undirected wiring diagrams are not really simpler than wiring diagrams and have their own subtlety.

The main reason that wiring diagrams and undirected wiring diagrams are important is that they have enormous potential for applications in many different disciplines. Wiring diagrams and undirected wiring diagrams allow one to consider a finite collection of related operations, wired together in some way, as an operation itself. Such an operation can then be considered as a single operation within a yet larger collection of operations, and so forth. For instance, a finite collection of related operations may be a group of neurons in a certain region of the brain, a collection of codes within a large computer program, or a few related agents within a large supply-chain. In fact, the authors of [RS13] cited both computer science and cognitive neuroscience as potential applications of wiring diagrams. Furthermore, in [Spi15b, VSL14] wiring diagrams were used to study dynamical systems and to model certain kinds of differential equations. Many potential fields of applications are mentioned in the introduction of [VSL14]. In [Spi13] undirected wiring diagrams were used to study database relational queries, plug-and-play devices, recursion, and circuit diagrams.

The substitution process involving wiring diagrams and undirected wiring diagrams described in the previous paragraph can be captured precisely using the notion of colored operads. A *colored operad*, or just an operad, is a mathematical object that describes operations with multiple inputs and one output and their compositions. A colored operad in which there are only unary operations is exactly a category. If one restricts even further to just the 1-colored case in which the unary operations form a set, then one has exactly a monoid, such as the set of integers under addition. Therefore, a colored operad is a multiple-input generalization of a category, and in fact colored operads are also called symmetric multicategories. Multicategories without symmetric group actions were introduced by Lambek [Lam69]. One-colored operads, together with the name *operad*, were introduced by May [May72] in the topological setting. See [May97] for the definition of a one-colored operad in a symmetric monoidal category. The book [Yau16] is an elementary introduction to colored operads in symmetric monoidal categories. The book [YJ15] has more in-depth discussion of colored operads and related objects.

In [RS13] Rupel and Spivak observed that the collection of wiring diagrams is a colored operad WD , in which the operadic composition corresponds precisely to the substitution process described above. Each colored operad has associated algebras, on which the colored operad acts. The operadic action is similar to the action of an associative algebra on a left module. The authors of [RS13] defined a WD -algebra, called the *propagator algebra*, that models a certain kind of input-output process.

Closely related colored operads of sub-classes of wiring diagrams were introduced in [Spi15, Spi15b, VSL14]. We will denote by WD_\bullet (Def. 5.3.1) the operad of *normal* wiring diagrams, meaning those without delay nodes. In [Spi15b] Spivak introduced a WD_\bullet -algebra, called the *algebra of discrete systems*, that is closely

related to a Moore machine, also known as a discrete state machine. Also we will write WD_0 (Def. 5.4.1) for the operad of *strict* wiring diagrams, meaning those without delay nodes and whose supplier assignments are bijections. In [VSL14] a WD_0 -algebra, called the *algebra of open dynamical systems*, was defined that models a certain kind of differential equations. Likewise, in [Spi13] Spivak constructed the colored operad UWD of undirected wiring diagrams. Spivak also defined a UWD-algebra called the *relational algebra*, which was used to model relational queries in database.

1.2. Purposes of this Monograph

This monograph is a comprehensive study of the combinatorial structure of the operads WD , WD_\bullet , WD_0 , and UWD of (normal/strict/undirected) wiring diagrams, their algebras, and the relationships between these operads. Specifically, our main results are of the following three types.

Finite Presentation for Operads: For each of the operads WD , WD_\bullet , WD_0 , and UWD, we prove a finite presentation theorem that describes the operad in terms of just a few operadic generators and a small number of generating relations. For the operad of wiring diagrams WD , there are 8 generating wiring diagrams and 28 generating relations. For the smaller operads WD_\bullet and WD_0 of normal and strict wiring diagrams, the numbers of operadic generators and of generating relations are (7, 28) and (4, 8), respectively. For the operad of undirected wiring diagrams UWD, there are 6 operadic generators and 17 generating relations.

Finite Presentation for Algebras: For each of the operads WD , WD_\bullet , WD_0 , and UWD, we prove a corresponding finite presentation theorem for their algebras. To be more precise, we describe WD -algebras using 8 generating structure maps and 28 generating axioms. Similar finite presentations are also obtained for the algebras over the operads WD_\bullet of normal wiring diagrams, WD_0 of strict wiring diagrams, and UWD of undirected wiring diagrams. As applications we provide finite presentations for the propagator algebra over WD , the algebra of discrete systems over WD_\bullet , the algebra of open dynamical systems over WD_0 , and the (typed) relational algebra over UWD. Along the way, we provide a partial verification of Spivak's conjecture [Spi13] regarding the quotient-freeness of the relational algebra.

Maps Between Operads: We construct a commutative diagram

$$\begin{array}{ccccc}
 WD_0 & \longrightarrow & WD_\bullet & \longrightarrow & WD \\
 & \searrow & \downarrow \chi & \swarrow \rho & \\
 & & UWD & &
 \end{array}$$

χ^0

of operad maps, in which the horizontal maps are operad inclusions. For each of the operad maps χ^0 , χ , and ρ , we compute precisely the image in UWD. In particular, the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ is surjective. The existence of the operad map ρ answers a question raised in [RS13].

The end of this chapter contains several tables that summarize the main results and contain some key references.

The finite presentation theorems for the operads WD , WD_\bullet , WD_0 , and UWD reduce the structure of these operads and their algebras to just a few generators and relations. For example, our finite presentation theorem for the operad WD reduces the understanding of this operad to just 8 simple wiring diagrams and 28 simple relations among them. Likewise, the structure map of a general WD -algebra can be quite involved, as can be seen in the propagator algebra [RS13]. Our finite presentation theorem for WD -algebras reduces the definition and understanding of WD -algebras to just 8 simple generating structure maps and 28 generating axioms, almost all of which are trivial to check in practice. We will further illuminate this point when we discuss the finite presentations for the propagator algebra over WD , the algebra of discrete systems over WD_\bullet , the algebra of open dynamical systems over WD_0 , and the (typed) relational algebra over UWD .

To give our finite presentation theorems for the operads WD , WD_\bullet , WD_0 , and UWD , and for their algebras an even more familiar feel, let us recall a few other places where various kinds of finite presentations occur. Each type of finite presentation is a way to reduce a large, usually infinite, collection of conditions to a finite, or at least smaller, collection of conditions, thereby making the relevant structure more manageable.

- (1) In basic group theory and commutative ring theory [AT69, Rot02], it is quite common to consider finite presentation of groups and modules. For example, over a commutative Noetherian ring, every finitely generated module is also finitely presented [Rot02] (Prop. 7.59).
- (2) A cornerstone in category theory, Mac Lane's Coherence Theorem [Mac63, Mac98] can be regarded as a finite presentation theorem for monoidal categories. Roughly speaking, this theorem says that, in any monoidal category, the infinite collection of commutative formal diagrams has a finite presentation. The generators are the associativity isomorphism, the left and the right units, and their inverses. The generating relations are the Pentagon Axiom for 4-fold iterated tensor products and two unity axioms.
- (3) In the linear setting, the operads for associative algebras, commutative algebras, Lie algebras, Leibniz algebras, Poisson algebras, and many others, are finitely presented [GK94]. For example, the associative operad has one generator, which in its algebras corresponds to the usual multiplication $A \otimes A \longrightarrow A$ of an associative algebra. The associative operad has

one generating relation, which in its algebras corresponds to the usual associativity axiom, $(ab)c = a(bc)$, of an associative algebra.

- (4) In [BE14, BSZ14] a finite presentation is given for the symmetric monoidal category of signal-flow graphs. In applications signal-flow graphs form another kind of graphical language that describes processes with inputs and outputs and relations between them. One main difference between (undirected) wiring diagrams and signal-flow graphs is that the composition of signal-flow graphs is done by *grafting*. This means that the outputs of one signal-flow graph are connected to the inputs of another signal-flow graph. This is similar to the situation in string diagrams [JSV96, SSR15]. On the other hand, the operadic composition of (undirected) wiring diagrams is done by *substitution*, which is pictorially depicted in (2.3.2.2) for wiring diagrams and in (7.3.2.2) for undirected wiring diagrams. In more conceptual terms, the collection of signal-flow graphs is a prop, hence an algebra over the operad for props [YJ15] (Theorem 14.1). On the other hand, the collection of (undirected) wiring diagrams is an operad.
- (5) Closer to the topic of this monograph is [YJ15] (Ch.7), where finite presentations are given for various graph groupoids including those for colored operads, colored props, and colored wheeled props. In fact, the way we phrase and verify our finite presentation theorems for the operads of (undirected) wiring diagrams and for their algebras is conceptually similar to the presentation in [YJ15] (Ch.7). One way to explain this conceptual similarity is that, for both (undirected) wiring diagrams and the graphs for, say, colored wheeled props, the composition is done by substitution. However, wiring diagrams are in several ways more complicated than the graphs in [YJ15]. In fact, the graphs in [YJ15] do not have delay nodes, internal and external wasted wires, and split wires, all of which can happen in a wiring diagram. See, for example, the wiring diagram in (2.2.14.1).

1.3. Audience and Features

The main results in this monograph—namely, the finite presentation theorems for the various operads of (undirected) wiring diagrams and for their algebras as well as operad maps between them—are new. So this monograph should be useful to mathematicians with an interest in operads and (undirected) wiring diagrams. Furthermore, due to the wide variety of potential applications, we also intend to make this monograph and this subject accessible to scientists and engineers.

With such a large audience in mind, the prerequisite for this monograph has been kept to an absolute minimum. In particular, we assume the reader is comfortable with basic concepts of sets, functions, and mathematical induction. No prior knowledge of categories, operads, and (undirected) wiring diagrams is assumed.

The presentation of the material proceeds at a fairly leisurely pace and is roughly at the advanced undergraduate to beginning graduate level. To motivate various constructions and concepts, we have many examples and a lot of discussion that explains the intuition behind the scene. Furthermore, there are over 100 pictures throughout this monograph that help the reader visualize (undirected) wiring diagrams. Finally, to solidify one's understanding of the subject, the reader may work through the problems in Chapter 14. There are enough problems there to keep one busy for a few days.

1.4. Chapter Summaries

This monograph is divided into three parts.

Part 1: Wiring Diagrams (Chapters 2–6)

This part contains the finite presentation theorems for the operad WD of wiring diagrams, the operad WD_\bullet of normal wiring diagrams, the operad WD_0 of strict wiring diagrams, and their algebras.

Part 2: Undirected Wiring Diagrams (Chapters 7–11)

This part contains the finite presentation theorems for the operad UWD of undirected wiring diagrams and for their algebras.

Part 3: Maps Between Operads of Wiring Diagrams (Chapters 12–14)

This part contains the construction and description of various operad maps between the operads WD , WD_\bullet , WD_0 , and UWD . The last chapter contains a list of problems.

Below is a brief description of each chapter.

In Chapter 2, to keep this document self-contained, we first recall two equivalent definitions of a colored operad. The first definition is in terms of May's operad structure map γ , and the other one is in terms of the \circ_i -compositions. After recalling the definition of a wiring diagram, we provide a proof of the fact from [RS13] that the collection of wiring diagrams WD is a colored operad. The main difference here is that we use the definition of a colored operad based on the \circ_i -compositions. In this monograph, we prefer to work with the \circ_i -compositions rather than May's operad structure map γ because the \circ_i -compositions are more convenient in phrasing and verifying our finite presentation theorems.

In Chapter 3 we introduce 8 *generating wiring diagrams* and 28 *elementary relations* among them. On the one hand, one may regard this chapter as a long list of concrete examples of wiring diagrams and their operadic compositions. On the other hand, in later chapters we will see that these finite collections of generating wiring diagrams and elementary relations are sufficient to describe the operad WD of wiring diagrams, its variants WD_\bullet and WD_0 , and their algebras.

For the finite presentation theorems for the operad WD of wiring diagrams and its variants WD_\bullet and WD_0 , we will need to be able to decompose every wiring diagram in terms of the 8 generating wiring diagrams in a highly structured way. The purpose of Chapter 4 is to supply all the steps needed to establish such a decomposition.

The finite presentation theorems for the operad WD of wiring diagrams as well as its two variants WD_\bullet and WD_0 are given in Chapter 5; see Theorems 5.2.10, 5.3.7, and 5.4.8. Since we are not working in the linear setting (e.g., of modules) where we can take quotients, we need to be extra careful in phrasing our finite presentations for the operads WD , WD_\bullet , and WD_0 . For this purpose, a crucial concept is that of a *stratified presentation*, which is the highly structured decomposition mentioned in the previous paragraph. The results in Chapter 4 guarantees the existence of a stratified presentation for each wiring diagram. This implies the finite generation parts of our finite presentation theorems for WD , WD_\bullet , and WD_0 . The relation parts of the finite presentation theorems are phrased in terms of our concept of an *elementary equivalence*. Roughly speaking, an elementary equivalence means replacing one side of either (i) an elementary relation in Chapter 3 or (ii) an operad associativity/unity axiom for the generating wiring diagrams, by the other side.

In Chapter 6 we discuss finite presentations for algebras over the operads WD , WD_\bullet , and WD_0 . In each case, the finite presentation for algebras is a consequence of the finite presentation theorem for the corresponding operad of wiring diagrams. To illustrate the finite presentation for WD -algebras, we will describe the propagator algebra in terms of 8 generating structure maps and 28 generating axioms. To illustrate our finite presentation for WD_\bullet -algebras, we will describe the algebra of discrete systems in terms of 7 generating structure maps and 28 generating axioms. To illustrate our finite presentation for WD_0 -algebras, we will similarly describe the algebra of open dynamical systems in terms of 4 generating structure maps and 8 generating axioms. This finishes Part 1 on wiring diagrams.

Part 2 begins with Chapter 7, where we first recall the notion of an undirected wiring diagram. Then we give a proof of the fact that the collection of undirected wiring diagrams forms an operad UWD . As in Chapter 2, the operad structure on UWD as well as its proof are both given in terms of the \circ_i -compositions because the finite presentation theorems are easier to phrase this way. One subtlety about the operad UWD is that undirected wiring diagrams may have wasted cables (Def. 7.1.1), which are cables that are not soldered to any wires. As opposed to what was stated in [Spi14] (Example 7.4.2.10), wasted cables *cannot* be excluded from the definition of undirected wiring diagrams. In fact, wasted cables can actually be created from operadic composition of undirected wiring diagrams without wasted cables. We will make this point precise in Example 7.3.7.

Chapter 8 is the undirected analogue of Chapter 3. In this chapter, we describe 6 *generating undirected wiring diagrams* and 17 *elementary relations* among them. On

the one hand, one may regard this chapter as a long list of concrete examples of undirected wiring diagrams and their operadic compositions. On the other hand, in later chapters we will see that these finite collections of generating undirected wiring diagrams and elementary relations are sufficient to describe the operad UWD of undirected wiring diagrams.

Chapter 9 is the undirected analogue of Chapter 4. In this chapter, we show that each undirected wiring diagram can be decomposed in terms of the generating undirected wiring diagrams in a highly structured way. Such a decomposition is needed to establish the finite presentation theorem for the operad UWD.

Chapter 10 is the undirected analogue of Chapter 5. In this chapter, we establish the finite presentation theorem for the operad UWD of undirected wiring diagrams; see Theorem 10.2.7. This result is phrased in terms of the generating undirected wiring diagrams and an undirected version of an elementary equivalence.

Chapter 11 contains the finite presentation theorem for UWD-algebras. This result is a consequence of the finite presentation theorem for the operad UWD. It describes each UWD-algebra in terms of 6 generating structure maps and 17 generating axioms, almost all of which are trivial to check in practice. We will illustrate this point with the relation algebra and the typed relational algebra from [Spi13]. We will also provide a partial verification of Spivak's conjecture regarding the quotient-freeness of the relational algebra. This finishes Part 2 on undirected wiring diagrams.

Part 3 begins with Chapter 12, in which we first construct the operad inclusions $WD_0 \longrightarrow WD_\bullet \longrightarrow WD$. Recall that WD_\bullet is the operad of normal wiring diagrams—i.e., those without delay nodes—and that WD_0 is the operad of strict wiring diagrams—i.e., those without delay nodes and whose supplier assignments are bijections. Then we construct an operad map $\chi : WD_\bullet \longrightarrow UWD$, essentially by forgetting directions, and its restriction $\chi^0 : WD_0 \longrightarrow UWD$. For each of the operad maps χ and χ^0 , we compute precisely the image in UWD. In the terminology of Notation 9.1.1, the image of the operad map χ consists of precisely the undirected wiring diagrams *without* wasted cables and $(0, \geq 2)$ -cables. The image of the operad map χ^0 consists of precisely the undirected wiring diagrams with only $(1, 1)$ -cables and $(2, 0)$ -cables.

In Chapter 13 we extend the operad map $\chi : WD_\bullet \longrightarrow UWD$ to an operad map $\rho : WD \longrightarrow UWD$ that is defined for all wiring diagrams. We prove that the operad map ρ is surjective, so every undirected wiring diagram is the image of some wiring diagram. The operad map ρ is slightly subtle because wiring diagrams may have delay nodes, while undirected wiring diagrams do not seem to have an exact analogue of delay nodes. In fact, for this reason Rupel and Spivak [RS13] (Section 4.1) expressed doubt about the possibility that there be an operad map $WD \longrightarrow UWD$.

We will see that delay nodes, far from being an obstruction, play a critical role in the surjectivity of the operad map ρ .

Chapter 14 contains some problems about operads and (undirected) wiring diagrams arising from the earlier chapters. This finishes Part 3.

The following table summarizes the key references for the various operads of (undirected) wiring diagrams and their finite presentation theorems.

	Operad of	Finite Presentation	Generators	Relations
WD	wiring diagrams (Theorem 2.3.8)	Theorem 5.2.10	8 (Def. 3.1.9)	28 (Def. 3.3.30)
WD \bullet	normal wiring diagrams (Prop. 5.3.5)	Theorem 5.3.7	7 (Def. 5.3.6(1))	28 (Def. 5.3.6(4))
WD $_0$	strict wiring diagrams (Prop. 5.4.6)	Theorem 5.4.8	4 (Def. 5.4.7(1))	8 (Def. 5.4.7(5))
UWD	undirected wiring diagrams (Theorem 7.3.11)	Theorem 10.2.7	6 (Def. 8.1.7)	17 (Def. 8.2.18)

The following table summarizes the key references for the finite presentation theorems for algebras over the various operads of (undirected) wiring diagrams.

Algebras over	Finite Presentation	(Generators, Relations)	Key Example
WD	Theorem 6.2.2	(8, 28) (Def. 6.2.1)	propagator algebra (Theorem 6.3.7)
WD \bullet	Theorem 6.4.2	(7, 28) (Def. 6.4.1)	discrete systems (Theorem 6.5.7)
WD $_0$	Theorem 6.6.2	(4, 8) (Def. 6.6.1)	open dynamical systems (Theorem 6.7.7)
UWD	Theorem 11.1.2	(6, 17) (Def. 11.1.1)	(typed) relational algebra (Theorems 11.2.5 and 11.4.7)

The following table summarizes the key references for the operad maps between the various operads of (undirected) wiring diagrams.

Operad Map	Reference	Note/Image
$WD_0 \longrightarrow WD_\bullet \longrightarrow WD$	Prop. 12.1.7	inclusions
$WD_\bullet \xrightarrow{\chi} UWD$	Theorem 12.2.4	no $(0,0)$ - and $(0,\geq 2)$ -cables (Theorem 12.4.1)
$WD_0 \xrightarrow{\chi^0} UWD$	Theorem 12.5.1	only $(1,1)$ - and $(2,0)$ -cables
$WD \xrightarrow{\rho} UWD$	Theorem 13.1.4	surjective (Theorem 13.3.3)

Part 1

Wiring Diagrams

The main purpose of this part is to describe the combinatorial structure of

- (1) the operad WD of wiring diagrams,
- (2) the operad WD_\bullet of normal wiring diagrams, and
- (3) the operad WD_0 of strict wiring diagrams.

A normal wiring diagram is a wiring diagram without delay nodes. A strict wiring diagram is a normal wiring diagram whose supplier assignment is a bijection. For each of these three operads, we prove a finite presentation theorem that describes the operad in terms of a few operadic generators and a small number of generating relations.

Operads and wiring diagrams are recalled in Chapter 2. Operadic generators and generating relations for the operad WD of wiring diagrams are presented in Chapter 3. Various decompositions of wiring diagrams are given in Chapter 4. Using the results in Chapters 3 and 4, the finite presentation theorems for the operads WD , WD_\bullet , and WD_0 are proved in Chapter 5. Corresponding finite presentation theorems for WD -algebras, WD_\bullet -algebras, and WD_0 -algebras are discussed in Chapter 6.

Wiring Diagrams

This purpose of this chapter is to recall the definitions of colored operads and wiring diagrams. In Section 2.1 we recall two equivalent definitions of a colored operad, one in terms of the structure map γ (2.1.2.2) and the other in terms of the \circ_i -compositions (2.1.4.1).

Wiring diagrams are defined in Section 2.2. The main difference between our definition of a wiring diagram and the original one in [RS13] is that we allow the wires to carry values in an arbitrary class S instead of just the class of pointed sets. This added flexibility will be important in later chapters when we discuss operad algebras. Indeed, in Section 6.3 when we discuss the propagator algebra, we will take S to be the class of pointed sets. On the other hand, in Section 6.7 when we discuss the algebra of open dynamical systems, we will take S to be a set of representatives of isomorphism classes of second-countable smooth manifolds.

In Section 2.3 we define the operad structure on wiring diagrams in terms of \circ_i -compositions. Although we could also have defined this operad structure in terms of γ as in [RS13], we chose to use \circ_i -compositions because the finite presentation theorems in Chapter 5 can be phrased and proved more easily using the latter.

2.1. Colored Operads

For brief discussion about *classes* in the set-theoretic sense, the reader is referred to [Hal74, Pin04]. In this monograph, the reader can safely take the word *class* to just mean a collection of objects, such as sets, pointed sets, and real functions. First we introduce some notations for the colors in a colored operad.

Definition 2.1.1. Suppose S is a class.

- (1) Denote by $\text{Prof}(S)$ the class of finite ordered sequences of elements in S . An element in $\text{Prof}(S)$ is called an S -profile or just a *profile* if S is clear from the context.
- (2) A typical S -profile of length n is denoted by $\underline{s} = (s_1, \dots, s_n)$ with $|\underline{s}|$ denoting its length.
- (3) The empty S -profile is denoted by \emptyset .
- (4) For $n \geq 0$ denote by $\text{Prof}^{\geq n}(S) \subseteq \text{Prof}(S)$ the sub-class of S -profiles of length at least n .

Next we define colored operads. See, for example, [Yau16] for more in-depth discussion, motivation, and examples of colored operads. For each integer $n \geq 0$, the symmetric group on n letters is denoted by Σ_n .

Definition 2.1.2. Suppose S is a class. An S -colored operad $(\mathcal{O}, \mathbb{1}, \gamma)$ consists of the following data.

- (1) For any $d \in S$ and $\underline{c} \in \text{Prof}(S)$ with length $n \geq 0$, \mathcal{O} is equipped with a class

$$\mathcal{O}(\underline{c})^d = \mathcal{O}(c_1, \dots, c_n)^d$$

called the *entry* of \mathcal{O} with *input profile* \underline{c} and *output color* d . An element in $\mathcal{O}(\underline{c})^d$ is called an n -ary element in \mathcal{O} .

- (2) For $(\underline{c})^d \in \text{Prof}(S) \times S$ as above and a permutation $\sigma \in \Sigma_n$, \mathcal{O} is equipped with a bijection

$$\mathcal{O}(\underline{c})^d \xrightarrow[\cong]{\sigma} \mathcal{O}(\underline{c}\sigma)^d \quad (2.1.2.1)$$

called the *right action* or the *symmetric group action*, in which

$$\underline{c}\sigma = (c_{\sigma(1)}, \dots, c_{\sigma(n)})$$

is the right permutation of \underline{c} by σ .

- (3) For each $c \in S$, \mathcal{O} is equipped with a specific element $\mathbb{1}_c \in \mathcal{O}(c)^c$, called the c -colored *unit*.
- (4) For $(\underline{c})^d \in \text{Prof}(S) \times S$ as above with $n \geq 1$, suppose $\underline{b}_1, \dots, \underline{b}_n \in \text{Prof}(S)$ and $\underline{b} = (\underline{b}_1, \dots, \underline{b}_n) \in \text{Prof}(S)$ is their concatenation. Then \mathcal{O} is equipped with a map

$$\mathcal{O}(\underline{c})^d \times \prod_{i=1}^n \mathcal{O}(\underline{b}_i)^{c_i} \xrightarrow{\gamma} \mathcal{O}(\underline{b})^d \quad (2.1.2.2)$$

called the *operadic composition*. For $y \in \mathcal{O}(\underline{c})^d$ and $x_i \in \mathcal{O}(\underline{b}_i)^{c_i}$ for $1 \leq i \leq n$, the image of the operadic composition is written as

$$\gamma(y; x_1, \dots, x_n) \in \mathcal{O}(\underline{b})^d.$$

This data is required to satisfy the following associativity, unity, and equivariance axioms.

Associativity Axiom: Suppose that:

- in (2.1.2.2)

$$\underline{b}_j = (b_1^j, \dots, b_{k_j}^j) \in \text{Prof}(S)$$

has length $k_j \geq 0$ for each $1 \leq j \leq n$ such that at least one $k_j > 0$;

- $\underline{a}_i^j \in \text{Prof}(S)$ for each $1 \leq j \leq n$ and $1 \leq i \leq k_j$;
- for each $1 \leq j \leq n$,

$$\underline{a}_j = \begin{cases} (\underline{a}_1^j, \dots, \underline{a}_{k_j}^j) & \text{if } k_j > 0, \\ \emptyset & \text{if } k_j = 0; \end{cases} \quad (2.1.2.3)$$

- $\underline{a} = (\underline{a}_1, \dots, \underline{a}_n)$ is their concatenation.

Then the *associativity diagram*

$$\begin{array}{ccc} \mathcal{O}_{\underline{c}}^{(d)} \times \left[\prod_{j=1}^n \mathcal{O}_{\underline{b}_j}^{(c_j)} \right] \times \prod_{j=1}^n \left[\prod_{i=1}^{k_j} \mathcal{O}_{\underline{a}_i^j}^{(b_i^j)} \right] & \xrightarrow{(\gamma, \text{Id})} & \mathcal{O}_{\underline{b}}^{(d)} \times \prod_{j=1}^n \left[\prod_{i=1}^{k_j} \mathcal{O}_{\underline{a}_i^j}^{(b_i^j)} \right] \\ \text{permute} \downarrow \cong & & \downarrow \gamma \\ \mathcal{O}_{\underline{c}}^{(d)} \times \prod_{j=1}^n \left[\mathcal{O}_{\underline{b}_j}^{(c_j)} \times \prod_{i=1}^{k_j} \mathcal{O}_{\underline{a}_i^j}^{(b_i^j)} \right] & & \\ (\text{Id}, \pi_j \gamma) \downarrow & & \\ \mathcal{O}_{\underline{c}}^{(d)} \times \prod_{j=1}^n \mathcal{O}_{\underline{a}_j}^{(c_j)} & \xrightarrow{\gamma} & \mathcal{O}_{\underline{a}}^{(d)} \end{array} \quad (2.1.2.4)$$

is commutative.

Unity Axioms: Suppose $d \in S$.

- (1) If $\underline{c} = (c_1, \dots, c_n) \in \text{Prof}(S)$ has length $n \geq 1$, then the *right unity diagram*

$$\begin{array}{ccc} \mathcal{O}_{\underline{c}}^{(d)} \times \{*\}^n & \xrightarrow{\cong} & \mathcal{O}_{\underline{c}}^{(d)} \\ (\text{Id}, \pi \mathbb{1}_{c_j}) \downarrow & & \downarrow = \\ \mathcal{O}_{\underline{c}}^{(d)} \times \prod_{j=1}^n \mathcal{O}_{c_j}^{(c_j)} & \xrightarrow{\gamma} & \mathcal{O}_{\underline{c}}^{(d)} \end{array} \quad (2.1.2.5)$$

is commutative. Here $\{*\}$ is the one-point set, and $\{*\}^n$ is its n -fold product.

(2) If $\underline{b} \in \text{Prof}(S)$, then the *left unity diagram*

$$\begin{array}{ccc} \{*\} \times \mathcal{O}(\underline{b}) & \xrightarrow{\cong} & \mathcal{O}(\underline{b}) \\ (\mathbb{1}_d, \text{Id}) \downarrow & & \downarrow = \\ \mathcal{O}(\underline{a}) \times \mathcal{O}(\underline{b}) & \xrightarrow{\gamma} & \mathcal{O}(\underline{b}) \end{array} \quad (2.1.2.6)$$

is commutative.

Equivariance Axioms: Suppose that in (2.1.2.2) $|\underline{b}_j| = k_j \geq 0$.

(1) For each permutation $\sigma \in \Sigma_n$, the *top equivariance diagram*

$$\begin{array}{ccc} \mathcal{O}(\underline{c}) \times \prod_{j=1}^n \mathcal{O}(\underline{b}_j) & \xrightarrow{(\sigma, \sigma^{-1})} & \mathcal{O}(\underline{c}^\sigma) \times \prod_{j=1}^n \mathcal{O}(\underline{b}_{\sigma(j)}) \\ \gamma \downarrow & & \downarrow \gamma \\ \mathcal{O}(\underline{b}_1, \dots, \underline{b}_n) & \xrightarrow{\sigma\langle k_1, \dots, k_n \rangle} & \mathcal{O}(\underline{b}_{\sigma(1)}, \dots, \underline{b}_{\sigma(n)}) \end{array} \quad (2.1.2.7)$$

is commutative. Here $\sigma\langle k_1, \dots, k_n \rangle \in \Sigma_{k_1 + \dots + k_n}$ is the block permutation induced by σ that permutes the n consecutive blocks of lengths k_1, \dots, k_n , leaving the relative order within each block unchanged.

(2) Given permutations $\tau_j \in \Sigma_{k_j}$ for $1 \leq j \leq n$, the *bottom equivariance diagram*

$$\begin{array}{ccc} \mathcal{O}(\underline{c}) \times \prod_{j=1}^n \mathcal{O}(\underline{b}_j) & \xrightarrow{(\text{Id}, \prod \tau_j)} & \mathcal{O}(\underline{c}) \times \prod_{j=1}^n \mathcal{O}(\underline{b}_j \tau_j) \\ \gamma \downarrow & & \downarrow \gamma \\ \mathcal{O}(\underline{b}_1, \dots, \underline{b}_n) & \xrightarrow{\tau_1 \oplus \dots \oplus \tau_n} & \mathcal{O}(\underline{b}_1 \tau_1, \dots, \underline{b}_n \tau_n) \end{array} \quad (2.1.2.8)$$

is commutative. Here the block sum $\tau_1 \oplus \dots \oplus \tau_n \in \Sigma_{k_1 + \dots + k_n}$ is the image of (τ_1, \dots, τ_n) under the inclusion $\Sigma_{k_1} \times \dots \times \Sigma_{k_n} \longrightarrow \Sigma_{k_1 + \dots + k_n}$.

A *colored operad* is a C -colored operad for some class C . We will also call a colored operad simply as an *operad*.

Remark 2.1.3. A 1-colored operad [Kel05, MSS02, May72, May97], with $S = \{*\}$, is usually called an *operad* or a *symmetric operad*. The underline notation for $\underline{c} \in \text{Prof}(S)$ and the vertical notation for $\binom{d}{\underline{c}} \in \text{Prof}(S) \times S$ originated in [JY09]. See [Yau16] (section 9.6) for more discussion of these notations.

Due to the presence of the colored units, a colored operad can also be defined in terms of a binary product, which leads to axioms that are sometimes easier to check in practice and that we will use in most of the rest of this monograph. In the one-colored linear setting, this alternative formulation of an operad was first made explicit in [Mar96]. We now recall this alternative formulation. The elementary

relations in Section 3.3 are almost all stated in terms of the \circ_i -compositions in the following definition.

Definition 2.1.4. Suppose S is a class. An S -colored operad $(O, \mathbb{1}, \circ)$ consists of the following data.

- (1) It has the same data as in (1)–(3) in Def. 2.1.2.
- (2) For each $d \in S$, $\underline{c} = (c_1, \dots, c_n) \in \text{Prof}(S)$ with length $n \geq 1$, $\underline{b} \in \text{Prof}(S)$, and $1 \leq i \leq n$, it is equipped with a map

$$O(\underline{c}) \times O(\underline{b}) \xrightarrow{\circ_i} O(\underline{c} \circ_i \underline{b}) \quad (2.1.4.1)$$

called the \circ_i -composition, where

$$\underline{c} \circ_i \underline{b} = \left(\underbrace{c_1, \dots, c_{i-1}}_{\emptyset \text{ if } i=1}, \underline{b}, \underbrace{c_{i+1}, \dots, c_n}_{\emptyset \text{ if } i=n} \right). \quad (2.1.4.2)$$

This data is required to satisfy the following associativity, unity, and equivariance axioms. Suppose $d \in S$, $\underline{c} = (c_1, \dots, c_n) \in \text{Prof}(S)$, $\underline{b} \in \text{Prof}(S)$ with length $|\underline{b}| = m$, and $\underline{a} \in \text{Prof}(S)$ with length $|\underline{a}| = l$.

Associativity Axioms: There are two associativity axioms.

- (1) Suppose $n \geq 2$ and $1 \leq i < j \leq n$. Then the *horizontal associativity diagram*

$$\begin{array}{ccc} O(\underline{c}) \times O(\underline{a}) \times O(\underline{b}) & \xrightarrow{(\circ_i, \text{Id})} & O(\underline{c} \circ_i \underline{a}) \times O(\underline{b}) \\ \text{permute} \downarrow \cong & & \downarrow \circ_{j-1+l} \\ O(\underline{c}) \times O(\underline{b}) \times O(\underline{a}) & & \\ (\circ_j, \text{Id}) \downarrow & & \\ O(\underline{c} \circ_j \underline{b}) \times O(\underline{a}) & \xrightarrow{\circ_i} & O(\underline{c} \circ_j \underline{b} \circ_i \underline{a}) = O(\underline{c} \circ_i \circ_{j-1+l} \underline{b}) \end{array} \quad (2.1.4.3)$$

is commutative.

- (2) Suppose $n, m \geq 1$, $1 \leq i \leq n$, and $1 \leq j \leq m$. Then the *vertical associativity diagram*

$$\begin{array}{ccc} O(\underline{c}) \times O(\underline{b}) \times O(\underline{a}) & \xrightarrow{(\text{Id}, \circ_j)} & O(\underline{c}) \times O(\underline{b} \circ_j \underline{a}) \\ (\circ_i, \text{Id}) \downarrow & & \downarrow \circ_i \\ O(\underline{c} \circ_i \underline{b}) \times O(\underline{a}) & \xrightarrow{\circ_{i-1+j}} & O(\underline{c} \circ_i \underline{b} \circ_{i-1+j} \underline{a}) = O(\underline{c} \circ_i (\underline{b} \circ_j \underline{a})) \end{array} \quad (2.1.4.4)$$

is commutative.

Unity Axioms: There are two unity axioms.

(1) The *left unity diagram*

$$\begin{array}{ccc} \{*\} \times \mathcal{O}_{\underline{c}}^{(d)} & \xrightarrow{(\mathbb{1}_d, \text{Id})} & \mathcal{O}_{\underline{d}}^{(d)} \times \mathcal{O}_{\underline{c}}^{(d)} \\ & \searrow \cong & \downarrow \circ_1 \\ & & \mathcal{O}_{\underline{c}}^{(d)} \end{array} \quad (2.1.4.5)$$

is commutative.

(2) If $n \geq 1$ and $1 \leq i \leq n$, then the *right unity diagram*

$$\begin{array}{ccc} \mathcal{O}_{\underline{c}}^{(d)} \times \{*\} & \xrightarrow{(\text{Id}, \mathbb{1}_{c_i})} & \mathcal{O}_{\underline{c}}^{(d)} \times \mathcal{O}_{c_i}^{(c_i)} \\ & \searrow \cong & \downarrow \circ_i \\ & & \mathcal{O}_{\underline{c}}^{(d)} \end{array} \quad (2.1.4.6)$$

is commutative.

Equivariance Axiom: Suppose $|\underline{c}| = n \geq 1$, $1 \leq i \leq n$, $\sigma \in \Sigma_n$, and $\tau \in \Sigma_m$. Then the *equivariance diagram*

$$\begin{array}{ccc} \mathcal{O}_{\underline{c}}^{(d)} \times \mathcal{O}_{\underline{b}}^{(c_{\sigma(i)})} & \xrightarrow{\circ_{\sigma(i)}} & \mathcal{O}_{(\underline{c}^{\circ_{\sigma(i)}} \underline{b})}^{(d)} \\ (\sigma, \tau) \downarrow & & \downarrow \sigma \circ_i \tau \\ \mathcal{O}_{(\underline{c}\sigma)}^{(d)} \times \mathcal{O}_{\underline{b}\tau}^{(c_{\sigma(i)})} & \xrightarrow{\circ_i} & \mathcal{O}_{(\underline{c}\sigma) \circ_i (\underline{b}\tau)}^{(d)} = \mathcal{O}_{(\underline{c}^{\circ_{\sigma(i)}} \underline{b}) (\sigma \circ_i \tau)}^{(d)} \end{array} \quad (2.1.4.7)$$

is commutative, where

$$\sigma \circ_i \tau = \underbrace{\sigma(1^{i-1}, m, 1^{n-i})}_{\text{block permutation}} \underbrace{(\text{id}^{i-1} \oplus \tau \oplus \text{id}^{n-i})}_{\text{block sum}} \in \Sigma_{n+m-1}.$$

On the right side, the block sum permutes the interval $[i, i+m-1]$ via τ . The block permutation induced by σ regards the interval $[i, i+m-1]$ as a single block, within which the relative order is unchanged.

Each \circ_i -composition is also called an *operadic composition* or just a *composition*.

Remark 2.1.5. Without the symmetric group action (2.1.2.1) and the equivariance axiom (2.1.4.7), a non-symmetric colored operad as in Def. 2.1.4 is exactly a *multi-category* as defined by Lambek [Lam69] (p.103-105). In [Lam69]:

- (1) The elements in an entry $\mathcal{O}_{\underline{c}}^{(d)}$ of a colored operad \mathcal{O} are called *multimaps*.
- (2) The \circ_i -composition (2.1.4.1) is called a *substitution* or a *cut*.
- (3) The horizontal associativity axiom (2.1.4.3) is called the *commutative law*.
- (4) The vertical associativity axiom (2.1.4.4) is called the *associative law*.

The reader is cautioned that there are several typographical errors in [Lam69] (p.104-105) in the definition of a multicategory.

Due to the presence of the colored units, the two definitions of a colored operad are in fact equivalent.

Proposition 2.1.6. *Definitions 2.1.2 and 2.1.4 of an S -colored operad are equivalent.*

Proof. In the 1-colored case, a proof can be found in [Mar08] (Prop. 13). For the general colored case, the proof is similar and can be found in, e.g., [Yau16] (section 16.4). The correspondence goes as follows. Given the operadic composition γ (2.1.2.2), $y \in \mathcal{O}_{\underline{c}}^{(d)}$ with $|\underline{c}| = n \geq 1$, and $x \in \mathcal{O}_{\underline{b}}^{(c_i)}$ with $1 \leq i \leq n$, one defines the \circ_i -composition as

$$y \circ_i x = \gamma\left(y; \underbrace{\mathbb{1}_{c_1}, \dots, \mathbb{1}_{c_{i-1}}}_{\emptyset \text{ if } i=1}, x, \underbrace{\mathbb{1}_{c_{i+1}}, \dots, \mathbb{1}_{c_n}}_{\emptyset \text{ if } i=n}\right).$$

Conversely, given the \circ_i -compositions (2.1.4.1), $y \in \mathcal{O}_{\underline{c}}^{(d)}$ with $|\underline{c}| = n \geq 1$, and $x_i \in \mathcal{O}_{\underline{b}_i}^{(c_i)}$ for $1 \leq i \leq n$ with $k_i = |\underline{b}_i|$, one defines the operadic composition γ as

$$\gamma(y; x_1, \dots, x_n) = \left(\left((y \circ_1 x_1) \circ_{k_1+1} x_2 \right) \dots \right) \circ_{k_1+\dots+k_{n-1}+1} x_n. \quad (2.1.6.1)$$

On the right side, every pair of parentheses starts on the left. \square

2.2. Defining Wiring Diagrams

The operad of wiring diagrams WD has Box_S as its class of colors. So before we define wiring diagrams, we first define Box_S . We begin by recalling the basic definition of a *category*. The reader may consult [Awo10, Lei14, Mac98] for more in-depth discussion of category theory. In this monograph, we do not need anything fancy from category theory. All that the reader needs to know is that a category consists of a collection of objects, such as sets or finite sets, and maps between them that can be composed and that satisfy some natural unity and associativity axioms with respect to compositions.

Definition 2.2.1. *A category \mathcal{C} consists of the following data.*

Objects: It is equipped with a collection $\text{Ob}(\mathcal{C})$ of *objects*. For an object a in \mathcal{C} , we will write either $a \in \text{Ob}(\mathcal{C})$ or simply $a \in \mathcal{C}$.

Morphisms: For any objects $a, b \in \text{Ob}(\mathcal{C})$, it is equipped with a collection $\mathcal{C}(a, b)$ of *morphisms* with domain a and codomain b . A morphism f in $\mathcal{C}(a, b)$ is usually denoted by $f : a \longrightarrow b$ and is also called a *map* from a to b .

Composition: For any objects $a, b, c \in \text{Ob}(\mathcal{C})$ and morphisms $f : a \longrightarrow b$ and $g : b \longrightarrow c$, it is equipped with a morphism $g \circ f : a \longrightarrow c$, called the *composition* of f and g .

Identities: Each object $a \in \text{Ob}(\mathcal{C})$ is equipped with a morphism $\mathbb{1}_a : a \longrightarrow a$, called the *identity morphism* of a .

The above data is required to satisfy the following axioms.

Unity: For any objects $a, b, c \in \text{Ob}(\mathcal{C})$ and morphisms $g : a \longrightarrow b$ and $h : c \longrightarrow a$, there are equalities of morphisms

$$g \circ \mathbb{1}_a = g \in \mathcal{C}(a, b) \quad \text{and} \quad \mathbb{1}_a \circ h = h \in \mathcal{C}(c, a).$$

Associativity: For any objects $a, b, c, d \in \text{Ob}(\mathcal{C})$ and morphisms $f : a \longrightarrow b$, $g : b \longrightarrow c$, and $h : c \longrightarrow d$, there is an equality of morphisms

$$(h \circ g) \circ f = h \circ (g \circ f)$$

in $\mathcal{C}(a, d)$.

Example 2.2.2. Here are some basic examples of categories. In each case, the identity morphisms and the composition are the obvious ones.

- (1) There is an empty category with no objects and no morphisms.
- (2) There is a category $*$ with only one object $*$ and only the identity morphism of $*$.
- (3) There is a category Fin whose objects are finite sets and whose morphisms are functions between finite sets. Given any finite sets X_1, \dots, X_n , their *coproduct* $\coprod_{i=1}^n X_i$ is the finite set given by their disjoint union. If $n = 0$ then the coproduct is defined as the empty set \emptyset .
- (4) There is a category Set whose objects are sets and whose morphisms are functions between sets.

In what follows, if the identity morphisms and the composition are obvious, then we will omit mentioning them.

For wiring diagrams, we will usually consider finite sets in which each element is allowed to carry a value of some kind. The precise notion is given in the following definition.

Definition 2.2.3. Suppose S is a non-empty class, and Fin is the category of finite sets and functions between them.

- (1) Denote by Fin_S the category in which:
 - an object is a pair (X, v) with $X \in \text{Fin}$ and $v : X \longrightarrow S$ a function;

- a map $(X, v_X) \longrightarrow (Y, v_Y)$ is a function $X \longrightarrow Y$ such that the diagram

$$\begin{array}{ccc} X & \longrightarrow & Y \\ & \searrow v_X & \downarrow v_Y \\ & & S \end{array} \quad (2.2.3.1)$$

is commutative.

- (2) An object $(X, v) \in \text{Fin}_S$ is called an *S-finite set*.
- (3) For $(X, v) \in \text{Fin}_S$, we call v the *value assignment* for X . For each $x \in X$, $v(x) \in S$ is called the *value of x* .
- (4) If $(X_i, v_i) \in \text{Fin}_S$ for $1 \leq i \leq n$, then their *coproduct* $X = \coprod_{i=1}^n X_i \in \text{Fin}_S$ has value assignment $\coprod_{i=1}^n v_i$.
- (5) The empty S -finite set is denoted by \emptyset .

Definition 2.2.4. Suppose S is a non-empty class.

- (1) An *S-box* is a pair $X = (X^{\text{in}}, X^{\text{out}}) \in \text{Fin}_S \times \text{Fin}_S$. If S is clear from the context, then we will drop S and call X a *box*.
 - An element of X^{in} is called an *input* of X .
 - An element of X^{out} is called an *output* of X .
 - We write $v = v_X : X^{\text{in}} \sqcup X^{\text{out}} \longrightarrow S$ for the value assignment for X .
- (2) The class of S -boxes is denoted by Box_S .
- (3) The empty S -box, denoted by \emptyset , is the S -box with $\emptyset^{\text{in}} = \emptyset^{\text{out}}$ the empty set.

Convention 2.2.5. From now on, whenever Fin_S or Box_S is used, we always assume that the class S is non-empty.

Remark 2.2.6. In [Spi15] (Def. 3.1) an S -box is called a *signed finite set*. It is a slight generalization of what appears in [RS13, VSL14]. In [RS13] S is the class of pointed sets, where an S -box is called a *black box*. In [VSL14] S is a set of representatives of isomorphism classes of second-countable smooth manifolds and smooth maps, or more generally the class of objects in a category with finite products.

Convention 2.2.7. For the purpose of visualization, an S -box X will be drawn as follows.

$$\begin{array}{ccc} X^{\text{in}} & & X^{\text{out}} \\ \begin{array}{c} \longrightarrow \\ \longrightarrow \\ \longrightarrow \end{array} & \boxed{X} & \begin{array}{c} \longrightarrow \\ \longrightarrow \\ \longrightarrow \end{array} \end{array} \quad \text{or} \quad \begin{array}{c} \Rightarrow \\ \boxed{X} \\ \Rightarrow \end{array} \quad (2.2.7.1)$$

On the left, the inputs of X are depicted as arrows going into the box, and the outputs of X are depicted as arrows leaving the box. Alternatively, if we do not need to specify the sizes of X^{in} and X^{out} , then we depict them using a generic arrow \Rightarrow , as in the picture on the right. The value of each $x \in X^{\text{in}} \sqcup X^{\text{out}}$ is either not depicted in the picture for simplicity, or it is written near the corresponding arrow.

Definition 2.2.8. Suppose X_1, \dots, X_n are S -boxes for some $n \geq 0$. Define the S -box $X = \coprod_{i=1}^n X_i$, called the *coproduct*, as follows.

- (1) If $n = 0$, then $X = \emptyset$, the empty S -box.
- (2) If $n \geq 1$, then:

$$X^{\text{in}} = \coprod_{i=1}^n X_i^{\text{in}}, \quad X^{\text{out}} = \coprod_{i=1}^n X_i^{\text{out}}, \quad \text{and} \quad v_X = \coprod_{i=1}^n v_{X_i}.$$

Wiring diagrams will be defined as equivalence classes of prewiring diagrams, as defined below. The reader may want to go to (2.2.14.1) to see a concrete example of a wiring diagram before reading the following definition.

Definition 2.2.9. Suppose S is a class. An S -prewiring diagram is a tuple

$$\varphi = (\underline{X}, Y, \text{DN}, v, s) \tag{2.2.9.1}$$

consisting of the following data.

- (1) $Y = (Y^{\text{in}}, Y^{\text{out}}) \in \text{Box}_S$, called the *output box* of φ .
 - An element in Y^{in} is called a *global input* for φ .
 - An element in Y^{out} is called a *global output* for φ .
- (2) $\underline{X} = (X_1, \dots, X_n)$ is a Box_S -profile for some $n \geq 0$; i.e., each $X_i \in \text{Box}_S$.
 - We call X_i the *i th input box* of φ .
 - Denote by $X = \coprod_{i=1}^n X_i \in \text{Box}_S$ the coproduct.
- (3) $(\text{DN}, v) \in \text{Fin}_S$ is an S -finite set. An element of DN is called a *delay node*. Define:
 - $\text{Dm} = Y^{\text{out}} \sqcup X^{\text{in}} \sqcup \text{DN} \in \text{Fin}_S$. An element of Dm is called a *demand wire* in φ .
 - $\text{Sp} = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN} \in \text{Fin}_S$. An element of Sp is called a *supplier wire* in φ .
 Furthermore:
 - When DN is regarded as a subset of Dm , an element in $X^{\text{in}} \sqcup \text{DN}$ is called an *internal input* for φ .
 - When DN is regarded as a subset of Sp , an element in $X^{\text{out}} \sqcup \text{DN}$ is called an *internal output* for φ .

- (4) With a slight abuse of notation, we write

$$\text{Dm} \coprod_{\text{DN}} \text{Sp} = Y^{\text{in}} \sqcup Y^{\text{out}} \sqcup X^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN} \xrightarrow{v} S$$

for the coproduct of the value assignments for X , Y , and DN .

- (5) $s : \text{Dm} \longrightarrow \text{Sp} \in \text{Fin}_S$ is a map, called the *supplier assignment* for φ , such that

$$y \in Y^{\text{out}} \subseteq \text{Dm} \quad \text{implies} \quad s(y) \in \text{Sp} \setminus Y^{\text{in}} = X^{\text{out}} \sqcup \text{DN}. \tag{2.2.9.2}$$

- The condition (2.2.9.2) is called the *non-instantaneity requirement*.
- For $w \in \text{Dm}$, we call $s(w) \in \text{Sp}$ the *supplier* or the *supply wire* of w . So non-instantaneity says that the supply wire of a global output cannot be a global input.
- A supply wire $w \in Y^{\text{in}}$ that does not belong to the image of the supplier assignment s is called an *external wasted wire*. The set of external wasted wires in φ is denoted by φ_-^{w} .
- A supply wire $w \in X^{\text{out}} \sqcup \text{DN}$ that does not belong to the image of the supplier assignment s is called an *internal wasted wire*. The set of internal wasted wires in φ is denoted by φ_+^{w} .

If S is clear from the context, then we will drop S and call φ a *prewiring diagram*. If we need to emphasize φ , then we will use subscripts such as Dm_φ , $\text{Sp}_{\varphi'}$, and s_φ .

Remark 2.2.10. In the constructions that follow, the compatibility of the value assignments with the various supplier assignments are usually immediate because, in each prewiring diagram, the supplier assignment $s : \text{Dm} \longrightarrow \text{Sp}$ is a map in Fin_S . Therefore, we will omit checking such compatibility.

Definition 2.2.11. Suppose S is a class, $\varphi = (\underline{X}, Y, \text{DN}, v, s)$ is an S -prewiring diagram as in (2.2.9.1), and $\varphi' = (\underline{X}, Y, \text{DN}', v', s')$ is another S -prewiring diagram with the same input boxes \underline{X} and output box Y .

- (1) An *equivalence* $f : \varphi \longrightarrow \varphi'$ is an isomorphism $f_0 : (\text{DN}, v) \longrightarrow (\text{DN}', v') \in \text{Fin}_S$ such that the diagram

$$\begin{array}{ccc} Y^{\text{out}} \sqcup X^{\text{in}} \sqcup \text{DN} = \text{Dm}_\varphi & \xrightarrow{\text{Id} \sqcup \text{Id} \sqcup f_0} & \text{Dm}_{\varphi'} = Y^{\text{out}} \sqcup X^{\text{in}} \sqcup \text{DN}' \\ \downarrow s_\varphi & & \downarrow s_{\varphi'} \\ Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN} = \text{Sp}_\varphi & \xrightarrow{\text{Id} \sqcup \text{Id} \sqcup f_0} & \text{Sp}_{\varphi'} = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}' \end{array}$$

in Fin_S is commutative.

- (2) We say that φ and φ' are *equivalent* if there exists an equivalence $\varphi \longrightarrow \varphi'$.
- (3) An *S-wiring diagram* is an equivalence class of S -prewiring diagrams. If S is clear from the context, we will drop S and just say *wiring diagram*.
- (4) The class of S -wiring diagrams with input boxes $\underline{X} = (X_1, \dots, X_n)$ and output box Y is denoted by


$$\text{WD}(\underline{X}) \quad \text{or} \quad \text{WD}(X_1, \dots, X_n, Y). \quad (2.2.11.1)$$

The class of all S -wiring diagrams is denoted by WD . If we want to emphasize S , then we will write WD^S .

Convention 2.2.12. To simplify the presentation, we usually suppress the difference between a prewiring diagram and a wiring diagram. Each wiring diagram has a unique representative in which:

- each delay node is an element in S ;
- $v : \text{DN} \longrightarrow S$ sends each delay node to itself.

Unless otherwise specified, in the rest of this book, we will always use this representative of a wiring diagram. For a wiring diagram $\varphi \in \text{WD}(\underline{X})$, we will sometimes draw it as




without drawing the input boxes \underline{X} .

Remark 2.2.13. Def. 2.2.11 of an S -wiring diagram is a slight generalization of the one given in [RS13], where S was taken to be the class of pointed sets. Note that when S is a proper class (e.g., the class of pointed sets), the collection $\text{WD}(\underline{X})$ (2.2.11.1) is also a proper class, not a set. This is the reason why in Def. 2.1.2 we allow $\text{O}(\underline{d})$ to be a class, in contrast to what was stated in [RS13] (Def. 2.1.2B).

Example 2.2.14. Suppose S is a non-empty class and:

- $X^{\text{in}} = \{x_1, x_1, x_3\}$, $X^{\text{out}} = \{x^1, x^2\}$, $Y^{\text{in}} = \{y_1, y_2\}$, $Y^{\text{out}} = \{y^1, y^2, y^3\}$, and $\text{DN} = \{d\}$;
- $v(x_2) = v(x_3) = v(y_1) = v(y^2) = v(y^3) = v(d) \in S$;
- $v(x_1) = v(x^1) = v(y^1) \in S$, and $v(x^2)$ and $v(y_2)$ in S are arbitrary;
- $s(x_1) = s(y^1) = x^1$, $s(x_2) = s(d) = y_1$, and $s(x_3) = s(y^2) = s(y^3) = d$.

Then the above data defines a wiring diagram $\varphi \in \text{WD}(\underline{X})$ with one input box X and output box Y , which can be depicted as follows:



(2.2.14.1)

The output box Y is drawn as the outermost box. The single input box X is the smaller box. The delay node d is drawn as a circle, which will be our convention from now on. The supply wires $y_2 \in Y^{\text{in}}$ and $x^2 \in X^{\text{out}}$ are not in the image of the supplier assignment $s : \text{Dm} \longrightarrow \text{Sp}$, so y_2 (resp., x^2) is an external (resp., internal) wasted wire.

2.3. Operad Structure

Throughout this section, S denotes a class. In this section, using Def. 2.1.4 of a colored operad, we define the colored operad structure on the collection WD of S -wiring diagrams (Def. 2.2.11).

Definition 2.3.1 (Equivariance in WD). Suppose $Y \in \text{Box}_S$, \underline{X} is a Box_S -profile of length n , and $\sigma \in \Sigma_n$ is a permutation. Define the function

$$\text{WD}_{(X_1, \dots, X_n)}^Y = \text{WD}_{(\underline{X})}^Y \xrightarrow[\cong]{\sigma} \text{WD}_{(\underline{X}\sigma)}^Y = \text{WD}_{(X_{\sigma(1)}, \dots, X_{\sigma(n)})}^Y \quad (2.3.1.1)$$

by sending $\varphi = (\text{DN}, v, s) \in \text{WD}_{(\underline{X})}^Y$ to $\varphi = (\text{DN}, v, s) \in \text{WD}_{(\underline{X}\sigma)}^Y$, using the fact that $\coprod_{i=1}^n X_i = \coprod_{i=1}^n X_{\sigma(i)} \in \text{Box}_S$.

In other words, the equivariant structure is given by permuting the labels of the input boxes.

Definition 2.3.2 (Units in WD). For each $Y \in \text{Box}_S$, the Y -colored unit is defined as the wiring diagram

$$\mathbb{1}_Y = (\text{DN} = \emptyset, s = \text{Id}) \in \text{WD}_{(Y)}^Y \quad (2.3.2.1)$$


with:

- no delay nodes and trivial $v : \text{DN} \rightarrow S$;
- supplier assignment

$$\text{Dm} = Y^{\text{out}} \sqcup Y^{\text{in}} \xrightarrow{\text{Id}} Y^{\text{in}} \sqcup Y^{\text{out}} = \text{Sp}$$


the identity function.

The Y -colored unit can be depicted as follows.



Next we define the \circ_i composition (2.1.4.1) in WD . Pictorially, the \circ_i composition $\varphi \circ_i \psi$ in WD replaces the i th input box X_i in φ with the wiring diagram ψ , using X_i^{in} and X_i^{out} for the necessary wire connections. Here is a picture to keep in

mind for $\varphi \circ_i \psi$.



For simplicity we did not draw any delay nodes. In the actual definition below, we will take the disjoint union of the sets of delay nodes in φ and ψ .

Definition 2.3.3 (\circ_i -Composition in WD). Suppose:

- $\varphi = (\text{DN}_\varphi, \nu_\varphi, \mathcal{S}_\varphi) \in \text{WD}(\underline{X})$ with $\underline{X} = (X_1, \dots, X_n)$, $n \geq 1$, and $1 \leq i \leq n$;
- $\psi = (\text{DN}_\psi, \nu_\psi, \mathcal{S}_\psi) \in \text{WD}(\underline{W})$ with $|\underline{W}| = r \geq 0$.

Define the wiring diagram

$$\varphi \circ_i \psi \in \text{WD}(\underline{X \circ_i W})$$

as follows, where the Box_S -profile

$$\underline{X \circ_i W} = (X_1, \dots, X_{i-1}, \underline{W}, X_{i+1}, \dots, X_n)$$

is as in (2.1.4.2).

- (1) $\text{DN}_{\varphi \circ_i \psi} = \text{DN}_\varphi \sqcup \text{DN}_\psi \in \text{Fin}_S$, so $\nu_{\varphi \circ_i \psi} = \nu_\varphi \sqcup \nu_\psi$.

(2) The supplier assignment for $\varphi \circ_i \psi$,

$$\begin{aligned} \text{Dm}_{\varphi \circ_i \psi} &= Y^{\text{out}} \sqcup \coprod_{j \neq i} X_j^{\text{in}} \sqcup \coprod_{k=1}^r W_k^{\text{in}} \sqcup \text{DN}_{\varphi} \sqcup \text{DN}_{\psi} \\ &\quad \downarrow s_{\varphi \circ_i \psi} \\ \text{Sp}_{\varphi \circ_i \psi} &= Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup \coprod_{k=1}^r W_k^{\text{out}} \sqcup \text{DN}_{\varphi} \sqcup \text{DN}_{\psi} \end{aligned} \quad (2.3.3.1)$$

in which the coproduct $\coprod_{j \neq i}$ is indexed by all $j \in \{1, \dots, i-1, i+1, \dots, n\}$, is defined as follows. Suppose $z \in \text{Dm}_{\varphi \circ_i \psi}$.

(a) If $z \in Y^{\text{out}} \sqcup \coprod_{j \neq i} X_j^{\text{in}} \sqcup \text{DN}_{\varphi} \subseteq \text{Dm}_{\varphi}$, then

$$s_{\varphi \circ_i \psi}(z) = \begin{cases} s_{\varphi}(z) & \text{if } s_{\varphi}(z) \notin X_i^{\text{out}}; \\ s_{\psi} s_{\varphi}(z) & \text{if } s_{\varphi}(z) \in X_i^{\text{out}}. \end{cases} \quad (2.3.3.2)$$

(b) If $z \in \coprod_{k=1}^r W_k^{\text{in}} \sqcup \text{DN}_{\psi} \subseteq \text{Dm}_{\psi}$, then

$$s_{\varphi \circ_i \psi}(z) = \begin{cases} s_{\psi}(z) & \text{if } s_{\psi}(z) \notin X_i^{\text{in}}; \\ s_{\varphi} s_{\psi}(z) & \text{if } s_{\psi}(z) \in X_i^{\text{in}} \text{ and } s_{\varphi} s_{\psi}(z) \notin X_i^{\text{out}}; \\ s_{\psi} s_{\varphi} s_{\psi}(z) & \text{if } s_{\psi}(z) \in X_i^{\text{in}} \text{ and } s_{\varphi} s_{\psi}(z) \in X_i^{\text{out}}. \end{cases} \quad (2.3.3.3)$$

This finishes the definition of $\varphi \circ_i \psi$.

Lemma 2.3.4. *Def. 2.3.3 indeed defines a wiring diagram $\varphi \circ_i \psi$ in $\text{WD}(\underline{X \circ_i W})$.*

Proof. We need to check that the supplier assignment for $\varphi \circ_i \psi$ satisfies the non-instantaneity requirement (2.2.9.2). So suppose $y \in Y^{\text{out}}$. We must show that $s_{\varphi \circ_i \psi}(y) \notin Y^{\text{in}}$. By (2.3.3.2) we have

$$s_{\varphi \circ_i \psi}(y) = \begin{cases} s_{\varphi}(y) \in \coprod_{j \neq i} X_j^{\text{out}} \sqcup \text{DN}_{\varphi} & \text{if } s_{\varphi}(y) \notin X_i^{\text{out}}; \\ s_{\psi} s_{\varphi}(y) \in \coprod_{k=1}^r W_k^{\text{out}} \sqcup \text{DN}_{\psi} & \text{if } s_{\varphi}(y) \in X_i^{\text{out}}. \end{cases}$$


Here we have used the non-instantaneity requirement for both φ and ψ . So in either case we have that $s_{\varphi \circ_i \psi}(y) \notin Y^{\text{in}}$. \square

Many examples of the \circ_i -composition in WD will be given in Chapter 3. We now prove that, equipped with the structure above, WD is a colored operad.

Lemma 2.3.5. *The \circ_i -composition in Def. 2.3.3 satisfies the left unity axiom (2.1.4.5), the right unity axiom (2.1.4.6), and the equivariance axiom (2.1.4.7).*

Proof. This follows from a direct inspection of the definitions of the equivariant structure (2.3.1.1) and the colored units in WD (2.3.2.1). \square

Next we show that WD satisfies the associativity axioms (2.1.4.3) and (2.1.4.4). For the horizontal associativity axiom (2.1.4.3), one should keep in mind the following picture for the iterated operadic composition $(\varphi \circ_j \zeta) \circ_i \psi$.



Note that on the right side, ψ and ζ are depicted as gray boxes because their output boxes—namely Y_i and Y_j —are no longer input boxes in $(\varphi \circ_j \zeta) \circ_i \psi$. Furthermore, for simplicity the delay nodes are not drawn.

Lemma 2.3.6. *The \circ_i -composition in Def. 2.3.3 satisfies the horizontal associativity axiom (2.1.4.3).*

Proof. Suppose:

- $\varphi \in \text{WD}(\underline{Z})$ with $|\underline{Y}| = n \geq 2$ and $1 \leq i < j \leq n$;
- $\psi \in \text{WD}(\underline{Y})$ with $|\underline{W}| = l$;
- $\zeta \in \text{WD}(\underline{X})$ with $|\underline{X}| = m$.

We must show that

$$(\varphi \circ_j \zeta) \circ_i \psi = (\varphi \circ_i \psi) \circ_{j-1+i} \zeta \in \text{WD}(\underline{Z} \circ_{(\underline{Y} \circ_i \underline{X})} \underline{W}). \quad (2.3.6.1)$$

By Lemma 2.3.4 we already know that both sides are well-defined wiring diagrams in the indicated entry of WD. Moreover, both sides have $\text{DN}_\varphi \sqcup \text{DN}_\psi \sqcup \text{DN}_\zeta \in \text{Fin}_S$ as the set of delay nodes. So it remains to show that their supplier assignments are equal.

Note that both sides in (2.3.6.1) have demand wires

$$\text{Dm} = Z^{\text{out}} \sqcup \coprod_{p \neq i, j} Y_p^{\text{in}} \sqcup \coprod_{q=1}^l W_q^{\text{in}} \sqcup \coprod_{r=1}^m X_r^{\text{in}} \sqcup \text{DN}_\varphi \sqcup \text{DN}_\psi \sqcup \text{DN}_\zeta$$

in which the coproduct $\coprod_{p \neq i, j}$ is indexed by all $1 \leq p \leq n$ such that $p \neq i, j$. Similarly, both sides in (2.3.6.1) have supply wires

$$\text{Sp} = Z^{\text{in}} \sqcup \coprod_{p \neq i, j} Y_p^{\text{out}} \sqcup \coprod_{q=1}^l W_q^{\text{out}} \sqcup \coprod_{r=1}^m X_r^{\text{out}} \sqcup \text{DN}_\varphi \sqcup \text{DN}_\psi \sqcup \text{DN}_\zeta.$$

Using the definitions (2.3.3.2) and (2.3.3.3), it follows from direct inspection that both sides in (2.3.6.1) have the following supplier assignment $s : \text{Dm} \longrightarrow \text{Sp}$.

(1) If $v \in Z^{\text{out}} \sqcup \coprod_{p \neq i, j} Y_p^{\text{in}} \sqcup \text{DN}_\varphi \subseteq \text{Dm}_\varphi$, then

$$s(v) = \begin{cases} s_\varphi(v) & \text{if } s_\varphi(v) \notin Y_i^{\text{out}} \sqcup Y_j^{\text{out}}; \\ s_\psi s_\varphi(v) & \text{if } s_\varphi(v) \in Y_i^{\text{out}}; \\ s_\zeta s_\varphi(v) & \text{if } s_\varphi(v) \in Y_j^{\text{out}}. \end{cases}$$

(2) If $v \in \coprod_{q=1}^l W_q^{\text{in}} \sqcup \text{DN}_\psi \subseteq \text{Dm}_\psi$, then


$$s(v) = \begin{cases} s_\psi(v) & \text{if } s_\psi(v) \notin Y_i^{\text{in}}; \\ s_\varphi s_\psi(v) & \text{if } s_\psi(v) \in Y_i^{\text{in}} \text{ and } s_\varphi s_\psi(v) \notin Y_i^{\text{out}} \sqcup Y_j^{\text{out}}; \\ s_\psi s_\varphi s_\psi(v) & \text{if } s_\psi(v) \in Y_i^{\text{in}} \text{ and } s_\varphi s_\psi(v) \in Y_i^{\text{out}}; \\ s_\zeta s_\varphi s_\psi(v) & \text{if } s_\psi(v) \in Y_i^{\text{in}} \text{ and } s_\varphi s_\psi(v) \in Y_j^{\text{out}}. \end{cases}$$

(3) Finally, if $v \in \coprod_{r=1}^m X_r^{\text{in}} \sqcup \text{DN}_\zeta \subseteq \text{Dm}_\zeta$, then

$$s(v) = \begin{cases} s_\zeta(v) & \text{if } s_\zeta(v) \notin Y_j^{\text{in}}; \\ s_\varphi s_\zeta(v) & \text{if } s_\zeta(v) \in Y_j^{\text{in}} \text{ and } s_\varphi s_\zeta(v) \notin Y_i^{\text{out}} \sqcup Y_j^{\text{out}}; \\ s_\psi s_\varphi s_\zeta(v) & \text{if } s_\zeta(v) \in Y_j^{\text{in}} \text{ and } s_\varphi s_\zeta(v) \in Y_i^{\text{out}}; \\ s_\zeta s_\varphi s_\zeta(v) & \text{if } s_\zeta(v) \in Y_j^{\text{in}} \text{ and } s_\varphi s_\zeta(v) \in Y_j^{\text{out}}. \end{cases}$$

This finishes the proof of the desired equality (2.3.6.1). \square

For the vertical associativity axiom, one should keep the following picture of $\varphi \circ_i (\psi \circ_j \zeta)$ in mind.



Once again on the right side, ζ is depicted as a gray box because its output box X_j is no longer an input box in $\varphi \circ_i (\psi \circ_j \zeta)$. Furthermore, for simplicity the delay nodes are not drawn.

Lemma 2.3.7. *The \circ_i -composition in Def. 2.3.3 satisfies the vertical associativity axiom (2.1.4.4).*

Proof. Suppose:

- $\varphi \in \text{WD}(\frac{Z}{Y})$ with $|Y| = n \geq 1$ and $1 \leq i \leq n$;
- $\psi \in \text{WD}(\frac{Y_j}{X})$ with $|X| = m \geq 1$ and $1 \leq j \leq m$;
- $\zeta \in \text{WD}(\frac{X_j}{W})$ with $|W| = l$.

We must show that

$$(\varphi \circ_i \psi) \circ_{i-1+j} \zeta = \varphi \circ_i (\psi \circ_j \zeta) \in \text{WD}(\frac{Z}{(Y \circ_i X) \circ_{i-1+j} W}). \quad (2.3.7.1)$$

By Lemma 2.3.4 we already know that both sides are well-defined wiring diagrams in the indicated entry of WD. Moreover, both sides have $\text{DN}_\varphi \sqcup \text{DN}_\psi \sqcup \text{DN}_\zeta \in \text{Fin}_S$ as the set of delay nodes. So it remains to show that their supplier assignments are equal.

Note that both sides in (2.3.7.1) have demand wires

$$\text{Dm} = Z^{\text{out}} \sqcup \coprod_{p \neq i} Y_p^{\text{in}} \sqcup \coprod_{q \neq j} X_q^{\text{in}} \sqcup \coprod_{r=1}^l W_r^{\text{in}} \sqcup \text{DN}_\varphi \sqcup \text{DN}_\psi \sqcup \text{DN}_\zeta$$

in which $\coprod_{p \neq i}$ is indexed by all $1 \leq p \leq n$ such that $p \neq i$, and $\coprod_{q \neq j}$ is indexed by all $1 \leq q \leq m$ such that $q \neq j$. Similarly, both sides in (2.3.7.1) have supply wires

$$\text{Sp} = Z^{\text{in}} \sqcup \coprod_{p \neq i} Y_p^{\text{out}} \sqcup \coprod_{q \neq j} X_q^{\text{out}} \sqcup \coprod_{r=1}^l W_r^{\text{out}} \sqcup \text{DN}_\varphi \sqcup \text{DN}_\psi \sqcup \text{DN}_\zeta.$$

Using the definitions (2.3.3.2) and (2.3.3.3), it follows from direct inspection that both sides in (2.3.7.1) have the following supplier assignment $s : \text{Dm} \longrightarrow \text{Sp}$.

(1) If $v \in Z^{\text{out}} \sqcup \coprod_{p \neq i} Y_p^{\text{in}} \sqcup \text{DN}_\varphi \subseteq \text{Dm}_\varphi$, then

$$s(v) = \begin{cases} s_\varphi(v) & \text{if } s_\varphi(v) \notin Y_i^{\text{out}}; \\ s_\psi s_\varphi(v) & \text{if } s_\varphi(v) \in Y_i^{\text{out}} \text{ and } s_\psi s_\varphi(v) \notin X_j^{\text{out}}; \\ s_\zeta s_\psi s_\varphi(v) & \text{if } s_\varphi(v) \in Y_i^{\text{out}} \text{ and } s_\psi s_\varphi(v) \in X_j^{\text{out}}. \end{cases}$$

(2) If $v \in \coprod_{q \neq j} X_q^{\text{in}} \sqcup \text{DN}_\psi \subseteq \text{Dm}_\psi$, then

$$s(v) = \begin{cases} s_\psi(v) & \text{if } s_\psi(v) \notin X_j^{\text{out}} \sqcup Y_i^{\text{in}}; \\ s_\zeta s_\psi(v) & \text{if } s_\psi(v) \in X_j^{\text{out}}; \\ s_\varphi s_\psi(v) & \text{if } s_\psi(v) \in Y_i^{\text{in}} \text{ and } s_\varphi s_\psi(v) \notin Y_i^{\text{out}}; \\ s_\psi s_\varphi s_\psi(v) & \text{if } s_\psi(v) \in Y_i^{\text{in}}, s_\varphi s_\psi(v) \in Y_i^{\text{out}}, \text{ and } s_\psi s_\varphi s_\psi(v) \notin X_j^{\text{out}}; \\ s_\zeta s_\psi s_\varphi s_\psi(v) & \text{if } s_\psi(v) \in Y_i^{\text{in}}, s_\varphi s_\psi(v) \in Y_i^{\text{out}}, \text{ and } s_\psi s_\varphi s_\psi(v) \in X_j^{\text{out}}. \end{cases}$$

(3) If $v \in \coprod_{r=1}^l W_r^{\text{in}} \sqcup \text{DN}_\zeta \subseteq \text{Dm}_\zeta$, then

$$s(v) = \begin{cases} s_\zeta(v) & \text{if } s_\zeta(v) \notin X_j^{\text{in}}; \\ s_\psi s_\zeta(v) & \text{if } s_\zeta(v) \in X_j^{\text{in}} \text{ and } s_\psi s_\zeta(v) \notin X_j^{\text{out}} \sqcup Y_i^{\text{in}}; \\ s_\zeta s_\psi s_\zeta(v) & \text{if } s_\zeta(v) \in X_j^{\text{in}} \text{ and } s_\psi s_\zeta(v) \in X_j^{\text{out}}; \\ s_\varphi s_\psi s_\zeta(v) & \text{if } s_\zeta(v) \in X_j^{\text{in}}, s_\psi s_\zeta(v) \in Y_i^{\text{in}}, \text{ and } s_\varphi s_\psi s_\zeta(v) \notin Y_i^{\text{out}}; \\ s_\psi s_\varphi s_\psi s_\zeta(v) & \text{if } s_\zeta(v) \in X_j^{\text{in}}, s_\psi s_\zeta(v) \in Y_i^{\text{in}}, s_\varphi s_\psi s_\zeta(v) \in Y_i^{\text{out}}, \text{ and } s_\psi s_\varphi s_\psi s_\zeta(v) \notin X_j^{\text{out}}; \\ s_\zeta s_\psi s_\varphi s_\psi s_\zeta(v) & \text{if } s_\zeta(v) \in X_j^{\text{in}}, s_\psi s_\zeta(v) \in Y_i^{\text{in}}, s_\varphi s_\psi s_\zeta(v) \in Y_i^{\text{out}}, \text{ and } s_\psi s_\varphi s_\psi s_\zeta(v) \in X_j^{\text{out}}. \end{cases}$$

This finishes the proof of the desired equality (2.3.7.1). \square

Theorem 2.3.8. For any class S , when equipped with the structure in Def. 2.3.1–2.3.3, WD in Def. 2.2.11 is a Box_S -colored operad, called the operad of wiring diagrams.

Proof. In view of Def. 2.1.4, this follows from Lemmas 2.3.5, 2.3.6, and 2.3.7. \square

Remark 2.3.9. When S is the class of pointed sets, Theorem 2.3.8 is proved in [RS13] (section 2). The proof in [RS13] is somewhat different than ours because it uses Def. 2.1.2 of a colored operad instead of Def. 2.1.4.

Generators and Relations

Fix a class S . The purpose of this chapter is to describe a finite number of wiring diagrams that we will later show to be sufficient to describe the entire operad WD of wiring diagrams (Theorems 5.2.10) as well as its variants WD_\bullet (Theorem 5.3.7) and WD_0 (Theorem 5.4.8). One may also regard this chapter as consisting of a long list of examples of wiring diagrams.

In Section 3.1 we describe eight wiring diagrams, called the *generating wiring diagrams*. In Theorem 5.1.7 we will show that they generate the operad WD of wiring diagrams. This means that every wiring diagram can be obtained from finitely many generating wiring diagrams via iterated operadic compositions. For now one may think of the generating wiring diagrams as examples of wiring diagrams.

In Section 3.2 we explain why a wiring diagram with an internal wasted wire is not among the generating wiring diagrams. More concretely, we will observe in Prop. 3.2.2 that an internal wasted wire can be generated using two generating wiring diagrams.

In Section 3.3 we describe 28 *elementary relations* among the generating wiring diagrams. In Theorem 5.2.10 we will show that these elementary relations together with the operad associativity and unity axioms—(2.1.4.3), (2.1.4.4), (2.1.4.5), and (2.1.4.6)—for the generating wiring diagrams generate *all* the relations in the operad WD of wiring diagrams. In other words, suppose an arbitrary wiring diagram can be built in two ways using the generating wiring diagrams. Then there exists a finite sequence of steps connecting them in which each step is given by one of the 28 elementary relations or an operad associativity/unity axiom for the generating wiring diagrams. For now one may think of the elementary relations as examples of the operadic composition in the operad WD .


3.1. Generating Wiring Diagrams

Recall the definition of a wiring diagram (Def. 2.2.11). In this section, we introduce 8 wiring diagrams, called the generating wiring diagrams. They will be used in later chapters to give a finite presentation for the operad WD of wiring diagrams.

Definition 3.1.1. Define the *empty wiring diagram* $\epsilon \in \text{WD}^{(\emptyset)}$ with:

- (1) no input boxes;
- (2) the empty box \emptyset (Def. 2.2.4) as the output box;
- (3) no delay nodes (i.e., $\text{DN} = \emptyset$);
- (4) supplier assignment $s : \text{Dm} = \emptyset \longrightarrow \emptyset = \text{Sp}$ the trivial function.

The next wiring diagram has a delay node as depicted in the following picture, where we use the convention that delay nodes are drawn as circles as in (2.2.14.1).




Definition 3.1.2. Suppose $d \in S$. Denote also by $d \in \text{Box}_S$ the box with one input and one output, both also denoted by d and have values $d \in S$. Define the *1-delay node* $\delta_d \in \text{WD}^{(d)}$ as the wiring diagram with:

- (1) no input boxes;
- (2) the output box $d = (\{d\}, \{d\})$, in which both d 's have values $d \in S$;
- (3) $\text{DN} = \{d\}$, in which d has value $d \in S$;
- (4) supplier assignment

$$\text{Dm} = Y^{\text{out}} \sqcup \text{DN} = \{d\} \sqcup \{d\} \xrightarrow{s} \{d\} \sqcup \{d\} = Y^{\text{in}} \sqcup \text{DN} = \text{Sp}$$

the identity function that takes $d \in Y^{\text{out}}$ to $d \in \text{DN}$ and $d \in \text{DN}$ to $d \in Y^{\text{in}}$.

Next we define the wiring diagram:



Definition 3.1.3. Suppose $X, Y \in \text{Box}_S$ together with isomorphisms $f^{\text{in}} : X^{\text{in}} \cong Y^{\text{in}}$ and $f^{\text{out}} : Y^{\text{out}} \cong X^{\text{out}}$ in Fin_S . Define the wiring diagram $\tau_f \in \text{WD}^{(Y)}$ with:

- (1) one input box X and output box Y ;


- (2) no delay nodes;
- (3) supplier assignment

$$\text{Dm} = Y^{\text{out}} \sqcup X^{\text{in}} \xrightarrow{s = f^{\text{in}} \sqcup f^{\text{out}}} Y^{\text{in}} \sqcup X^{\text{out}} = \text{Sp}$$

the coproduct of the given isomorphisms.

We will often suppress the given isomorphisms and simply write $\tau_{X,Y}$ or even τ , which will be called a *name change*.

Next we define the wiring diagram:



Definition 3.1.4. Suppose $X, Y \in \text{Box}_S$. Define the wiring diagram $\theta_{X,Y} \in \text{WD}(\begin{smallmatrix} X \sqcup Y \\ X, Y \end{smallmatrix})$ with:


- (1) two input boxes (X, Y) and output box $X \sqcup Y$;
- (2) no delay nodes;
- (3) supplier assignment

$$\text{Dm} = [X^{\text{out}} \sqcup Y^{\text{out}}] \sqcup [X^{\text{in}} \sqcup Y^{\text{in}}] \xrightarrow{s} [X^{\text{in}} \sqcup Y^{\text{in}}] \sqcup [X^{\text{out}} \sqcup Y^{\text{out}}] = \text{Sp}$$

the identity map.

We will call $\theta_{X,Y}$ a *2-cell*.

Next we define the wiring diagram:



Definition 3.1.5. Suppose:

- $X \in \text{Box}_S$, and $(x_+, x_-) \in X^{\text{out}} \times X^{\text{in}}$ such that $v(x_+) = v(x_-) \in S$.
- $X \setminus x \in \text{Box}_S$ is obtained from X by removing x_{\pm} , so $(X \setminus x)^{\text{in}} = X^{\text{in}} \setminus \{x_-\}$ and $(X \setminus x)^{\text{out}} = X^{\text{out}} \setminus \{x_+\}$.

Define the wiring diagram $\lambda_{X,x} \in \text{WD}(\begin{smallmatrix} X \setminus x \\ X \end{smallmatrix})$ with:


- (1) one input box X and output box $X \setminus x$;
- (2) no delay nodes;
- (3) supplier assignment

$$\begin{array}{c}
 \text{Dm} = \overbrace{[X^{\text{out}} \setminus \{x_+\}]}^{(X \setminus x)^{\text{out}}} \sqcup \overbrace{[X^{\text{in}} \setminus \{x_-\}]}^{X^{\text{in}}} \sqcup \{x_-\} \\
 \downarrow s \\
 \text{Sp} = \overbrace{[X^{\text{in}} \setminus \{x_-\}]}^{(X \setminus x)^{\text{in}}} \sqcup \overbrace{[X^{\text{out}} \setminus \{x_+\}]}^{X^{\text{out}}} \sqcup \{x_+\}
 \end{array}$$

given by $s(x_-) = x_+$ and the identity function everywhere else.

We will call the wiring diagram $\lambda_{X,x}$ a 1-loop.

Next we define the wiring diagram:



Definition 3.1.6. Suppose:

- $X \in \text{Box}_S$, and $x_1, x_2 \in X^{\text{in}}$ are distinct elements such that $v(x_1) = v(x_2) \in S$.
- $Y = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 , so $Y^{\text{in}} = X^{\text{in}}/(x_1 = x_2)$ and $Y^{\text{out}} = X^{\text{out}}$. The identified element of x_1 and x_2 in Y^{in} will be denoted by x_{12} .

Define the wiring diagram $\sigma_{X,x_1,x_2} \in \text{WD}(Y)$ with:


- (1) one input box X and output box Y ;
- (2) no delay nodes;
- (3) supplier assignment

$$\begin{array}{ccc}
 \text{Dm} = Y^{\text{out}} \sqcup X^{\text{in}} = X^{\text{out}} \sqcup X^{\text{in}} & \ni & x_1, x_2 \\
 \downarrow s & & \downarrow \\
 \text{Sp} = Y^{\text{in}} \sqcup X^{\text{out}} = \frac{X^{\text{in}}}{(x_1 = x_2)} \sqcup X^{\text{out}} & \ni & x_{12}
 \end{array}$$

that sends both $x_1, x_2 \in X^{\text{in}}$ to $x_{12} \in Y^{\text{in}}$ and is the identity function everywhere else.

We will call the wiring diagram σ_{X,x_1,x_2} an *in-split*.

Next we define the wiring diagram:



Definition 3.1.7. Suppose:

- $Y \in \text{Box}_S$, and $y_1, y_2 \in Y^{\text{out}}$ are distinct elements such that $v(y_1) = v(y_2) \in S$.
- $X = Y/(y_1 = y_2) \in \text{Box}_S$ is obtained from Y by identifying y_1 and y_2 , so $X^{\text{in}} = Y^{\text{in}}$ and $X^{\text{out}} = Y^{\text{out}}/(y_1 = y_2)$. The identified element of y_1 and y_2 in X^{out} will be denoted by y_{12} .

Define the wiring diagram $\sigma^{Y,y_1,y_2} \in \text{WD}(X)$ with:


- (1) one input box X and output box Y ;
- (2) no delay nodes;
- (3) supplier assignment

$$\begin{array}{ccc} \text{Dm} = Y^{\text{out}} \sqcup X^{\text{in}} = Y^{\text{out}} \sqcup Y^{\text{in}} & \ni & y_1, y_2 \\ \downarrow s & & \downarrow \\ \text{Sp} = Y^{\text{in}} \sqcup X^{\text{out}} = Y^{\text{in}} \sqcup \frac{Y^{\text{out}}}{(y_1 = y_2)} & \ni & y_{12} \end{array}$$

that sends both $y_1, y_2 \in Y^{\text{out}}$ to $y_{12} \in X^{\text{out}}$ and is the identity function everywhere else.

We will call the wiring diagram σ^{Y,y_1,y_2} an *out-split*.

Next we define the following wiring diagram with an external wasted wire:



Definition 3.1.8. Suppose:

- $Y \in \text{Box}_S$, and $y \in Y^{\text{in}}$.
- $X \in \text{Box}_S$ is obtained from Y by removing y , so $X^{\text{in}} = Y^{\text{in}} \setminus \{y\}$ and $X^{\text{out}} = Y^{\text{out}}$.

Define the wiring diagram $\omega_{Y,y} \in \text{WD}(X^Y)$ with:

- (1) one input box X and output box Y ;
- (2) no delay nodes;
- (3) supplier assignment

$$\begin{array}{c} \text{Dm} = Y^{\text{out}} \sqcup X^{\text{in}} = Y^{\text{out}} \sqcup [Y^{\text{in}} \setminus \{y\}] \\ \downarrow s \\ \text{Sp} = Y^{\text{in}} \sqcup X^{\text{out}} = Y^{\text{in}} \sqcup Y^{\text{out}} \end{array}$$

the inclusion.

We will call the wiring diagram $\omega_{Y,y}$ a *1-wasted wire*.


Definition 3.1.9. The eight wiring diagrams in Def. 3.1.1–3.1.8 will be referred to as *generating wiring diagrams*.

Remark 3.1.10. Among the generating wiring diagrams:

- (1) A 1-delay node δ_d (Def. 3.1.2) is the only wiring diagram that has a delay node.
- (2) A 1-wasted wire $\omega_{Y,y}$ (Def. 3.1.8) is the only wiring diagram that has an external wasted wire, namely $y \in Y^{\text{in}}$.
- (3) None has an internal wasted wire (Def. 2.2.9). As we will see in Prop. 3.2.2 below, an internal wasted wire can be generated using a 1-loop and a 1-wasted wire, hence is not needed as a generator.
- (4) The empty wiring diagram ϵ (Def. 3.1.1) and a 1-delay node δ_d are 0-ary elements in WD.
- (5) A name change τ (Def. 3.1.3), a 1-loop $\lambda_{X,x}$ (Def. 3.1.5), an in-split σ_{X,x_1,x_2} (Def. 3.1.6), an out-split σ^{Y,y_1,y_2} (Def. 3.1.7), and a 1-wasted wire $\omega_{Y,y}$ are unary elements in WD.
- (6) A 2-cell $\theta_{X,Y}$ (Def. 3.1.4) is a binary element in WD.

3.2. Internal Wasted Wires

Recall from Def. 2.2.9 that an *internal wasted wire* is an internal output, hence a supply wire, that does not belong to the image of the supplier assignment. The purpose of this section is to explain why the wiring diagram



that has an internal wasted wire x is not needed as a generating wiring diagram. First we define this wiring diagram.

Definition 3.2.1. Suppose:

- $X \in \text{Box}_S$, and $x \in X^{\text{out}}$.
- $Y = X \setminus \{x\} \in \text{Box}_S$ is obtained from X by removing x .

Define the wiring diagram $\omega^{X,x} \in \text{WD}(\frac{Y}{X})$ with:


- (1) one input box X and output box Y ;
- (2) no delay nodes;
- (3) supplier assignment

$$\begin{aligned} \text{Dm} &= Y^{\text{out}} \sqcup X^{\text{in}} = [X^{\text{out}} \setminus \{x\}] \sqcup X^{\text{in}} \\ &\quad \downarrow s \\ \text{Sp} &= Y^{\text{in}} \sqcup X^{\text{out}} = X^{\text{in}} \sqcup X^{\text{out}} \end{aligned}$$

the inclusion.

We will call the wiring diagram $\omega^{X,x}$ a *1-internal wasted wire*.

The following observation says that a 1-internal wasted wire can be obtained as the substitution of a 1-wasted wire into a 1-loop, both of which are generating wiring diagrams. This is expressed in the following picture



in which the intermediate gray box will be called W below.

Proposition 3.2.2. Suppose:

- $\omega^{X,x} \in \text{WD}(\frac{Y}{X})$ is a 1-internal wasted wire (Def. 3.2.1).
- $W = X \sqcup \{w\} \in \text{Box}_S$ such that $w \in W^{\text{in}}$ satisfies $v(w) = v(x) \in S$.

- $\lambda_{W,\{w,x\}} \in \text{WD}(\frac{Y}{W})$ is the 1-loop (Def. 3.1.5) in which $x \in X^{\text{out}} = W^{\text{out}}$ is the supply wire of $w \in W^{\text{in}}$.
- $\omega_{W,w} \in \text{WD}(\frac{W}{X})$ is a 1-wasted wire (Def. 3.1.8).

Then

$$(\lambda_{W,\{w,x\}}) \circ_1 (\omega_{W,w}) = \omega^{X,x} \in \text{WD}(\frac{Y}{X}). \quad (3.2.2.1)$$

Proof. By definition both sides of (3.2.2.1) belong to $\text{WD}(\frac{Y}{X})$ and have no delay nodes. It remains to check that their supplier assignments are equal. By the definitions of \circ_1 (Def. 2.3.3), 1-loop, and 1-wasted wire, the supplier assignment of the left side $(\lambda_{W,\{w,x\}}) \circ_1 (\omega_{W,w})$, namely

$$\begin{array}{c} \text{Dm} = Y^{\text{out}} \sqcup X^{\text{in}} = [X^{\text{out}} \setminus \{x\}] \sqcup X^{\text{in}} \\ \downarrow s \\ \text{Sp} = Y^{\text{in}} \sqcup X^{\text{out}} = X^{\text{in}} \sqcup X^{\text{out}} \end{array}$$

is the inclusion. By Def. 3.2.1 this is also the supplier assignment of the 1-internal wasted wire $\omega^{X,x}$. \square

As a consequence of (3.2.2.1), the 1-internal wasted wire $\omega^{X,x}$ is *not* needed as a generating wiring diagram.

3.3. Elementary Relations

The purpose of this section is to introduce 28 elementary relations among the generating wiring diagrams (Def. 3.1.9). Each elementary relation is proved by a simple inspection of the relevant definitions of the generating wiring diagrams and operadic compositions, similar to the proofs of Lemma 2.3.6, Lemma 2.3.7, and Prop. 3.2.2 above. Therefore, we will omit the proofs, providing a picture instead in most cases. We will frequently use the \circ_i -composition (2.1.4.1) in describing these elementary relations.

Notation 3.3.1. Suppose \mathcal{O} is an S -colored operad (Def. 2.1.4), and T is a set.

- (1) If $\varphi \in \mathcal{O}(\frac{d}{c})$ where the input profile (c) has length 1 and if $\phi \in \mathcal{O}(\frac{c}{b})$, then we write

$$\varphi \circ \phi = \varphi \circ_1 \phi. \quad (3.3.1.1)$$

- (2) Suppose $\varphi_1, \dots, \varphi_k \in \mathcal{O}$ such that each of $\varphi_1, \dots, \varphi_{k-1}$ belongs to an entry of \mathcal{O} whose input profile has length 1. Then we write

$$\varphi_1 \circ \dots \circ \varphi_k = \left(\dots (\varphi_1 \circ_1 \varphi_2) \circ_1 \dots \right) \circ_1 \varphi_k \quad (3.3.1.2)$$

whenever the right side is defined, in which each pair of parentheses starts on the left. For example, we have

$$\begin{aligned}\varphi_1 \circ \varphi_2 \circ \varphi_3 &= (\varphi_1 \circ_1 \varphi_2) \circ_1 \varphi_3, \\ \varphi_1 \circ \varphi_2 \circ \varphi_3 \circ \varphi_4 &= \left((\varphi_1 \circ_1 \varphi_2) \circ_1 \varphi_3 \right) \circ_1 \varphi_4.\end{aligned}$$

(3) Write $|T|$ for the cardinality of T .

The first six relations are about the name change wiring diagrams (Def. 3.1.3). The first relation says that two consecutive name changes can be composed into one name change.

Proposition 3.3.2. *Suppose:*

- $\tau_{Y,Z} \in \text{WD}(\overset{Z}{Y})$ and $\tau_{X,Y} \in \text{WD}(\overset{Y}{X})$ are name changes.
- $\tau_{X,Z} \in \text{WD}(\overset{Z}{X})$ is the name change given by composing the isomorphisms that define $\tau_{Y,Z}$ and $\tau_{X,Y}$.

Then

$$(\tau_{Y,Z}) \circ (\tau_{X,Y}) = \tau_{X,Z} \in \text{WD}(\overset{Z}{X}). \quad (3.3.2.1)$$

The next relation says that name changes inside a 2-cell (Def. 3.1.4) can be rewritten as a name change outside of a 2-cell.

Proposition 3.3.3. *Suppose:*

- $\tau_{X,X'} \in \text{WD}(\overset{X'}{X})$ and $\tau_{Y,Y'} \in \text{WD}(\overset{Y'}{Y})$ are name changes.
- $\tau_{X \sqcup Y, X' \sqcup Y'} \in \text{WD}(\overset{X' \sqcup Y'}{X \sqcup Y})$ is the name change induced by $\tau_{X,X'}$ and $\tau_{Y,Y'}$.
- $\theta_{X',Y'} \in \text{WD}(\overset{X' \sqcup Y'}{X',Y'})$ and $\theta_{X,Y} \in \text{WD}(\overset{X \sqcup Y}{X,Y})$ are 2-cells.

Then

$$\left(\theta_{X',Y'} \circ_1 \tau_{X,X'} \right) \circ_2 \tau_{Y,Y'} = \left(\tau_{X \sqcup Y, X' \sqcup Y'} \right) \circ (\theta_{X,Y}) \in \text{WD}(\overset{X' \sqcup Y'}{X,Y}). \quad (3.3.3.1)$$

The next relation says that a name change inside a 1-loop (Def. 3.1.5) can be rewritten as a name change of a 1-loop.

Proposition 3.3.4. *Suppose:*

- $X \in \text{Box}_S$, $(x_+, x_-) \in X^{\text{out}} \times X^{\text{in}}$ such that $v(x_+) = v(x_-) \in S$.
- $X \setminus x \in \text{Box}_S$ is obtained from X by removing x_{\pm} .
- $\lambda_{X,x} \in \text{WD}(\overset{X \setminus x}{X})$ is the corresponding 1-loop.
- $\tau_{X,Y} \in \text{WD}(\overset{Y}{X})$ is a name change such that $(y_+, y_-) \in Y^{\text{out}} \times Y^{\text{in}}$ corresponds to (x_+, x_-) .
- $\lambda_{Y,y} \in \text{WD}(\overset{Y \setminus y}{Y})$ is the corresponding 1-loop.

- $\tau_{X \setminus x, Y \setminus y} \in \text{WD}(\frac{Y \setminus y}{X \setminus x})$ is the name change induced by $\tau_{X, Y}$.

Then

$$(\lambda_{Y, y}) \circ (\tau_{X, Y}) = (\tau_{X \setminus x, Y \setminus y}) \circ (\lambda_{X, x}) \in \text{WD}(\frac{Y \setminus y}{X}). \quad (3.3.4.1)$$

The next relation says that a name change inside an in-split (Def. 3.1.6) can be rewritten as a name change of an in-split.

Proposition 3.3.5. *Suppose:*

- $X \in \text{Box}_S$, and $x_1, x_2 \in X^{\text{in}}$ are distinct elements such that $v(x_1) = v(x_2) \in S$.
- $X' = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 .
- $\sigma_{X, x_1, x_2} \in \text{WD}(\frac{X'}{X})$ is the corresponding in-split.
- $\tau_{X, Y} \in \text{WD}(\frac{Y}{X})$ is a name change with $y_1, y_2 \in Y^{\text{in}}$ corresponding to $x_1, x_2 \in X^{\text{in}}$.
- $Y' = Y/(y_1 = y_2) \in \text{Box}_S$ is obtained from Y by identifying y_1 and y_2 .
- $\sigma_{Y, y_1, y_2} \in \text{WD}(\frac{Y'}{Y})$ is the corresponding in-split.
- $\tau_{X', Y'} \in \text{WD}(\frac{Y'}{X'})$ is the name change induced by $\tau_{X, Y}$.

Then

$$(\sigma_{Y, y_1, y_2}) \circ (\tau_{X, Y}) = (\tau_{X', Y'}) \circ (\sigma_{X, x_1, x_2}) \in \text{WD}(\frac{Y'}{X'}). \quad (3.3.5.1)$$

The next relation is the out-split (Def. 3.1.7) analogue of (3.3.5.1).

Proposition 3.3.6. *Suppose:*

- $Y \in \text{Box}_S$, and $y_1, y_2 \in Y^{\text{out}}$ are distinct elements such that $v(y_1) = v(y_2) \in S$.
- $Y' = Y/(y_1 = y_2) \in \text{Box}_S$ is obtained from Y by identifying y_1 and y_2 .
- $\sigma^{Y, y_1, y_2} \in \text{WD}(\frac{Y'}{Y})$ is an out-split.
- $\tau_{X, Y} \in \text{WD}(\frac{Y}{X})$ is a name change with $x_1, x_2 \in X^{\text{out}}$ corresponding to $y_1, y_2 \in Y^{\text{out}}$.
- $X' = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 .
- $\sigma^{X, x_1, x_2} \in \text{WD}(\frac{X'}{X})$ is the corresponding out-split.
- $\tau_{X', Y'} \in \text{WD}(\frac{Y'}{X'})$ is the name change induced by $\tau_{X, Y}$.

Then

$$(\sigma^{Y, y_1, y_2}) \circ (\tau_{X', Y'}) = (\tau_{X, Y}) \circ (\sigma^{X, x_1, x_2}) \in \text{WD}(\frac{Y'}{X'}). \quad (3.3.6.1)$$

The next relation says that a name change inside a 1-wasted wire (Def. 3.1.8) can be rewritten as a name change of a 1-wasted wire.

Proposition 3.3.7. *Suppose:*

- $Y \in \text{Box}_S$, $y \in Y^{\text{in}}$, and $Y' = Y \setminus \{y\} \in \text{Box}_S$ is obtained from Y by removing y .

- $\omega_{Y,y} \in \text{WD}(Y)$ is the corresponding 1-wasted wire.
- $\tau_{X,Y} \in \text{WD}(X)$ is a name change with $x \in X^{\text{in}}$ corresponding to $y \in Y^{\text{in}}$.
- $X' \in \text{Box}_S$ is obtained from X by removing x .
- $\omega_{X,x} \in \text{WD}(X)$ is the corresponding 1-wasted wire.
- $\tau_{X',Y'} \in \text{WD}(X')$ is the name change induced by $\tau_{X,Y}$.

Then

$$(\omega_{Y,y}) \circ (\tau_{X',Y'}) = (\tau_{X,Y}) \circ (\omega_{X,x}) \in \text{WD}(X'). \quad (3.3.7.1)$$

The next seven relations are about 2-cells (Def. 3.1.4). The following relation says that substituting the empty wiring diagram (Def. 3.1.1) into a 2-cell yields a colored unit (2.3.2.1).


Proposition 3.3.8. *Suppose:*

- $X \in \text{Box}_S$ with X -colored unit $\mathbb{1}_X \in \text{WD}(X)$.
- $\epsilon \in \text{WD}(\emptyset)$ is the empty wiring diagram.
- $\theta_{X,\emptyset} \in \text{WD}(X, \emptyset)$ is the 2-cell with input boxes (X, \emptyset) and output box X .

Then

$$\theta_{X,\emptyset} \circ_2 \epsilon = \mathbb{1}_X \in \text{WD}(X). \quad (3.3.8.1)$$

The next relation is the associativity property of 2-cells. It says that, in the picture below, the wiring diagram in the middle can be constructed using two 2-cells, either as the operadic composition on the left or the one on the right.



Proposition 3.3.9. *Suppose:*

- $\theta_{X \sqcup Y, Z} \in \text{WD}(X \sqcup Y, Z)$ and $\theta_{X, Y} \in \text{WD}(X, Y)$ are 2-cells.
- $\theta_{X, Y \sqcup Z} \in \text{WD}(X, Y \sqcup Z)$ and $\theta_{Y, Z} \in \text{WD}(Y, Z)$ are 2-cells.

Then

$$(\theta_{X \sqcup Y, Z}) \circ_1 (\theta_{X, Y}) = (\theta_{X, Y \sqcup Z}) \circ_2 (\theta_{Y, Z}) \in \text{WD}(X \sqcup Y, Z). \quad (3.3.9.1)$$

The next relation is the commutativity property of 2-cells and uses the equivariant structure in WD (2.3.1.1).


Proposition 3.3.10. *Suppose:*

- $\theta_{X,Y} \in \text{WD}(\begin{smallmatrix} X \sqcup Y \\ X, Y \end{smallmatrix})$ is a 2-cell.
- $(1\ 2) \in \Sigma_2$ is the non-trivial permutation.

Then

$$\theta_{X,Y}(1\ 2) = \theta_{Y,X} \in \text{WD}(\begin{smallmatrix} Y \sqcup X \\ Y, X \end{smallmatrix}). \quad (3.3.10.1)$$

The next relation says that substituting a 1-loop inside a 2-cell can be rewritten as substituting a 2-cell inside a 1-loop. It gives two different ways to construct the wiring diagram in the middle in the picture below using a 1-loop and a 2-cell, either as the operadic composition on the left or the one on the right.



Proposition 3.3.11. *Suppose:*


- $X \in \text{Box}_S$, and $(x_+, x_-) \in X^{\text{out}} \times X^{\text{in}}$ such that $v(x_+) = v(x_-) \in S$.
- $X \setminus x \in \text{Box}_S$ is obtained from X by removing x_{\pm} .
- $\theta_{X \setminus x, Y} \in \text{WD}(\begin{smallmatrix} (X \sqcup Y) \setminus \{x\} \\ X \setminus x, Y \end{smallmatrix})$ and $\theta_{X, Y} \in \text{WD}(\begin{smallmatrix} X \sqcup Y \\ X, Y \end{smallmatrix})$ are 2-cells.
- $\lambda_{X, x} \in \text{WD}(\begin{smallmatrix} X \setminus x \\ X \end{smallmatrix})$ and $\lambda_{X \sqcup Y, x} \in \text{WD}(\begin{smallmatrix} (X \sqcup Y) \setminus \{x\} \\ X \sqcup Y \end{smallmatrix})$ are the corresponding 1-loops.

Then

$$(\theta_{X \setminus x, Y}) \circ_1 (\lambda_{X, x}) = (\lambda_{X \sqcup Y, x}) \circ (\theta_{X, Y}) \in \text{WD}(\begin{smallmatrix} (X \sqcup Y) \setminus \{x\} \\ X, Y \end{smallmatrix}). \quad (3.3.11.1)$$

All the relations in the rest of this section can be illustrated with pictures similar to the two previous pictures, each one showing how a wiring diagram can be built in two different ways using operadic compositions. So we will mostly just draw the picture of the wiring diagram being built without the accompanying pictures of the operadic compositions.

The next relation says that substituting an in-split inside a 2-cell can be rewritten as substituting a 2-cell inside an in-split. It gives two different ways to construct the following wiring diagram using an in-split and a 2-cell:




Proposition 3.3.12. *Suppose:*

- $X \in \text{Box}_S$, and $x_1, x_2 \in X^{\text{in}}$ are distinct elements such that $v(x_1) = v(x_2) \in S$.
- $X' = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 .
- $\theta_{X',Y} \in \text{WD}_{(X',Y)}^{(X' \sqcup Y)}$ and $\theta_{X,Y} \in \text{WD}_{(X,Y)}^{(X \sqcup Y)}$ are 2-cells.
- $\sigma_{X,x_1,x_2} \in \text{WD}_X^{(X')}$ and $\sigma_{X \sqcup Y, x_1, x_2} \in \text{WD}_{(X \sqcup Y)}^{(X' \sqcup Y)}$ are in-splits.

Then

$$(\theta_{X',Y}) \circ_1 (\sigma_{X,x_1,x_2}) = (\sigma_{X \sqcup Y, x_1, x_2}) \circ (\theta_{X,Y}) \in \text{WD}_{(X',Y)}^{(X' \sqcup Y)}. \quad (3.3.12.1)$$

The next relation says that substituting an out-split inside a 2-cell can be rewritten as substituting a 2-cell inside an out-split. It gives two different ways to construct the following wiring diagram using an out-split and a 2-cell:




Proposition 3.3.13. *Suppose:*

- $X \in \text{Box}_S$, and $x_1, x_2 \in X^{\text{out}}$ are distinct elements such that $v(x_1) = v(x_2) \in S$.
- $X' = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 .
- $\theta_{X,Y} \in \text{WD}_{(X,Y)}^{(X \sqcup Y)}$ and $\theta_{X',Y} \in \text{WD}_{(X',Y)}^{(X' \sqcup Y)}$ are 2-cells.
- $\sigma^{X,x_1,x_2} \in \text{WD}_{(X')}^X$ and $\sigma^{X \sqcup Y, x_1, x_2} \in \text{WD}_{(X' \sqcup Y)}^{(X \sqcup Y)}$ are out-splits.

Then

$$(\theta_{X,Y}) \circ_1 (\sigma^{X,x_1,x_2}) = (\sigma^{X \sqcup Y, x_1, x_2}) \circ (\theta_{X',Y}) \in \text{WD}_{(X',Y)}^{(X \sqcup Y)}. \quad (3.3.13.1)$$

The next relation says that substituting a 1-wasted wire inside a 2-cell can be rewritten as substituting a 2-cell inside a 1-wasted wire. It gives two different ways to construct the following wiring diagram using a 1-wasted wire and a 2-cell:




Proposition 3.3.14. *Suppose:*

- $X \in \text{Box}_S$, $x_0 \in X^{\text{in}}$, and $X' = X \setminus \{x_0\} \in \text{Box}_S$ is obtained from X by removing x_0 .
- $\theta_{X,Y} \in \text{WD}_{(X,Y)}^{(X \sqcup Y)}$ and $\theta_{X',Y} \in \text{WD}_{(X',Y)}^{(X' \sqcup Y)}$ are 2-cells.
- $\omega_{X,x_0} \in \text{WD}_{(X')}^{(X)}$ and $\omega_{X \sqcup Y, x_0} \in \text{WD}_{(X' \sqcup Y)}^{(X \sqcup Y)}$ are 1-wasted wires.

Then

$$(\theta_{X,Y}) \circ_1 (\omega_{X,x_0}) = (\omega_{X \sqcup Y, x_0}) \circ (\theta_{X',Y}) \in \text{WD}_{(X',Y)}^{(X \sqcup Y)}. \quad (3.3.14.1)$$

The following six relations are about 1-loops. The next relation is the commutativity property of 1-loops. It gives two different ways to construct the following wiring diagram, which we will call a *double-loop*, using two 1-loops:




Proposition 3.3.15. *Suppose:*

- $X \in \text{Box}_S$, $x_-^1 \neq x_-^2 \in X^{\text{in}}$, and $x_+^1 \neq x_+^2 \in X^{\text{out}}$ such that $v(x_+^1) = v(x_-^1) \in S$ and $v(x_+^2) = v(x_-^2) \in S$.
- $X \setminus x^1$, $X \setminus x^2$, and $X \setminus x \in \text{Box}_S$ are obtained from X by removing x_{\pm}^1 , x_{\pm}^2 , and $\{x_{\pm}^1, x_{\pm}^2\}$, respectively.
- $\lambda_{X \setminus x^1, x^2} \in \text{WD}_{(X \setminus x^1)}^{(X \setminus x)}$ and $\lambda_{X, x^1} \in \text{WD}_{(X)}^{(X \setminus x^1)}$ are 1-loops.
- $\lambda_{X \setminus x^2, x^1} \in \text{WD}_{(X \setminus x^2)}^{(X \setminus x)}$ and $\lambda_{X, x^2} \in \text{WD}_{(X)}^{(X \setminus x^2)}$ are 1-loops.

Then

$$(\lambda_{X \setminus x^1, x^2}) \circ (\lambda_{X, x^1}) = (\lambda_{X \setminus x^2, x^1}) \circ (\lambda_{X, x^2}) \in \text{WD}_{(X)}^{(X \setminus x)}. \quad (3.3.15.1)$$

The next relation is the commutativity property between 1-loops and in-splits. It gives two different ways to construct the following wiring diagram using one 1-loop and one in-split:




Proposition 3.3.16. *Suppose:*

- $X \in \text{Box}_S$, $x_-, x_1, x_2 \in X^{\text{in}}$ are distinct, and $x_+ \in X^{\text{out}}$ such that $v(x_+) = v(x_-) \in S$ and $v(x_1) = v(x_2) \in S$.
- $X \setminus x \in \text{Box}_S$ is obtained from X by removing x_{\pm} .
- $X' = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 .
- $X' \setminus x \in \text{Box}_S$ is obtained from X' by removing x_{\pm} .
- $\lambda_{X',x} \in \text{WD}(\frac{X' \setminus x}{X'})$ and $\lambda_{X,x} \in \text{WD}(\frac{X \setminus x}{X})$ are 1-loops.
- $\sigma_{X,x_1,x_2} \in \text{WD}(\frac{X'}{X})$ and $\sigma_{X \setminus x, x_1, x_2} \in \text{WD}(\frac{X' \setminus x}{X \setminus x})$ are in-splits.

Then

$$(\lambda_{X',x}) \circ (\sigma_{X,x_1,x_2}) = (\sigma_{X \setminus x, x_1, x_2}) \circ (\lambda_{X,x}) \in \text{WD}(\frac{X' \setminus x}{X}). \quad (3.3.16.1)$$

The next relation is the commutativity property between 1-loops and out-splits. It gives two different ways to construct the following wiring diagram using one 1-loop and one out-split:




Proposition 3.3.17. *Suppose:*

- $X \in \text{Box}_S$, and $(x_+, x_-) \in X^{\text{out}} \times X^{\text{in}}$ such that $v(x_+) = v(x_-) \in S$.
- $x_1 \neq x_2 \in X^{\text{out}} \setminus \{x_+\}$ such that $v(x_1) = v(x_2) \in S$.
- $X' = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 .
- $X \setminus x \in \text{Box}_S$ is obtained from X by removing x_{\pm} .
- $X' \setminus x \in \text{Box}_S$ is obtained from X' by removing x_{\pm} .
- $\lambda_{X',x} \in \text{WD}(\frac{X' \setminus x}{X'})$ and $\lambda_{X,x} \in \text{WD}(\frac{X \setminus x}{X})$ are 1-loops.
- $\sigma^{X \setminus x, x_1, x_2} \in \text{WD}(\frac{X \setminus x}{X' \setminus x})$ and $\sigma^{X, x_1, x_2} \in \text{WD}(\frac{X}{X'})$ are out-splits.

Then

$$(\sigma^{X \setminus x, x_1, x_2}) \circ (\lambda_{X',x}) = (\lambda_{X,x}) \circ (\sigma^{X, x_1, x_2}) \in \text{WD}(\frac{X \setminus x}{X'}). \quad (3.3.17.1)$$

The next relation is the commutativity property between 1-loops and 1-wasted wires. It gives two different ways to construct the following wiring diagram using one 1-loop and one 1-wasted wire:




Proposition 3.3.18. *Suppose:*

- $X \in \text{Box}_S$, $(x_+, x_-) \in X^{\text{out}} \times X^{\text{in}}$ such that $v(x_+) = v(x_-) \in S$, and $x_0 \in X^{\text{in}} \setminus \{x_-\}$.
- $X' = X \setminus \{x_0\} \in \text{Box}_S$ is obtained from X by removing x_0 .
- $X' \setminus x \in \text{Box}_S$ is obtained from X' by removing x_{\pm} .
- $X \setminus x \in \text{Box}_S$ is obtained from X by removing x_{\pm} .
- $\lambda_{X',x} \in \text{WD}(\frac{X' \setminus x}{X'})$ and $\lambda_{X,x} \in \text{WD}(\frac{X \setminus x}{X})$ are 1-loops.
- $\omega_{X \setminus x, x_0} \in \text{WD}(\frac{X \setminus x}{X' \setminus x})$ and $\omega_{X, x_0} \in \text{WD}(\frac{X}{X'})$ are 1-wasted wires.

Then

$$(\omega_{X \setminus x, x_0}) \circ (\lambda_{X', x}) = (\lambda_{X, x}) \circ (\omega_{X, x_0}) \in \text{WD}(\frac{X \setminus x}{X'}). \quad (3.3.18.1)$$

The next relation involves 1-loops, in-splits, and out-splits. It says that the following two wiring diagrams are equal:



The wiring diagram on the left, in which the gray box is called X' below, is created by substituting an in-split into a 1-loop. The wiring diagram on the right is created by substituting an out-split into a 1-loop, which is then substituted into another 1-loop. The inner gray box is called Y , and the outer gray box is called $Y \setminus x(1)$ below. In both wiring diagrams, the outermost box is called X^* .

Proposition 3.3.19. *Suppose:*


- $Y \in \text{Box}_S$, and $x^1 \neq x^2 \in Y^{\text{out}}$ such that $v(x^1) = v(x^2) \in S$.

- $X = Y/(x^1 = x^2) \in \text{Box}_S$ is obtained from Y by identifying x^1 and x^2 , called $x^{12} \in X^{\text{out}}$.
- $x_1 \neq x_2 \in X^{\text{in}} = Y^{\text{in}}$ such that $v(x^{12}) = v(x_1) = v(x_2) \in S$.
- $X' = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 , called x_{12} in X' .
- $\sigma_{X,x_1,x_2} \in \text{WD}(X')$ is an in-split.
- $X^* = X \setminus \{x^{12}, x_1, x_2\} \in \text{Box}_S$ is obtained from X by removing x^{12}, x_1 , and x_2 .
- $\lambda_{X',x} \in \text{WD}(X')$ is the 1-loop in which x^{12} is the supply wire of x_{12} .
- $\sigma^{Y,x^1,x^2} \in \text{WD}(Y)$ is an out-split.
- $\lambda_{Y,x(1)} \in \text{WD}(Y \setminus x(1))$ is a 1-loop, where $Y \setminus x(1) \in \text{Box}_S$ is obtained from Y by removing $\{x_1, x^1\}$.
- $\lambda_{Y \setminus x(1),x(2)} \in \text{WD}(Y \setminus x(1))$ is a 1-loop, in which x^2 is the supply wire of x_2 .

Then

$$(\lambda_{X',x}) \circ (\sigma_{X,x_1,x_2}) = (\lambda_{Y \setminus x(1),x(2)}) \circ (\lambda_{Y,x(1)}) \circ (\sigma^{Y,x^1,x^2}) \in \text{WD}(X^*). \quad (3.3.19.1)$$

The next relation says that the colored unit of a box can be rewritten as the substitution of an out-split into a 1-wasted wire and then into a 1-loop. This is depicted in the picture



in which the outer gray box is called Z and the inner gray box is called Y below.

Proposition 3.3.20. *Suppose:*


- $Z \in \text{Box}_S$, and $(x_1, x^1) \in Z^{\text{in}} \times Z^{\text{out}}$ such that $v(x_1) = v(x^1) \in S$.
- $Y = Z \setminus \{x_1\} \in \text{Box}_S$ is obtained from Z by removing $x_1 \in Z^{\text{in}}$.
- $x^1 \neq x^2 \in Y^{\text{out}} = Z^{\text{out}}$ such that $v(x^1) = v(x^2) \in S$.
- $X = Z \setminus \{x_1, x^1\} \in \text{Box}_S$ is obtained from Z by removing $\{x_1, x^1\}$.
- $\sigma^{Y,x^1,x^2} \in \text{WD}(Y)$ is an out-split in which both $x^1, x^2 \in Y^{\text{out}}$ have supply wire $x^2 \in X^{\text{out}}$.
- $\omega_{Z,x_1} \in \text{WD}(Z)$ is a 1-wasted wire.

- $\lambda_{Z,x} \in \text{WD}(\frac{X}{Z})$ is a 1-loop in which $x^1 \in Z^{\text{out}}$ is the supply wire of $x_1 \in Z^{\text{in}}$.

Then

$$(\lambda_{Z,x}) \circ (\omega_{Z,x_1}) \circ (\sigma^{Y,x^1,x^2}) = \mathbb{1}_X \in \text{WD}(\frac{X}{X}). \quad (3.3.20.1)$$

The following five relations are about in-splits. The next one is the associativity property of in-splits. It gives two different ways to construct the following wiring diagram using two in-splits:




Proposition 3.3.21. *Suppose:*

- $X \in \text{Box}_S$, and $x_1, x_2, x_3 \in X^{\text{in}}$ are distinct elements such that $v(x_1) = v(x_2) = v(x_3) \in S$.
- $X_{12} = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 , called $x_{12} \in X_{12}^{\text{in}}$.
- $X_{23} = X/(x_2 = x_3) \in \text{Box}_S$ is obtained from X by identifying x_2 and x_3 , called $x_{23} \in X_{23}^{\text{in}}$.
- $Y = X/(x_1 = x_2 = x_3) \in \text{Box}_S$ is obtained from X by identifying x_1, x_2 , and x_3 .
- $\sigma_{X_{12},x_{12},x_3} \in \text{WD}(\frac{Y}{X_{12}})$ and $\sigma_{X,x_1,x_2} \in \text{WD}(\frac{X_{12}}{X})$ are in-splits.
- $\sigma_{X_{23},x_1,x_{23}} \in \text{WD}(\frac{Y}{X_{23}})$ and $\sigma_{X,x_2,x_3} \in \text{WD}(\frac{X_{23}}{X})$ are in-splits.

Then

$$(\sigma_{X_{12},x_{12},x_3}) \circ (\sigma_{X,x_1,x_2}) = (\sigma_{X_{23},x_1,x_{23}}) \circ (\sigma_{X,x_2,x_3}) \in \text{WD}(\frac{Y}{X}). \quad (3.3.21.1)$$

The next relation is the commutativity property of in-splits. It gives two different ways to construct the following wiring diagram using two in-splits:



Proposition 3.3.22. *Suppose:*


- $X \in \text{Box}_S$, and $x_1, x_2, x_3, x_4 \in X^{\text{in}}$ are distinct elements such that $v(x_1) = v(x_2)$ and $v(x_3) = v(x_4) \in S$.
- $X_{12} = X/(x_1 = x_2) \in \text{Box}_S$ is obtained from X by identifying x_1 and x_2 , called $x_{12} \in X_{12}^{\text{in}}$.

- $X_{34} = X/(x_3 = x_4) \in \text{Box}_S$ is obtained from X by identifying x_3 and x_4 , called $x_{34} \in X_{34}^{\text{in}}$.
- $Y = X/(x_1 = x_2; x_3 = x_4) \in \text{Box}_S$ is obtained from X by (i) identifying x_1 and x_2 and (ii) identifying x_3 and x_4 .
- $\sigma_{X_{12}, x_3, x_4} \in \text{WD}(X_{12}^Y)$ and $\sigma_{X, x_1, x_2} \in \text{WD}(X_{12}^X)$ are in-splits.
- $\sigma_{X_{34}, x_1, x_2} \in \text{WD}(X_{34}^Y)$ and $\sigma_{X, x_3, x_4} \in \text{WD}(X_{34}^X)$ are in-splits.

Then

$$(\sigma_{X_{12}, x_3, x_4}) \circ (\sigma_{X, x_1, x_2}) = (\sigma_{X_{34}, x_1, x_2}) \circ (\sigma_{X, x_3, x_4}) \in \text{WD}(X^Y). \quad (3.3.22.1)$$

The next relation is the commutativity property between an in-split and an out-split. It gives two different ways to construct the following wiring diagram using one in-split and one out-split:




Proposition 3.3.23. *Suppose:*

- $Z \in \text{Box}_S$, and $z^1 \neq z^2 \in Z^{\text{out}}$ such that $v(z^1) = v(z^2) \in S$.
- $X = Z/(z^1 = z^2) \in \text{Box}_S$ is obtained from Z by identifying z^1 and z^2 .
- $z_1 \neq z_2 \in Z^{\text{in}}$ such that $v(z_1) = v(z_2) \in S$.
- $Y = Z/(z_1 = z_2) \in \text{Box}_S$ is obtained from Z by identifying z_1 and z_2 .
- $W = Z/(z_1 = z_2; z^1 = z^2) \in \text{Box}_S$ is obtained from Z by (i) identifying z_1 and z_2 and (ii) identifying z^1 and z^2 .
- $\sigma^{Y, z^1, z^2} \in \text{WD}(W)$ is an out-split, and $\sigma_{X, z_1, z_2} \in \text{WD}(X^W)$ is an in-split.
- $\sigma_{Z, z_1, z_2} \in \text{WD}(Z^Y)$ is an in-split, and $\sigma^{Z, z^1, z^2} \in \text{WD}(Z^X)$ is an out-split.

Then

$$(\sigma^{Y, z^1, z^2}) \circ (\sigma_{X, z_1, z_2}) = (\sigma_{Z, z_1, z_2}) \circ (\sigma^{Z, z^1, z^2}) \in \text{WD}(X^Y). \quad (3.3.23.1)$$

The next relation is the commutativity property between an in-split and a 1-wasted wire. It gives two different ways to construct the following wiring diagram using one in-split and one 1-wasted wire:




Proposition 3.3.24. *Suppose:*

- $Z \in \text{Box}_S$, and $z, z_1, z_2 \in Z^{\text{in}}$ are distinct elements such that $v(z_1) = v(z_2) \in S$.
- $Y = Z/(z_1 = z_2) \in \text{Box}_S$ is obtained from Z by identifying z_1 and z_2 .
- $X = Z \setminus \{z\} \in \text{Box}_S$ is obtained from Z by removing $z \in Z^{\text{in}}$.
- $W = X/(z_1 = z_2) \in \text{Box}_S$ is obtained from X by identifying z_1 and z_2 .
- $\sigma_{X,z_1,z_2} \in \text{WD}(\overset{W}{X})$ and $\sigma_{Z,z_1,z_2} \in \text{WD}(\overset{Y}{Z})$ are in-splits.
- $\omega_{Y,z} \in \text{WD}(\overset{Y}{W})$ and $\omega_{Z,z} \in \text{WD}(\overset{Z}{X})$ are 1-wasted wires.

Then

$$(\omega_{Y,z}) \circ (\sigma_{X,z_1,z_2}) = (\sigma_{Z,z_1,z_2}) \circ (\omega_{Z,z}) \in \text{WD}(\overset{Y}{X}). \quad (3.3.24.1)$$

The next relation says that the colored unit of a box X can be rewritten as the substitution of a 1-wasted wire into an in-split. This is depicted in the picture



in which the intermediate gray box is called Y below.


Proposition 3.3.25. *Suppose:*

- $Y \in \text{Box}_S$, and $x, y \in Y^{\text{in}}$ are distinct elements such that $v(x) = v(y) \in S$.
- $X = Y/(x = y) \in \text{Box}_S$ is obtained from Y by identifying x and y .
- $\omega_{Y,y} \in \text{WD}(\overset{Y}{X})$ is a 1-wasted wire.
- $\sigma_{Y,x,y} \in \text{WD}(\overset{X}{Y})$ is an in-split.

Then

$$(\sigma_{Y,x,y}) \circ (\omega_{Y,y}) = \mathbb{1}_X \in \text{WD}(\overset{X}{X}). \quad (3.3.25.1)$$

The following three relations are about out-splits. The next one is the associativity property of out-splits. It gives two different ways to construct the following wiring diagram using two out-splits:




Proposition 3.3.26. *Suppose:*

- $Y \in \text{Box}_S$, and $y^1, y^2, y^3 \in Y^{\text{out}}$ are distinct elements such that $v(y^1) = v(y^2) = v(y^3) \in S$.
- $Y^{12} = Y/(y^1 = y^2) \in \text{Box}_S$ is obtained from Y by identifying y^1 and y^2 , called y^{12} in Y^{12} .
- $Y^{23} = Y/(y^2 = y^3) \in \text{Box}_S$ is obtained from Y by identifying y^2 and y^3 , called y^{23} in Y^{23} .
- $X = Y/(y^1 = y^2 = y^3) \in \text{Box}_S$ is obtained from Y by identifying y^1, y^2 , and y^3 .
- $\sigma^{Y, y^1, y^2} \in \text{WD}(Y)$ and $\sigma^{Y^{12}, y^{12}, y^3} \in \text{WD}(Y^{12}_X)$ are out-splits.
- $\sigma^{Y, y^2, y^3} \in \text{WD}(Y)$ and $\sigma^{Y^{23}, y^1, y^{23}} \in \text{WD}(Y^{23}_X)$ are out-splits.

Then

$$\left(\sigma^{Y, y^1, y^2}\right) \circ \left(\sigma^{Y^{12}, y^{12}, y^3}\right) = \left(\sigma^{Y, y^2, y^3}\right) \circ \left(\sigma^{Y^{23}, y^1, y^{23}}\right) \in \text{WD}(Y_X). \quad (3.3.26.1)$$

The next relation is the commutativity property of out-splits. It gives two different ways to construct the following wiring diagram using two out-splits:




Proposition 3.3.27. *Suppose:*

- $Y \in \text{Box}_S$, and $y^1, y^2, y^3, y^4 \in Y^{\text{out}}$ are distinct elements such that $v(y^1) = v(y^2)$ and $v(y^3) = v(y^4) \in S$.
- $Y^{12} = Y/(y^1 = y^2) \in \text{Box}_S$ is obtained from Y by identifying y^1 and y^2 .
- $Y^{34} = Y/(y^3 = y^4) \in \text{Box}_S$ is obtained from Y by identifying y^3 and y^4 .
- $X = Y/(y^1 = y^2; y^3 = y^4) \in \text{Box}_S$ is obtained from Y by (i) identifying y^1 and y^2 and (ii) identifying y^3 and y^4 .
- $\sigma^{Y, y^1, y^2} \in \text{WD}(Y)$ and $\sigma^{Y^{12}, y^3, y^4} \in \text{WD}(Y^{12}_X)$ are out-splits.
- $\sigma^{Y, y^3, y^4} \in \text{WD}(Y)$ and $\sigma^{Y^{34}, y^1, y^2} \in \text{WD}(Y^{34}_X)$ are out-splits.

Then

$$\left(\sigma^{Y, y^1, y^2}\right) \circ \left(\sigma^{Y^{12}, y^3, y^4}\right) = \left(\sigma^{Y, y^3, y^4}\right) \circ \left(\sigma^{Y^{34}, y^1, y^2}\right) \in \text{WD}(Y_X). \quad (3.3.27.1)$$

The next relation is the commutativity property between an out-split and a 1-wasted wire. It gives two different ways to construct the following wiring diagram using one out-split and one 1-wasted wire:




Proposition 3.3.28. *Suppose:*

- $Y \in \text{Box}_S$, $y \in Y^{\text{in}}$, and $y^1, y^2 \in Y^{\text{out}}$ such that $v(y^1) = v(y^2) \in S$.
- $W = Y / (y^1 = y^2) \in \text{Box}_S$ is obtained from Y by identifying y^1 and y^2 .
- $Z = Y \setminus \{y\} \in \text{Box}_S$ is obtained from Y by removing $y \in Y^{\text{in}}$.
- $X = Z / (y^1 = y^2) \in \text{Box}_S$ is obtained from Z by identifying y^1 and y^2 .
- $\sigma^{Z, y^1, y^2} \in \text{WD}(\frac{Z}{X})$ and $\sigma^{Y, y^1, y^2} \in \text{WD}(\frac{Y}{W})$ are out-splits.
- $\omega_{Y, y} \in \text{WD}(\frac{Y}{Z})$ and $\omega_{W, y} \in \text{WD}(\frac{W}{X})$ are 1-wasted wires.

Then

$$(\omega_{Y, y}) \circ (\sigma^{Z, y^1, y^2}) = (\sigma^{Y, y^1, y^2}) \circ (\omega_{W, y}) \in \text{WD}(\frac{Y}{X}). \quad (3.3.28.1)$$

The final relation is the commutativity property of 1-wasted wires. It gives two different ways to construct the following wiring diagram using two 1-wasted wires:



Proposition 3.3.29. *Suppose:*

- $Y \in \text{Box}_S$, and $y_1, y_2 \in Y^{\text{in}}$ are distinct elements.
- $Y_1 = Y \setminus \{y_1\} \in \text{Box}_S$ is obtained from Y by removing y_1 .
- $Y_2 = Y \setminus \{y_2\} \in \text{Box}_S$ is obtained from Y by removing y_2 .
- $X = Y \setminus \{y_1, y_2\} \in \text{Box}_S$ is obtained from Y by removing y_1 and y_2 .
- $\omega_{Y, y_1} \in \text{WD}(\frac{Y}{Y_1})$ and $\omega_{Y_1, y_2} \in \text{WD}(\frac{Y_1}{X})$ are 1-wasted wires.
- $\omega_{Y, y_2} \in \text{WD}(\frac{Y}{Y_2})$ and $\omega_{Y_2, y_1} \in \text{WD}(\frac{Y_2}{X})$ are 1-wasted wires.

Then

$$(\omega_{Y, y_1}) \circ (\omega_{Y_1, y_2}) = (\omega_{Y, y_2}) \circ (\omega_{Y_2, y_1}) \in \text{WD}(\frac{Y}{X}). \quad (3.3.29.1)$$

Definition 3.3.30. The 28 relations (3.3.2.1)–(3.3.29.1) are called *elementary relations*.

Decomposition of Wiring Diagrams

As part of the finite presentation theorem for the operad WD of wiring diagrams (Theorem 5.2.10), in Theorem 5.1.7 we will observe that each wiring diagram has a highly structured decomposition into generating wiring diagrams (Def. 3.1.9), called a stratified presentation. Stratified presentations are also needed to establish the second part of the finite presentation theorem for WD regarding relations. The purpose of this chapter is to provide all the steps needed to establish the existence of a stratified presentation for each wiring diagram. We remind the reader about Notation 3.3.1 for (iterated) operadic compositions.

In Section 4.1 we show that each wiring diagram ψ has a specific operadic decomposition (4.1.5.1)

$$\psi = \alpha \circ \varphi.$$

An explanation of this decomposition is given just before Def. 4.1.3. The idea of this decomposition is that we are breaking the complexity of a general wiring diagram into two simpler parts. On the one hand, the inner wiring diagram φ contains all the input boxes and the delay nodes of ψ , but its supplier assignment is as simple as possible, namely the identity map. See Lemmas 4.1.6 and 4.1.7. On the other hand, the outer wiring diagram α has only one input box and no delay nodes, but its supplier assignment is equal to that of ψ .

In Section 4.2 we observe that the outer wiring diagram α in the previous decomposition of ψ can be decomposed as (4.2.6.1)

$$\alpha = \pi_1 \circ \pi_2.$$

Example 4.2.3 has a concrete wiring diagram that illustrates this decomposition. The idea of this decomposition is that in a wiring diagram there are usually wires that go backward (i.e., "point to the left"), as in (2.2.14.1), in a 1-loop (Def. 3.1.5), and in the pictures just before Prop. 3.3.11 and Prop. 3.3.15. This decomposition breaks the complexity of the wiring diagram α into two simpler parts. On the one hand, the outer wiring diagram π_1 contains all the backward-going wires in α but no wasted wires or split wires (Lemma 4.2.7). On the other hand, the inner wiring diagram π_2 contains no backward-going wires, but it has all the wasted wires and split wires in α .

In Section 4.3 we observe that the wiring diagram π_2 in the previous decomposition of α can be decomposed further as (4.3.5.1)

$$\pi_2 = \beta_1 \circ \beta_2 \circ \beta_3.$$

Example 4.3.2 has a concrete wiring diagram that illustrates this decomposition. In this decomposition:

- The outermost wiring diagram β_1 is an iterated operadic composition of 1-wasted wires (Lemma 4.3.6).
- The middle wiring diagram β_2 is an iterated operadic composition of in-splits (Lemma 4.3.8).
- The innermost wiring diagram β_3 is an iterated operadic composition of out-splits (Lemma 4.3.10).

By convention an empty operadic composition means a colored unit. In summary, for a wiring diagram ψ , we will decompose it as

$$\psi = \pi_1 \circ \beta_1 \circ \beta_2 \circ \beta_3 \circ \varphi.$$

4.1. Factoring Wiring Diagrams

Assumption 4.1.1. Throughout this chapter, fix a class S . Suppose

$$\psi = (\text{DN}_\psi, v_\psi, s_\psi) \in \text{WD}(\underline{Y}, \underline{X}) \quad (4.1.1.1)$$

is a wiring diagram with:

- output box $Y \in \text{Box}_S$ and input boxes $\underline{X} = (X_1, \dots, X_N)$ for some $N \geq 0$;
- r delay nodes $\text{DN}_\psi = \{d_1, \dots, d_r\}$ for some $r \geq 0$;
- value assignment $v_\psi : Y^{\text{in}} \sqcup Y^{\text{out}} \sqcup X^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\psi \longrightarrow S$, where $X^{\text{in}} = \coprod_{i=1}^N X_i^{\text{in}}$ and $X^{\text{out}} = \coprod_{i=1}^N X_i^{\text{out}}$;
- supplier assignment $s_\psi : \text{Dm}_\psi \longrightarrow \text{Sp}_\psi$.

Since $N = 0$ and $r = 0$ are both allowed, ψ is a general wiring diagram. Furthermore:

- (1) To simplify notation, we will write $v_\psi(d_i) \in S$ simply as d_i , so each $\delta_{d_i} \in \text{WD}^{(d_i)}$ is a 1-delay node (Def. 3.1.2).
- (2) $X = \coprod_{i=1}^N X_i \in \text{Box}_S$ is the coproduct of the X_i 's.
- (3) Define $X' \in \text{Box}_S$ as

$$X'^{\text{in}} = X^{\text{in}} \sqcup \text{DN}_\psi \quad \text{and} \quad X'^{\text{out}} = X^{\text{out}} \sqcup \text{DN}_\psi. \quad (4.1.1.2)$$

The first observation is about the marginal case where ψ has no input boxes and no delay nodes.

Lemma 4.1.2. *Suppose $N = r = 0$ in ψ ; i.e., $\psi \in \text{WD}^{(Y)}$ has no input boxes and no delay nodes. Then one of the following two statements is true.*

- (1) $\psi = \epsilon \in \text{WD}^{(\emptyset)}$, the empty wiring diagram (Def. 3.1.1).
- (2) There exist 1-wasted wires (Def. 3.1.8) $\omega_1, \dots, \omega_m$, where $m = |Y^{\text{in}}| > 0$, such that

$$\psi = \omega_1 \circ \dots \circ \omega_m \circ \epsilon. \quad (4.1.2.1)$$

Proof. Since $X^{\text{in}} = X^{\text{out}} = \text{DN}_\psi = \emptyset$, the supplier assignment of ψ is a function

$$\text{Dm}_\psi = Y^{\text{out}} \xrightarrow{s} Y^{\text{in}} = \text{Sp}_\psi.$$

The non-instantaneity requirement (2.2.9.2) then implies $Y^{\text{out}} = \emptyset$. If $m = |Y^{\text{in}}| = 0$, then Y is the empty box and $\psi = \epsilon$, the empty wiring diagram, by definition.

If $m > 0$, then every global input $y \in Y^{\text{in}} = \{y_1, \dots, y_m\}$ is an external wasted wire, and the supplier assignment $s : Y^{\text{out}} = \emptyset \longrightarrow Y^{\text{in}}$ is the trivial map. For each $1 \leq j \leq m$, define the box


$$Y_j = \begin{cases} Y & \text{if } j = 1; \\ Y \setminus \{y_1, \dots, y_{j-1}\} & \text{if } 2 \leq j \leq m; \\ \emptyset & \text{if } j = m + 1. \end{cases}$$

Each $\omega_{Y_j, y_j} \in \text{WD}^{(Y_j)}$ is a 1-wasted wire. Using the notation (3.3.1.2), the iterated composition

$$\omega_{Y_1, y_1} \circ \dots \circ \omega_{Y_m, y_m} \circ \epsilon \in \text{WD}^{(Y)}$$

is then a wiring diagram with output box $Y_1 = Y$, no input boxes and no delay nodes, and supplier assignment $\emptyset = Y^{\text{out}} \longrightarrow Y^{\text{in}}$ the trivial map. This is the same as ψ . \square

Next, for wiring diagrams ψ not necessarily covered by Lemma 4.1.2, we define two relatively simple wiring diagrams that will be shown to provide a decomposition for ψ . Each of these two simpler wiring diagrams will then be analyzed further. This decomposition for ψ is depicted in the following picture:



Here the intermediate gray box is X' (4.1.1.2). In this decomposition, the inside wiring diagram φ has all the input boxes and the delay nodes of ψ , but its supplier assignment is the identity function. The outside wiring diagram α has a single input box X' and no delay nodes, but it has the same supplier assignment as ψ .

Definition 4.1.3. Suppose ψ is as in Assumption 4.1.1. Define the wiring diagram

$$\varphi = (\text{DN}_\varphi, \nu_\varphi, s_\varphi) \in \text{WD}(\underline{X}^{\prime}) \quad (4.1.3.1)$$

with:

- output box X' (4.1.1.2) and input boxes $\underline{X} = (X_1, \dots, X_N)$;
- delay nodes $\text{DN}_\varphi = \text{DN}_\psi = \{d_1, \dots, d_r\}$;
- supplier assignment

$$\begin{aligned} \text{Dm}_\varphi &= X'^{\text{out}} \sqcup X^{\text{in}} \sqcup \text{DN}_\varphi = (X^{\text{out}} \sqcup \text{DN}_\psi) \sqcup (X^{\text{in}} \sqcup \text{DN}_\psi) \\ &\quad \downarrow s_\varphi \\ \text{Sp}_\varphi &= X'^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\varphi = (X^{\text{in}} \sqcup \text{DN}_\psi) \sqcup (X^{\text{out}} \sqcup \text{DN}_\psi) \end{aligned}$$

the identity function that sends X'^{out} to $(X^{\text{out}} \sqcup \text{DN}_\psi)$ and $(X^{\text{in}} \sqcup \text{DN}_\psi)$ to X'^{in} .

Definition 4.1.4. Suppose ψ is as in Assumption 4.1.1. Define the wiring diagram

$$\alpha = (\text{DN}_\alpha, \nu_\alpha, s_\alpha) \in \text{WD}(\underline{Y}^{\prime}) \quad (4.1.4.1)$$

with:

- one input box X' (4.1.1.2) and output box Y ;
- no delay nodes;

- supplier assignment

$$\begin{array}{c} \text{Dm}_\alpha = Y^{\text{out}} \sqcup X^{\text{in}} = Y^{\text{out}} \sqcup X^{\text{in}} \sqcup \text{DN}_\psi = \text{Dm}_\psi \\ \downarrow s_\alpha \\ \text{Sp}_\alpha = Y^{\text{in}} \sqcup X^{\text{out}} = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\psi = \text{Sp}_\psi \end{array}$$

equal to s_ψ .

Lemma 4.1.5. *Given a wiring diagram ψ (4.1.1.1), there is a decomposition*

$$\psi = \alpha \circ \varphi \in \text{WD}\left(\begin{smallmatrix} Y \\ X \end{smallmatrix}\right) \quad (4.1.5.1)$$

in which $\alpha \in \text{WD}\left(\begin{smallmatrix} Y \\ X' \end{smallmatrix}\right)$ is as in (4.1.4.1) and $\varphi \in \text{WD}\left(\begin{smallmatrix} X' \\ X \end{smallmatrix}\right)$ is as in (4.1.3.1).

Proof. By the definition of \circ_1 (Def. 2.3.3), $\alpha \circ \varphi = \alpha \circ_1 \varphi$ belongs to $\text{WD}\left(\begin{smallmatrix} Y \\ X \end{smallmatrix}\right)$ and has $\text{DN}_\varphi = \text{DN}_\psi$ as its set of delay nodes. It remains to check that its supplier assignment is equal to that of ψ . This follows from a direct inspection because s_φ is the identity function, while $s_\alpha = s_\psi$. \square


To obtain the desired stratified presentation of ψ , we now begin to analyze the wiring diagram φ .

Lemma 4.1.6. *Consider the wiring diagram φ (4.1.3.1).*

- (1) *If $N = r = 0$, then $\varphi = \epsilon$, the empty wiring diagram (Def. 3.1.1).*
- (2) *If $(N, r) = (1, 0)$, then $\varphi = \mathbb{1}_{X_1}$, the colored unit of X_1 (Def. 2.3.2).*
- (3) *If $(N, r) = (0, 1)$, then $\varphi = \delta_{d_1}$, a 1-delay node (Def. 3.1.2).*

Proof. All three cases are checked by direct inspection. \square

Next we observe that, for higher values of $N + r$, the wiring diagram φ is generated by 2-cells (Def. 3.1.4) and 1-delay nodes via iterated operadic compositions, as depicted in the following picture.



The operadic composition γ (2.1.2.2) is used in the following observation.

Lemma 4.1.7. *Suppose $N + r \geq 2$ in the wiring diagram $\varphi \in \text{WD}(\underline{X}')$ (4.1.3.1). Then it admits a decomposition*

$$\varphi = \gamma \left(\underline{\theta}; \{\mathbb{1}_{X_i}\}_{i=1}^N, \{\delta_{d_j}\}_{j=1}^r \right). \quad (4.1.7.1)$$

Here

$$\underline{\theta} = \begin{cases} \theta_1 & \text{if } N + r = 2, \\ \theta_1 \circ_2 (\dots \circ_2 (\theta_{N+r-2} \circ_2 \theta_{N+r-1})) & \text{if } N + r > 2 \end{cases} \quad (4.1.7.2)$$

with each θ_k a 2-cell, and each $\delta_{d_j} \in \text{WD}^{(d_j)}$ is a 1-delay node as in Assumption 4.1.1.

Proof. Recall that $\underline{X} = (X_1, \dots, X_N)$ and $\text{DN}_\varphi = \text{DN}_\psi = \{d_1, \dots, d_r\}$. For $N + 1 \leq j \leq N + r$ define the box $X_j = d_j \in \text{Box}_S$ as

$$X_j^{\text{in}} = \{d_j\} = X_j^{\text{out}}.$$

For $1 \leq i \leq N + r$ define the box

$$X^{\geq i} = \coprod_{p=i}^{N+r} X_p \in \text{Box}_S.$$

Note that $X^{\geq 1} = X'$ (4.1.1.2). Next, for $1 \leq k \leq N + r - 1$, define the 2-cell

$$\theta_k = \theta_{X_k, X^{\geq k+1}} \in \text{WD}(X_k, X^{\geq k+1}).$$

Then we have a wiring diagram

$$\underline{\theta} \in \text{WD}(X_1, \dots, X_{N+r})$$

in which θ^* is defined as in (4.1.7.2). Since $\mathbb{1}_{X_i} \in \text{WD}(X_i)$ and $\delta_{d_j} \in \text{WD}^{(d_j)}$, the operadic composition on the right side of (4.1.7.1) is defined and belongs to $\text{WD}(\underline{X}')$.

Since the two sides of (4.1.7.1) both have delay nodes $\{d_1, \dots, d_r\}$, it remains to check that the supplier assignment of the right side is equal to $s_\varphi = \text{Id}$. This follows from a direct inspection because (i) colored units (Def. 2.3.2), 1-delay nodes (Def.

3.1.2), and 2-cells (Def. 3.1.4) all have identity supplier assignments and because (ii) γ (2.1.6.1) is an iteration of various \circ_i (Def. 2.3.3). \square

4.2. Unary Wiring Diagrams

In this section, we analyze wiring diagrams with exactly one input box and no delay nodes, such as α (4.1.4.1). We will show that such a wiring diagram can be generated by the generating wiring diagrams (Def. 3.1.9) of name changes (Def. 3.1.3), 1-loops (Def. 3.1.5), 1-wasted wires (Def. 3.1.8), in-splits (Def. 3.1.6), and out-splits (Def. 3.1.7), in this order. We remind the reader of Notation 3.3.1 for (iterated) \circ_1 .

We will need a few definitions and notations.

Definition 4.2.1. Suppose $\pi \in \text{WD}(X^Y)$ is a wiring diagram with one input box X and no delay nodes.

- (1) A *loop element* in π is an element $x \in X^{\text{out}}$ such that there exists $x' \in X^{\text{in}}$ with x as its supply wire. The set of loop elements in π is denoted by π^{lp} .
- (2) An element $x' \in X^{\text{in}}$ is said to be *internally supplied* if $s_\pi(x') \in X^{\text{out}}$. The set of such elements in π is denoted by π_+^{sp} .
- (3) An element $x' \in X^{\text{in}}$ is said to be *externally supplied* if $s_\pi(x') \in Y^{\text{in}}$. The set of such elements in π is denoted by π_-^{sp} .


Recall from Definition 2.2.9 the concepts of external wasted wires π_-^{w} and of internal wasted wires π_+^{w} of a wiring diagram π .

Lemma 4.2.2. Suppose $\pi \in \text{WD}(X^Y)$ is a wiring diagram with one input box X and no delay nodes. Then:

- (1) $\pi_+^{\text{sp}} \sqcup \pi_-^{\text{sp}} = X^{\text{in}}$.
- (2) $\pi_+^{\text{w}} \sqcup \pi^{\text{lp}} \subseteq X^{\text{out}}$.
- (3) $s_\pi(\pi_+^{\text{sp}}) = \pi^{\text{lp}}$.
- (4) $s_\pi(\pi_-^{\text{sp}}) \sqcup \pi_-^{\text{w}} = Y^{\text{in}}$.
- (5) $s_\pi(Y^{\text{out}}) \subseteq X^{\text{out}} \setminus \pi_+^{\text{w}}$.

Proof. All the statements are immediate from the definitions. \square


Example 4.2.3. Consider the wiring diagram $\pi \in \text{WD}(X^Y)$ as depicted in the picture



with

- $X^{\text{in}} = \{x_1, x_2, x_3, x_4\}$, $X^{\text{out}} = \{x^1, x^2, x^3\}$, $Y^{\text{in}} = \{y_1, y_2\}$, and $Y^{\text{out}} = \{y^1, y^2\}$;
- $\pi^{\text{lp}} = \{x^1\}$, $\pi_+^{\text{sp}} = \{x_1, x_2\}$, $\pi_-^{\text{sp}} = \{x_3, x_4\}$, $\pi_+^{\text{w}} = \{x^3\}$, and $\pi_-^{\text{w}} = \{y_1\}$.

Note that we may operadically decompose π as follows.



(4.2.3.1)

The point of this decomposition is that the inner wiring diagram π_2 is generated by:

- two 1-wasted wires, one for the external wasted wire y_1 and the other for the internal wasted wire x^3 ;
- two in-splits, one for $\{x_1, x_2\}$ and the other for $\{x_3, x_4\}$;
- one out-split for x^1 , which is the supply wire of y^1 , x_1 , and x_2 .

At the same time, the outer wiring diagram π_1 is generated by two 1-loops, one for the loop element x^1 and the other for the internal wasted wire x^3 .

With this example as a guide, next we will factor a general wiring diagram with one input box and no delay nodes into two wiring diagrams. The outer wiring diagram will be generated by name changes and 1-loops. The inner wiring diagram will be generated by 1-wasted wires, in-splits, and out-splits. The intermediate gray box in (4.2.3.1) will be called Z below.

Convention 4.2.4. Using the five elementary relations (3.3.3.1), (3.3.4.1), (3.3.5.1), (3.3.6.1), and (3.3.7.1), name changes can always be rewritten on the outside (i.e., left side) of an iterated operadic composition in WD. Moreover, using the elementary relation (3.3.2.1), an iteration of name changes can be composed down into just one name change. To simplify the presentation, in what follows these elementary relations regarding name changes are automatically applied wherever necessary. With this in mind, we will mostly not mention name changes.

For a wiring diagram with one input box and no delay nodes, we will decompose it using the wiring diagrams in the next definition.

Definition 4.2.5. Suppose $\pi \in \text{WD}(X^Y)$ is a wiring diagram with one input box X and no delay nodes.

- (1) Define the box $Z \in \text{Box}_S$ as

$$\begin{aligned} Z^{\text{in}} &= Y^{\text{in}} \sqcup \pi_+^{\text{w}} \sqcup \pi^{\text{lp}}; \\ Z^{\text{out}} &= Y^{\text{out}} \sqcup \pi_+^{\text{w}} \sqcup \pi^{\text{lp}}. \end{aligned}$$

- (2) Define the wiring diagram $\pi_1 \in \text{WD}(Z^Y)$ with:

- one input box Z , output box Y , and no delay nodes;
- supplier assignment

$$\begin{aligned} \text{Dm}_{\pi_1} &= Y^{\text{out}} \sqcup Z^{\text{in}} = Y^{\text{out}} \sqcup [Y^{\text{in}} \sqcup \pi_+^{\text{w}} \sqcup \pi^{\text{lp}}] \\ &\quad \downarrow s_{\pi_1} \\ \text{Sp}_{\pi_1} &= Y^{\text{in}} \sqcup Z^{\text{out}} = Y^{\text{in}} \sqcup [Y^{\text{out}} \sqcup \pi_+^{\text{w}} \sqcup \pi^{\text{lp}}] \end{aligned} \tag{4.2.5.1}$$

the identity function.

- (3) Define the wiring diagram $\pi_2 \in \text{WD}(X^Z)$ with:

- one input box X , output Z , and no delay nodes;
- supplier assignment

$$\begin{aligned} \text{Dm}_{\pi_2} &= Z^{\text{out}} \sqcup X^{\text{in}} = [Y^{\text{out}} \sqcup \pi_+^{\text{w}} \sqcup \pi^{\text{lp}}] \sqcup [\pi_+^{\text{sp}} \sqcup \pi_-^{\text{sp}}] \\ &\quad \downarrow s_{\pi_2} \\ \text{Sp}_{\pi_2} &= Z^{\text{in}} \sqcup X^{\text{out}} = [Y^{\text{in}} \sqcup \pi_+^{\text{w}} \sqcup \pi^{\text{lp}}] \sqcup X^{\text{out}} \end{aligned} \tag{4.2.5.2}$$

whose restriction to:

- Y^{out} is $s_{\pi} : Y^{\text{out}} \longrightarrow X^{\text{out}}$;
- $\pi_+^{\text{w}} \sqcup \pi^{\text{lp}}$ is the subset inclusion into X^{out} ;
- π_+^{sp} is $s_{\pi} : \pi_+^{\text{sp}} \longrightarrow \pi^{\text{lp}}$;
- π_-^{sp} is $s_{\pi} : \pi_-^{\text{sp}} \longrightarrow Y^{\text{in}}$.

This is well-defined by the non-instantaneity requirement (2.2.9.2) for π and Lemma 4.2.2.

Lemma 4.2.6. Suppose $\pi \in \text{WD}(X^Y)$ is a wiring diagram with one input box X and no delay nodes. Then it admits a decomposition

$$\pi = \pi_1 \circ \pi_2 \tag{4.2.6.1}$$

in which $\pi_1 \in \text{WD}(Z^Y)$ and $\pi_2 \in \text{WD}(X^Z)$ are as in Def. 4.2.5.

Proof. Both sides of (4.2.6.1) belong to $\text{WD}(\overset{Y}{X})$ and have no delay nodes. So it remains to check that the supplier assignment s of $\pi_1 \circ \pi_2$ is equal to s_π . Note that

$$\text{Dm}_{\pi_1 \circ \pi_2} = Y^{\text{out}} \sqcup X^{\text{in}} = Y^{\text{out}} \sqcup [\pi_+^{\text{sp}} \sqcup \pi_-^{\text{sp}}].$$

By the definitions of $\circ = \circ_1$ (Def. 2.3.3), s_{π_1} (4.2.5.1), and s_{π_2} (4.2.5.2):

- on Y^{out} the supplier assignment s is $s_{\pi_2} s_{\pi_1} = s_\pi \text{Id} = s_\pi$.
- on $\pi_+^{\text{sp}} \sqcup \pi_-^{\text{sp}}$ the supplier assignment s is $s_{\pi_2} s_{\pi_1} = \text{Id} s_\pi = s_\pi$.

So the supplier assignment of $\pi_1 \circ \pi_2$ is equal to s_π . \square

To obtain the desired stratified presentation of π , next we observe that π_1 in Def. 4.2.5 is either a colored unit (2.3.2.1) or an iterated operadic composition of 1-loops (Def. 3.1.5). An example of π_1 is the outer wiring diagram in the example (4.2.3.1).

Lemma 4.2.7. *Suppose:*

- $Y, Z \in \text{Box}_S$ such that $Z^{\text{in}} = Y^{\text{in}} \sqcup T$ and $Z^{\text{out}} = Y^{\text{out}} \sqcup T$ for some $T \in \text{Fin}_S$.
- $\zeta \in \text{WD}(\overset{Y}{Z})$ is a wiring diagram with no delay nodes and with supplier assignment

$$\begin{array}{c} \text{Dm}_\zeta = Y^{\text{out}} \sqcup Z^{\text{in}} = Y^{\text{out}} \sqcup [Y^{\text{in}} \sqcup T] \\ \downarrow s_\zeta \\ \text{Sp}_\zeta = Y^{\text{in}} \sqcup Z^{\text{out}} = Y^{\text{in}} \sqcup [Y^{\text{out}} \sqcup T] \end{array}$$

the identity function.


Then the following statements hold.

- (1) $\zeta = \mathbb{1}_Y$ if $T = \emptyset$.
- (2) If $p = |T| > 0$, then there exist 1-loops $\lambda_1, \dots, \lambda_p$ such that

$$\zeta = \lambda_1 \circ \dots \circ \lambda_p. \quad (4.2.7.1)$$

Proof. If $T = \emptyset$, then $\zeta \in \text{WD}(\overset{Y}{Y})$ has no delay nodes and has supplier assignment $s_\zeta = \text{Id}$. So ζ is the Y -colored unit.

Next suppose $T = \{t_1, \dots, t_p\}$ with $p > 0$. For the definitions below, it is convenient to keep in mind the following picture of ζ :



For $0 \leq j \leq p$ define the box $Y_j \in \text{Box}_S$ as

$$Y_j = \begin{cases} Y & \text{if } j = 0; \\ Y \sqcup \{t_1, \dots, t_j\} & \text{if } 1 \leq j \leq p. \end{cases}$$

Here $Y \sqcup \{t_1, \dots, t_j\}$ means a copy of t_i for $1 \leq i \leq j$ is added to each of Y^{in} and Y^{out} . In particular, we have $Y_p = Z$. For $1 \leq j \leq p$ define the 1-loop

$$\lambda_j = \lambda_{Y_j, t_j} \in \text{WD}(Y_j^{Y_j^{-1}})$$

in which $t_j \in Y_j^{\text{in}}$ has supply wire $t_j \in Y_j^{\text{out}}$.

The iterated operadic composition

$$\lambda_1 \circ \dots \circ \lambda_p \in \text{WD}(Y_p^{Y_p^0}) = \text{WD}(Z^Y)$$

has no delay nodes. To see that it is equal to ζ , it remains to check that its supplier assignment is equal to $s_\zeta = \text{Id}$. This holds because each 1-loop λ_j has identity supplier assignment. \square

Observe that Lemma 4.2.7 applies to $\pi_1 \in \text{WD}(Z^Y)$ in Def. 4.2.5 with $T = \pi_+^w \sqcup \pi^{\text{lp}}$. So π_1 is either the Y -colored unit or an iterated operadic composition of 1-loops.

4.3. Unary Wiring Diagrams with No Loop Elements

In order to show that the wiring diagram $\pi_2 \in \text{WD}(Z^X)$ in Def. 4.2.5 is generated by 1-wasted wires, in-splits, and out-splits, first we identify its external wasted wires, internal wasted wires, and loop elements.

Lemma 4.3.1. *Consider the wiring diagram $\pi_2 \in \text{WD}(Z^X)$ in Def. 4.2.5.*

- (1) *The set of external wasted wires in π_2 is $\pi_{2-}^w = \pi_+^w \sqcup \pi_-^w$.*
- (2) *The set of internal wasted wires in π_2 is $\pi_{2+}^w = \emptyset$.*
- (3) *The set of loop elements in π_2 is $\pi_2^{\text{lp}} = \emptyset$.*
- (4) *$s_{\pi_2}(Z^{\text{out}}) = X^{\text{out}}$.*
- (5) *$Z^{\text{in}} = \pi_+^w \sqcup \pi_-^w \sqcup s_{\pi_2}(X^{\text{in}})$.*

Proof. (1) By definition an external wasted wire in π_2 is an element in Z^{in} that is not in the image of s_{π_2} (4.2.5.2). By the definition of s_{π_2} , this is the subset

$$\pi_+^w \sqcup [Y^{\text{in}} \setminus s_\pi(\pi_-^{\text{sp}})] \subseteq Z^{\text{in}}.$$

It follows from the non-instantaneity requirement (2.2.9.2) for π that

$$Y^{\text{in}} \setminus s_\pi(\pi_-^{\text{sp}}) = \pi_-^w.$$

- (2) By definition an internal wasted wire in π_2 is an element in X^{out} that is not in the image of s_{π_2} . An element of X^{out} is either an internal wasted wire in π , or else it is the s_π -image of an element in $\pi_+^{\text{sp}} \sqcup Y^{\text{out}}$. Since

$$\begin{aligned} X^{\text{out}} &= \pi_+^{\text{w}} \sqcup s_\pi(\pi_+^{\text{sp}} \sqcup Y^{\text{out}}) \\ &= \pi_+^{\text{w}} \sqcup [\pi^{\text{lp}} \cup s_\pi(Y^{\text{out}})], \end{aligned}$$

an inspection of the definition of s_{π_2} (4.2.5.2) reveals that all of X^{out} is in the image of s_{π_2} . So π_2 has no internal wasted wires.

- (3) By definition a loop element in π_2 is an element in X^{out} that is the supply wire, under s_{π_2} , of some element in X^{in} . Since $X^{\text{in}} = \pi_+^{\text{sp}} \sqcup \pi_-^{\text{sp}}$, the definition of s_{π_2} (4.2.5.2) yields

$$s_{\pi_2}(\pi_+^{\text{sp}} \sqcup \pi_-^{\text{sp}}) = s_\pi(\pi_+^{\text{sp}}) \sqcup s_\pi(\pi_-^{\text{sp}}) \subseteq \pi^{\text{lp}} \sqcup Y^{\text{in}} \subseteq Z^{\text{in}} = \text{Sp}_{\pi_2} \setminus X^{\text{out}}.$$


So π_2 has no loop elements.

- (4) By (2) π_2 has no internal wasted wires, so $X^{\text{out}} = s_{\pi_2}(Z^{\text{out}} \sqcup \pi_{2+}^{\text{sp}})$. But by (3) π_2 has no loop elements, so $\pi_{2+}^{\text{sp}} = \emptyset$ and $X^{\text{out}} = s_{\pi_2}(Z^{\text{out}})$.
- (5) Since π_2 has no loop elements by (3), $s_{\pi_2}(X^{\text{in}}) \subseteq Z^{\text{in}}$. An element in Z^{in} that is not in $s_{\pi_2}(X^{\text{in}})$ is precisely an external wasted wire in π_2 . By (1) the set of external wasted wires in π_2 is $\pi_+^{\text{w}} \sqcup \pi_-^{\text{w}}$.


□

Continuing our analysis of wiring diagrams with one input box and no delay nodes, our next goal is to construct a decomposition for π_2 (Def. 4.2.5) involving 1-wasted wires, in-splits, and out-splits.

Example 4.3.2. Consider the inner wiring diagram $\pi_2 \in \text{WD}(\frac{Z}{X})$ in the example (4.2.3.1), which is depicted in the following picture.



For this wiring diagram, the desired decomposition is depicted in the picture:



The inner gray box will be called V , and the outer gray box will be called W below. Note that:

- The outermost wiring diagram $\beta_1 \in \text{WD}(\frac{Z}{W})$ is generated by two 1-wasted wires.
- The middle wiring diagram $\beta_2 \in \text{WD}(\frac{W}{V})$ is generated by two in-splits.
- The innermost wiring diagram $\beta_3 \in \text{WD}(\frac{V}{X})$ is an out-split.

For a general wiring diagram with one input box, no delay nodes, no loop elements, and no internal wasted wires, such a decomposition uses the following definitions.

Definition 4.3.3. Suppose $X, Z \in \text{Box}_S$ and $\beta \in \text{WD}(\frac{Z}{X})$ is a wiring diagram with no delay nodes and no loop elements.

- (1) Suppose the box $W = Z \setminus \beta_-^w \in \text{Box}_S$ is obtained from $Z \in \text{Box}_S$ by removing the external wasted wires of β , so $W^{\text{in}} = Z^{\text{in}} \setminus \beta_-^w$ and $W^{\text{out}} = Z^{\text{out}}$.
- (2) Define the wiring diagram $\beta_1 \in \text{WD}(\frac{Z}{W})$ as having:
 - no delay nodes;
 - supplier assignment

$$\begin{aligned} \text{Dm}_{\beta_1} &= Z^{\text{out}} \sqcup W^{\text{in}} = Z^{\text{out}} \sqcup [Z^{\text{in}} \setminus \beta_-^w] & (4.3.3.1) \\ &\downarrow s_{\beta_1} \\ \text{Sp}_{\beta_1} &= Z^{\text{in}} \sqcup W^{\text{out}} = Z^{\text{in}} \sqcup Z^{\text{out}} \end{aligned}$$

the identity function on Z^{out} and the subset inclusion on $Z^{\text{in}} \setminus \beta_-^w \subseteq Z^{\text{in}}$.

- (3) Define the box $V \in \text{Box}_S$ as $V^{\text{in}} = X^{\text{in}}$ and $V^{\text{out}} = Z^{\text{out}} = W^{\text{out}}$.
- (4) Define the wiring diagram $\beta_2 \in \text{WD}(\frac{W}{V})$ as having:
 - no delay nodes;
 - supplier assignment

$$\begin{aligned} \text{Dm}_{\beta_2} &= W^{\text{out}} \sqcup V^{\text{in}} = W^{\text{out}} \sqcup X^{\text{in}} & (4.3.3.2) \\ &\downarrow s_{\beta_2} \\ \text{Sp}_{\beta_2} &= W^{\text{in}} \sqcup V^{\text{out}} = [Z^{\text{in}} \setminus \beta_-^w] \sqcup W^{\text{out}} \end{aligned}$$

the coproduct of the identity function on W^{out} and the restriction of the supplier assignment $s_\beta : X^{\text{in}} \longrightarrow Z^{\text{in}} \setminus \beta_-^w$.

This is well-defined because β has no delay nodes and no loop elements.

- (5) Define the wiring diagram $\beta_3 \in \text{WD}(\frac{V}{X})$ as having:
 - no delay nodes;

- supplier assignment

$$\begin{array}{c} \text{Dm}_{\beta_3} = V^{\text{out}} \sqcup X^{\text{in}} = Z^{\text{out}} \sqcup X^{\text{in}} \\ \downarrow s_{\beta_3} \\ \text{Sp}_{\beta_3} = V^{\text{in}} \sqcup X^{\text{out}} = X^{\text{in}} \sqcup X^{\text{out}} \end{array} \quad (4.3.3.3)$$

the coproduct of the identity function on X^{in} and $s_{\beta} : Z^{\text{out}} \longrightarrow X^{\text{out}}$. This is well-defined because β has no delay nodes and because of the non-instantaneity requirement (2.2.9.2) for β .

Lemma 4.3.4. *In the context of Def. 4.3.3:*

- (1) *The map $s_{\beta} : X^{\text{in}} \longrightarrow Z^{\text{in}} \setminus \beta_-^{\text{w}}$, which is part of s_{β_2} , is surjective.*
- (2) *If β has no internal wasted wires (such as π_2 in Def. 4.2.5), then the map $s_{\beta} : Z^{\text{out}} \longrightarrow X^{\text{out}}$, which is part of s_{β_3} , is surjective.*

Proof. The first assertion is true because β has no delay nodes and because of the non-instantaneity requirement (2.2.9.2). The second assertion is true because β has no delay nodes and no loop elements. \square

Lemma 4.3.5. *In the context of Def. 4.3.3, there is a decomposition*

$$\beta = \beta_1 \circ \beta_2 \circ \beta_3 \in \text{WD}(\frac{Z}{X}). \quad (4.3.5.1)$$

Proof. By construction the iterated operadic composition $\beta_1 \circ \beta_2 \circ \beta_3$ also belongs to $\text{WD}(\frac{Z}{X})$ and has no delay nodes. So it remains to check that its supplier assignment s is equal to s_{β} . A direct inspection of (4.3.3.1), (4.3.3.2), and (4.3.3.3) reveals that:

- on $X^{\text{in}} \subseteq \text{Dm}_{\beta_3}$ the supplier assignment s is given by $\text{Id}_{s_{\beta_2}} \text{Id}_{X^{\text{in}}} = s_{\beta}$;
- on $Z^{\text{out}} \subseteq \text{Dm}_{\beta_1}$ the supplier assignment s is given by $s_{\beta_3} \text{Id}_{Z^{\text{out}}} \text{Id}_{Z^{\text{out}}} = s_{\beta}$.

So the supplier assignment of $\beta_1 \circ \beta_2 \circ \beta_3$ is equal to s_{β} . \square

Note that the decomposition in Lemma 4.3.5 applies to π_2 because π_2 has one input box, no delay nodes, and no loop elements (by Lemma 4.3.1).

Next we show that in the decomposition 4.3.5.1:

- (1) β_1 is either a colored unit (Def. 2.3.2) or an iterated operadic composition of 1-wasted wires (Def. 3.1.8). See Lemma 4.3.6.
- (2) β_2 is either a colored unit or an iterated operadic composition of in-splits (Def. 3.1.6). See Lemma 4.3.8.

- (3) If β has no internal wasted wires, such as π_2 by Lemma 4.3.1, then β_3 is either a colored unit or an iterated operadic composition of out-splits (Def. 3.1.7). See Lemma 4.3.10.

The following observation deals with the first statement.

Lemma 4.3.6. Consider the wiring diagram $\beta_1 \in \text{WD}(\frac{Z}{W})$ in Def. 4.3.3.

- (1) If $\beta_-^w = \emptyset$ (i.e., β has no external wasted wires), then $\beta_1 = \mathbb{1}_Z$, the Z -colored unit.
(2) If $q = |\beta_-^w| > 0$, then there exist 1-wasted wires $\omega_1, \dots, \omega_q$ such that

$$\beta_1 = \omega_1 \circ \dots \circ \omega_q. \quad (4.3.6.1)$$

Proof. Recall that β_1 has no delay nodes and has supplier assignment (4.3.3.1)


$$\begin{aligned} \text{Dm}_{\beta_1} &= Z^{\text{out}} \sqcup W^{\text{in}} = Z^{\text{out}} \sqcup [Z^{\text{in}} \setminus \beta_-^w] \\ &\quad \downarrow s_{\beta_1} \\ \text{Sp}_{\beta_1} &= Z^{\text{in}} \sqcup W^{\text{out}} = Z^{\text{in}} \sqcup Z^{\text{out}} \end{aligned}$$

that is the identity function on Z^{out} and the subset inclusion on $Z^{\text{in}} \setminus \beta_-^w$. If $\beta_-^w = \emptyset$, then $s_{\beta_1} = \text{Id}$ and, therefore, β_1 is the colored unit.

Next suppose $\beta_-^w = \{w_1, \dots, w_q\} \subseteq Z^{\text{in}}$ with $q > 0$. Recall that $W = Z \setminus \beta_-^w$. For $0 \leq j \leq q$ define the box

$$Z_j = \begin{cases} Z & \text{if } j = 0; \\ Z \setminus \{w_1, \dots, w_j\} & \text{if } 1 \leq j \leq q. \end{cases}$$

So in particular $Z_q = W$. The iterated operadic composition on the right side of (4.3.6.1) is represented in the following picture.



Here the outermost box is Z , the outermost gray box is Z_1 , and the innermost gray box is Z_{q-1} .

For $1 \leq j \leq q$ define the 1-wasted wires (Def. 3.1.8)

$$\omega_j = \omega_{Z_{j-1}, w_j} \in \text{WD}(\frac{Z_{j-1}}{Z_j}).$$

The iterated operadic composition


$$\omega_1 \circ \dots \circ \omega_q \in \text{WD}(\frac{Z_0}{Z_q}) = \text{WD}(\frac{Z}{W})$$

has no delay nodes. So to prove (4.3.6.1), it remains to check that its supplier assignment s is equal to s_{β_1} .

- On $Z^{\text{out}} \subseteq \text{Dm}_{\omega_1}$ the supplier assignment s is the composition of q copies of the identity function, hence is the identity function.
- On $W^{\text{in}} \subseteq \text{Dm}_{\omega_q}$ the supplier assignment s is the composition of the inclusions $Z_j^{\text{in}} \longrightarrow Z_{j-1}^{\text{in}}$ for $1 \leq j \leq q$, which is the inclusion $W^{\text{in}} \longrightarrow Z^{\text{in}}$.

□

To show that β_2 is either a colored unit or an iterated composition of in-splits, we first need a lemma that says that the following wiring diagram is generated by in-splits.



Lemma 4.3.7. *Suppose:*

- $X, Y \in \text{Box}_S$ such that $X^{\text{out}} = Y^{\text{out}}$.
- There exist $y \in Y^{\text{in}}$ and distinct elements $x_1, \dots, x_k \in X^{\text{in}}$ with $k \geq 1$ such that

$$X^{\text{in}} = [Y^{\text{in}} \setminus \{y\}] \sqcup \{x_1, \dots, x_k\}$$

and $v(y) = v(x_i) \in S$ for all i .

- $\sigma \in \text{WD}_{(X)}^Y$ is a wiring diagram with no delay nodes and with supplier assignment

$$\text{Dm}_{\sigma} = Y^{\text{out}} \sqcup X^{\text{in}} = Y^{\text{out}} \sqcup [Y^{\text{in}} \setminus \{y\}] \sqcup \{x_1, \dots, x_k\}$$

$$\begin{array}{c} \downarrow \\ s_{\sigma} \end{array}$$

$$\text{Sp}_{\sigma} = Y^{\text{in}} \sqcup X^{\text{out}} = Y^{\text{in}} \sqcup Y^{\text{out}}$$

given by

$$s_{\sigma}(z) = \begin{cases} y & \text{if } z = x_1, \dots, x_k; \\ z & \text{if } z \in Y^{\text{out}} \sqcup [Y^{\text{in}} \setminus \{y\}]. \end{cases}$$


Then:

- (1) σ is the Y -colored unit if $k = 1$;
- (2) σ is an iterated operadic composition of $(k - 1)$ in-splits if $k \geq 2$.

Proof. Since σ has no delay nodes, if $k = 1$, then $s_{\sigma} = \text{Id}$. So σ is a colored unit.

Suppose $k \geq 2$. We will prove that σ is an iterated operadic composition of $(k-1)$ in-splits by induction on k . If $k = 2$, then by definition σ is the in-split σ_{X, x_1, x_2} (Def. 3.1.6).

Suppose $k \geq 3$. We will factor σ into two wiring diagrams as depicted in the picture



in which the intermediate gray box will be called W below. The outer wiring diagram σ_1 will be an in-split, and the inner wiring diagram σ_2 will be an iterated operadic composition of $(k-2)$ in-splits. To define such a decomposition, we will need the following definitions.

- (1) Suppose $W \in \text{Box}_S$ such that $W^{\text{out}} = Y^{\text{out}} = X^{\text{out}}$ and

$$W^{\text{in}} = [Y^{\text{in}} \setminus \{y\}] \sqcup \{x', x_k\}$$

for some $x_k \neq x'$ such that $v(x') = v(x_k) \in S$. In particular, we have

$$X^{\text{in}} = [W^{\text{in}} \setminus \{x'\}] \sqcup \{x_1, \dots, x_{k-1}\}. \quad (4.3.7.1)$$

- (2) Define the wiring diagram $\sigma_1 \in \text{WD}(\overset{Y}{W})$ with no delay nodes and with supplier assignment

$$\text{Dm}_{\sigma_1} = Y^{\text{out}} \sqcup W^{\text{in}} = Y^{\text{out}} \sqcup [Y^{\text{in}} \setminus \{y\}] \sqcup \{x', x_k\}$$

$$\begin{array}{c} \downarrow \\ s_{\sigma_1} \end{array}$$

$$\text{Sp}_{\sigma_1} = Y^{\text{in}} \sqcup W^{\text{out}} = [Y^{\text{in}} \setminus \{y\}] \sqcup \{y\} \sqcup Y^{\text{out}}$$

given by

$$s_{\sigma_1}(z) = \begin{cases} y & \text{if } z = x', x_k \\ z & \text{otherwise.} \end{cases}$$

- (3) Define the wiring diagram $\sigma_2 \in \text{WD}(\overset{W}{X})$ with no delay nodes and with supplier assignment

$$\text{Dm}_{\sigma_2} = W^{\text{out}} \sqcup X^{\text{in}} = W^{\text{out}} \sqcup [Y^{\text{in}} \setminus \{y\}] \sqcup \{x_1, \dots, x_{k-1}\} \sqcup \{x_k\}$$

$$\begin{array}{c} \downarrow \\ s_{\sigma_2} \end{array}$$

$$\text{Sp}_{\sigma_2} = W^{\text{in}} \sqcup X^{\text{out}} = [Y^{\text{in}} \setminus \{y\}] \sqcup \{x', x_k\} \sqcup W^{\text{out}}$$

given by

$$s_{\sigma_2}(z) = \begin{cases} x' & \text{if } z = x_1, \dots, x_{k-1}; \\ z & \text{otherwise.} \end{cases}$$

Then $\sigma_1 \circ \sigma_2 \in \text{WD}(X)$ is a wiring diagram with no delay nodes. To see that it is equal to σ , it suffices to check that the supplier assignment of $\sigma_1 \circ \sigma_2$ is equal to s_σ . This is true by a direct inspection of s_{σ_1} and s_{σ_2} .

By definition σ_1 is the in-split σ_{W, x', x_k} . By (4.3.7.1) the induction hypothesis applies to σ_2 , which says that it is an iterated operadic composition of $(k-2)$ in-splits. Combined with the previous paragraph, it follows that $\sigma = \sigma_1 \circ \sigma_2$ is the iterated operadic composition of $(k-1)$ in-splits, finishing the induction. \square

Next we consider β_2 .

Lemma 4.3.8. *The wiring diagram $\beta_2 \in \text{WD}(V)$ in Def. 4.3.3 is either a colored unit or an iterated operadic composition of in-splits.*


Proof. Recall that $W^{\text{in}} = Z^{\text{in}} \setminus \beta_-^{\text{w}}$, $V^{\text{in}} = X^{\text{in}}$, and $V^{\text{out}} = Z^{\text{out}} = W^{\text{out}}$. The wiring diagram $\beta_2 \in \text{WD}(V)$ has no delay nodes and has supplier assignment (4.3.3.2)

$$\begin{array}{c} \text{Dm}_{\beta_2} = W^{\text{out}} \sqcup V^{\text{in}} = Z^{\text{out}} \sqcup X^{\text{in}} \\ \quad \quad \quad \downarrow s_{\beta_2} \\ \text{Sp}_{\beta_2} = W^{\text{in}} \sqcup V^{\text{out}} = [Z^{\text{in}} \setminus \beta_-^{\text{w}}] \sqcup Z^{\text{out}} \end{array}$$

the coproduct of the identity function on Z^{out} and $s_\beta : X^{\text{in}} \longrightarrow Z^{\text{in}} \setminus \beta_-^{\text{w}}$. Write $W^{\text{in}} = Z^{\text{in}} \setminus \beta_-^{\text{w}} = \{z_1, \dots, z_p\}$, so each $s_\beta^{-1}(z_i)$ is non-empty by Lemma 4.3.4.

If $p = 0$, then $Z^{\text{in}} \setminus \beta_-^{\text{w}} = \emptyset = X^{\text{in}}$, and β_2 is the W -colored unit.

Suppose $p > 0$. We will write β_2 as an iterated composition as in the following picture.



There are $p - 1$ gray boxes. The outermost gray box will be called W_1 , and the innermost gray box will be called W_{p-1} below. To define such a decomposition, we will need the following definitions.

- (1) For $0 \leq j \leq p$ define the box $W_j \in \text{Box}_S$ with $W_j^{\text{out}} = W^{\text{out}}$ and

$$W_j^{\text{in}} = \underbrace{\left[\prod_{i=1}^j s_\beta^{-1}(z_i) \right]}_{\emptyset \text{ if } j=0} \sqcup \underbrace{\{z_{j+1}, \dots, z_p\}}_{\emptyset \text{ if } j=p}.$$

Note that $W_0^{\text{in}} = W^{\text{in}}$ by definition, while $W_p^{\text{in}} = X^{\text{in}} = V^{\text{in}}$ by Lemma 4.3.4. So $W_0 = W$ and $W_p = V$.

- (2) For $1 \leq j \leq p$ define the wiring diagram $\sigma_j \in \text{WD}(W_{j-1}^{\text{in}})$ with no delay nodes and with supplier assignment

$$\begin{aligned} \text{Dm}_{\sigma_j} &= W_{j-1}^{\text{out}} \sqcup W_j^{\text{in}} = W^{\text{out}} \sqcup \left[\prod_{i=1}^j s_\beta^{-1}(z_i) \right] \sqcup \{z_{j+1}, \dots, z_p\} \\ &\quad \downarrow s_{\sigma_j} \\ \text{Sp}_{\sigma_j} &= W_{j-1}^{\text{in}} \sqcup W_j^{\text{out}} = \left[\prod_{i=1}^{j-1} s_\beta^{-1}(z_i) \right] \sqcup \{z_j, \dots, z_p\} \sqcup W^{\text{out}} \end{aligned}$$

given by

$$s_{\sigma_j}(x) = \begin{cases} z_j & \text{if } x \in s_\beta^{-1}(z_j); \\ x & \text{otherwise.} \end{cases}$$

Since

$$W_j^{\text{in}} = \left[W_{j-1}^{\text{in}} \setminus \{z_j\} \right] \sqcup s_\beta^{-1}(z_j),$$

by Lemma 4.3.7 σ_j is:

- a colored unit if $|s_\beta^{-1}(z_j)| = 1$;
- an iterated operadic composition of $(|s_\beta^{-1}(z_j)| - 1)$ in-splits if $|s_\beta^{-1}(z_j)| \geq 2$.

Therefore, to show that β_2 is either a colored unit or an iterated operadic composition of in-splits, it is enough to check that there is a decomposition

$$\beta_2 = \sigma_1 \circ \dots \circ \sigma_p \in \text{WD}(W).$$


Since the iterated operadic composition on the right has no delay nodes, it remains to check that its supplier assignment s is equal to s_{β_2} (4.3.3.2).

On $W^{\text{out}} = Z^{\text{out}} \subseteq \text{Dm}_{\sigma_1}$ the supplier assignment s is the composition of p identity functions, hence the identity function. On

$$V^{\text{in}} = X^{\text{in}} = \prod_{i=1}^p s_{\beta}^{-1}(z_i) \subseteq \text{Dm}_{\sigma_p}$$

the supplier assignment s sends elements in each $s_{\beta}^{-1}(z_j)$ to $z_j \in W^{\text{in}}$, so it is equal to s_{β_2} . \square

Next, to show that β_3 is either a colored unit or an iterated operadic composition of out-splits, we first need a lemma that says that the following wiring diagram is generated by out-splits.



The following observation is the out-split analogue of Lemma 4.3.7.

Lemma 4.3.9. *Suppose:*

- $X, Y \in \text{Box}_S$ such that $X^{\text{in}} = Y^{\text{in}}$.
- There exist $x \in X^{\text{out}}$ and distinct elements $y_1, \dots, y_k \in Y^{\text{out}}$ with $k \geq 1$ such that

$$Y^{\text{out}} = [X^{\text{out}} \setminus \{x\}] \sqcup \{y_1, \dots, y_k\}$$

and $v(x) = v(y_i) \in S$ for $1 \leq i \leq k$.

- $\sigma \in \text{WD}_{(X)}^Y$ is a wiring diagram with no delay nodes and with supplier assignment

$$\text{Dm}_{\sigma} = Y^{\text{out}} \sqcup X^{\text{in}} = [X^{\text{out}} \setminus \{x\}] \sqcup \{y_1, \dots, y_k\} \sqcup X^{\text{in}}$$

$$\downarrow s_{\sigma}$$

$$\text{Sp}_{\sigma} = Y^{\text{in}} \sqcup X^{\text{out}} = X^{\text{in}} \sqcup X^{\text{out}}$$

given by

$$s_{\sigma}(z) = \begin{cases} x & \text{if } z = y_1, \dots, y_k; \\ z & \text{if } z \in [X^{\text{out}} \setminus \{x\}] \sqcup X^{\text{in}}. \end{cases}$$


Then:

- (1) σ is the Y -colored unit if $k = 1$;
- (2) σ is an iterated operadic composition of $(k - 1)$ out-splits if $k \geq 2$.

Proof. If $k = 1$, then s_{σ} is the identity function, so σ is a colored unit.

The assertion for $k \geq 2$ is proved by induction. If $k = 2$, then σ is by definition the out-split σ^{Y, y_1, y_2} (Def. 3.1.7).

Suppose $k \geq 3$. We will factor σ into two wiring diagrams as depicted in the picture



in which the intermediate gray box will be called W below. The inner wiring diagram σ^2 will be an out-split, and the outer wiring diagram σ^1 will be an iterated operadic composition of $(k-2)$ out-splits. To define such a decomposition, we will need the following definitions.

- (1) Define the box $W \in \text{Box}_S$ with $W^{\text{in}} = X^{\text{in}} = Y^{\text{in}}$ and

$$W^{\text{out}} = [X^{\text{out}} \setminus \{x\}] \sqcup \{w, y_k\}$$

for some $w \neq y_k$ such that $v(w) = v(y_k) \in S$. In particular, we have

$$Y^{\text{out}} = [W^{\text{out}} \setminus \{w\}] \sqcup \{y_1, \dots, y_{k-1}\}. \quad (4.3.9.1)$$

- (2) Define the wiring diagram $\sigma^1 \in \text{WD}(Y^{\text{in}})$ with no delay nodes and with supplier assignment

$$\begin{aligned} \text{Dm}_{\sigma^1} &= Y^{\text{out}} \sqcup W^{\text{in}} = [X^{\text{out}} \setminus \{x\}] \sqcup \{y_1, \dots, y_k\} \sqcup Y^{\text{in}} \\ &\quad \downarrow s_{\sigma^1} \\ \text{Sp}_{\sigma^1} &= Y^{\text{in}} \sqcup W^{\text{out}} = Y^{\text{in}} \sqcup [X^{\text{out}} \setminus \{x\}] \sqcup \{w, y_k\} \end{aligned}$$

given by

$$s_{\sigma^1}(z) = \begin{cases} w & \text{if } z = y_1, \dots, y_{k-1}; \\ z & \text{otherwise.} \end{cases}$$

- (3) Define the wiring diagram $\sigma^2 \in \text{WD}(X^{\text{in}})$ with no delay nodes and with supplier assignment

$$\begin{aligned} \text{Dm}_{\sigma^2} &= W^{\text{out}} \sqcup X^{\text{in}} = [X^{\text{out}} \setminus \{x\}] \sqcup \{w, y_k\} \sqcup W^{\text{in}} \\ &\quad \downarrow s_{\sigma^2} \\ \text{Sp}_{\sigma^2} &= W^{\text{in}} \sqcup X^{\text{out}} \end{aligned}$$

given by

$$s_{\sigma^2}(z) = \begin{cases} x & \text{if } z = w, y_k; \\ z & \text{otherwise.} \end{cases}$$

Then $\sigma^1 \circ \sigma^2 \in \text{WD}(X^V)$ is a wiring diagram with no delay nodes. To see that it is equal to σ , it suffices to check that the supplier assignment of $\sigma^1 \circ \sigma^2$ is equal to s_σ . This is true by a direct inspection of s_{σ^1} and s_{σ^2} .

By (4.3.9.1) the induction hypothesis applies to σ^1 , which says that it is an iterated operadic composition of $(k-2)$ out-splits. By definition σ^2 is the out-split σ^{W,w,y_k} . Combined with the previous paragraph, it follows that $\sigma = \sigma^1 \circ \sigma^2$ is the iterated operadic composition of $(k-1)$ out-splits, finishing the induction. \square

Finally, we consider β_3 .

Lemma 4.3.10. *In the context of Def. 4.3.3, suppose β has no internal wasted wires (such as π_2 (4.2.5.2) by Lemma 4.3.1). Then $\beta_3 \in \text{WD}(X^V)$ is either a colored unit or an iterated operadic composition of out-splits.*


Proof. Recall that the wiring diagram $\beta_3 \in \text{WD}(X^V)$ has no delay nodes and has supplier assignment (4.3.3.3)

$$\begin{array}{c} \text{Dm}_{\beta_3} = V^{\text{out}} \amalg X^{\text{in}} = Z^{\text{out}} \amalg X^{\text{in}} \\ \downarrow s_{\beta_3} \\ \text{Sp}_{\beta_3} = V^{\text{in}} \amalg X^{\text{out}} = X^{\text{in}} \amalg X^{\text{out}} \end{array}$$

the coproduct of the identity function on X^{in} and $s_\beta : Z^{\text{out}} \longrightarrow X^{\text{out}}$. Since β has no internal wasted wires, by Lemma 4.3.4 the map $s_\beta : Z^{\text{out}} \longrightarrow X^{\text{out}}$ is surjective.

Write $X^{\text{out}} = \{x_1, \dots, x_r\}$, so $Z^{\text{out}} = \coprod_{i=1}^r s_\beta^{-1}(x_i)$ with each $s_\beta^{-1}(x_i)$ non-empty. If $r = 0$, then $X^{\text{out}} = \emptyset = Z^{\text{out}}$, and β_3 is a colored unit.

Suppose $r > 0$. We will decompose β_3 as in the picture:



The outermost gray box will be called V_1 , and the innermost gray box will be called V_{r-1} below. To define such a decomposition, we first need some definitions.

(1) For $0 \leq j \leq r$ define the box $V_j \in \text{Box}_S$ with $V_j^{\text{in}} = V^{\text{in}} = X^{\text{in}}$ and

$$V_j^{\text{out}} = \underbrace{\{x_1, \dots, x_j\}}_{\emptyset \text{ if } j=0} \sqcup \underbrace{\prod_{i=j+1}^r s_{\beta}^{-1}(x_i)}_{\emptyset \text{ if } j=r}.$$

Note that $V_0^{\text{out}} = Z^{\text{out}} = V^{\text{out}}$, so $V_0 = V$. Also, $V_r^{\text{out}} = X^{\text{out}}$, so $V_r = X$.

(2) For $1 \leq j \leq r$ define the wiring diagram $\sigma^j \in \text{WD}(\frac{V_{j-1}}{V_j})$ with no delay nodes and with supplier assignment

$$\begin{aligned} \text{Dm}_{\sigma^j} &= V_{j-1}^{\text{out}} \sqcup V_j^{\text{in}} = \{x_1, \dots, x_{j-1}\} \sqcup \prod_{i=j}^r s_{\beta}^{-1}(x_i) \sqcup X^{\text{in}} \\ &\quad \downarrow s_{\sigma^j} \\ \text{Sp}_{\sigma^j} &= V_{j-1}^{\text{in}} \sqcup V_j^{\text{out}} = X^{\text{in}} \sqcup \{x_1, \dots, x_j\} \sqcup \prod_{i=j+1}^r s_{\beta}^{-1}(x_i) \end{aligned}$$

given by

$$s_{\sigma^j}(z) = \begin{cases} x_j & \text{if } z \in s_{\beta}^{-1}(x_j); \\ z & \text{otherwise.} \end{cases}$$

The iterated operadic composition

$$\sigma^1 \circ \dots \circ \sigma^r \in \text{WD}(\frac{V_0}{V_r}) = \text{WD}(\frac{V}{X})$$

has no delay nodes. To see that it is equal to β_3 , it remains to check that the former's supplier assignment s is equal to s_{β_3} .

- On $X^{\text{in}} \subseteq \text{Dm}_{\sigma^r}$ the supplier assignment s is the composition of r identity functions, hence the identity function.
- On $V^{\text{out}} = Z^{\text{out}} \subseteq \text{Dm}_{\sigma^1}$ the supplier assignment s sends elements in each $s_{\beta}^{-1}(x_i)$ to x_i .

So s is equal to s_{β_3} .

By Lemma 4.3.9 each σ^j for $1 \leq j \leq r$ is either a colored unit or an iterated operadic composition of out-splits. Therefore, $\beta_3 = \sigma^1 \circ \dots \circ \sigma^r$ is either a colored unit or an iterated operadic composition of out-splits. \square

Finite Presentation

Fix a class S , with respect to which the Box_S -colored operad WD of wiring diagrams is defined (Theorem 2.3.8). The main purpose of this chapter is to establish finite presentations for the operad WD of wiring diagrams and its variants WD_\bullet and WD_0 . For the operad WD , our finite presentation means the following two statements.

- (1) The 8 generating wiring diagrams (Def. 3.1.9) generate the operad WD . This means that every wiring diagram can be expressed as a finite iterated operadic composition involving only generating wiring diagrams.
- (2) If a wiring diagram can be operadically generated by the generating wiring diagrams in two different ways, then there exists a finite sequence of *elementary equivalences* from the first iterated operadic composition to the other one. An elementary equivalence is induced by either an elementary relation (Def. 3.3.30) or an operad associativity/unity axiom for the generating wiring diagrams.

In Chapter 6 we will use these finite presentations to describe algebras over the operads WD , WD_\bullet , and WD_0 in terms of finitely many generating structure maps and generating axioms corresponding to the generating wiring diagrams and elementary relations. In Section 6.3 we will use the finite presentation for WD -algebras to study the propagator algebra. In Section 6.7 we will use the finite presentation for WD_0 -algebras to study the algebra of open dynamical systems.

In Section 5.1 we establish the first part of the finite presentation theorem for WD by showing that every wiring diagram has a *stratified presentation* (Theorem 5.1.7). A stratified presentation (Def. 5.1.5) is a highly structured iterated operadic composition of the generating wiring diagrams. The proof of the second part of the finite presentation theorem also requires the use of stratified presentations.

In Section 5.2 we establish the second part of the finite presentation theorem for WD. We show that any two presentations of the same wiring diagram in terms of generating wiring diagrams are connected by a finite sequence of elementary equivalences (Theorem 5.2.10).

In Section 5.3 we establish a finite presentation for the operad WD_\bullet of wiring diagrams without delay nodes, which we call *normal* wiring diagrams. Normal wiring diagrams appeared in Spivak's study of mode-dependent networks and dynamical systems [Spi15, Spi15b].

In Section 5.4 we restrict further and establish a finite presentation for the operad WD_0 of wiring diagrams without delay nodes and whose supplier assignments are bijections. We call them *strict* wiring diagrams. They appeared in [VSL14]. We will use strict wiring diagrams in Section 6.7 to study the algebra of open dynamical systems.

5.1. Stratified Presentation

In this section, we define a *stratified presentation* and show that every wiring diagram has a stratified presentation (Theorem 5.1.7). We also need the concept of a *simplex* to discuss generators and relations in the operad WD of wiring diagrams.

Definition 5.1.1. Suppose $n \geq 1$. An n -simplex Ψ and its *composition* $|\Psi| \in \text{WD}$ are defined inductively as follows.

- (1) A 1-simplex is a generating wiring diagram (Def. 3.1.9) ψ . Its *composition* $|\psi|$ is defined as ψ itself.
- (2) Suppose $n \geq 2$ and that k -simplices for $1 \leq k \leq n-1$ and their compositions in WD are already defined. An n -simplex is a tuple $\Psi = (\underline{\psi}, i, \underline{\phi})$ consisting of

- an integer $i \geq 1$,
- a p -simplex $\underline{\psi}$ for some $p \geq 1$, and
- a q -simplex $\underline{\phi}$ for some $q \geq 1$

such that:

- (i) $p + q = n$;
- (ii) the operadic composition

$$|\Psi| \stackrel{\text{def}}{=} |\underline{\psi}| \circ_i |\underline{\phi}| \tag{5.1.1.1}$$

is defined in WD (Def. 2.3.3).

The wiring diagram $|\Psi|$ in (5.1.1.1) is the *composition* of Ψ .

A *simplex* in WD is an m -simplex in WD for some $m \geq 1$. We say that a simplex Ψ is a *presentation* of the wiring diagram $|\Psi|$.

Notation 5.1.2. To simplify notations, we will sometimes use the right side of (5.1.1.1) to denote a simplex. To simplify notations even further, we may even just list the generating wiring diagrams (ψ_1, \dots, ψ_n) in a simplex in the order in which they appear in the composition (5.1.1.1), omitting all the pairs of parentheses and the operadic compositions from the notations.

Remark 5.1.3. Consider Def. 5.1.1.

- (1) In plain language, a simplex is a finite parenthesized word whose alphabets are generating wiring diagrams, in which each pair of parentheses has a well-defined associated \circ_i -composition.
- (2) We could have made the definition for a general operad O other than WD , using a collection of elements in O in place of the generating wiring diagrams. Such a definition would be useful in discussing generators and relations in a general operad O .

Example 5.1.4. Every ψ_i here denotes a generating wiring diagram. Using Notation 5.1.2:

- (1) A 2-simplex has the form (ψ_1, i, ψ_2) , which we abbreviate to $\psi_1 \circ_i \psi_2$, for some integer $i \geq 1$.
- (2) A 3-simplex is an iterated operadic composition in WD of the form

$$(\psi_1 \circ_i \psi_2) \circ_j \psi_3 \quad \text{or} \quad \psi_1 \circ_i (\psi_2 \circ_j \psi_3)$$

for some integers $i, j \geq 1$. Once again these are really abbreviations for the 3-simplices

$$((\psi_1, i, \psi_2), j, \psi_3) \quad \text{or} \quad (\psi_1, i, (\psi_2, j, \psi_3)).$$

- (3) A 4-simplex is an iterated operadic composition in WD of the form

$$((\psi_1 \circ_i \psi_2) \circ_j \psi_3) \circ_k \psi_4, \quad (\psi_1 \circ_i (\psi_2 \circ_j \psi_3)) \circ_k \psi_4, \quad (\psi_1 \circ_i \psi_2) \circ_j (\psi_3 \circ_k \psi_4), \\ \psi_1 \circ_i ((\psi_2 \circ_j \psi_3) \circ_k \psi_4), \quad \text{or} \quad \psi_1 \circ_i (\psi_2 \circ_j (\psi_3 \circ_k \psi_4))$$

for some integers $i, j, k \geq 1$.

In Section 5.2 we will show that any two presentations of the same wiring diagram are equivalent in a certain way. For this purpose, we will need a more structured kind of presentation.

Definition 5.1.5. A *stratified simplex* in WD is a simplex in WD (Def. 5.1.1) of one of the following two forms, where Notation 5.1.2 is used:

- (1) $(\underline{\omega}, \epsilon)$, where:
 - $\underline{\omega}$ is a possibly empty string of 1-wasted wires (Def. 3.1.8);
 - ϵ is the empty wiring diagram (Def. 3.1.1).

- (2) $(\tau, \underline{\lambda}, \underline{\omega}, \underline{\sigma}_*, \underline{\sigma}^*, \underline{\theta}, \underline{\delta})$, where:
- τ is a name change (Def. 3.1.3);
 - $\underline{\lambda}$ is a possibly empty string of 1-loops (Def. 3.1.5);
 - $\underline{\omega}$ is a possibly empty string of 1-wasted wires;
 - $\underline{\sigma}_*$ is a possibly empty string of in-splits (Def. 3.1.6);
 - $\underline{\sigma}^*$ is a possibly empty string of out-splits (Def. 3.1.7);
 - $\underline{\theta}$ is a possibly empty string of 2-cells (Def. 3.1.4);
 - $\underline{\delta}$ is a possibly empty string of 1-delay nodes (Def. 3.1.2).

We call these stratified simplices of type (1) and of type (2), respectively. If Ψ is a stratified simplex, then we call it a *stratified presentation* of the wiring diagram $|\Psi|$.

Remark 5.1.6. Stratified simplices of type (1) and of type (2) are mutually exclusive. Indeed, the composition of a stratified simplex of type (1) has no input boxes and no delay nodes. On the other hand, the composition of a stratified simplex of type (2) either has at least one input box or at least one delay node or both.

We now observe that the generating wiring diagrams generate the operad WD of wiring diagrams in a highly structured way.

Theorem 5.1.7. *Every wiring diagram has a stratified presentation (Def. 5.1.5).*

Proof. Suppose $\psi \in \text{WD}(\underline{X})$ is a general wiring diagram as in Assumption 4.1.1 with input boxes $\underline{X} = (X_1, \dots, X_N)$ and delay nodes $\text{DN}_\psi = \{d_1, \dots, d_r\}$. Recall Notation 3.3.1 for (iterated) \circ_1 .

If $N = r = 0$, then ψ has a stratified presentation of type (1) by Lemma 4.1.2.

Next suppose $N + r \geq 1$. We use the decomposition $\psi = \alpha \circ \varphi$ (4.1.5.1) and show that ψ has a stratified presentation of type (2) using the following observations.

- (1) If $N + r = 1$, then φ is either a colored unit, which can be ignored in a simplex by Lemma 2.3.5, or a 1-delay node by Lemma 4.1.6.
- (2) If $N + r \geq 2$, then φ has a stratified presentation $(\underline{\theta}, \underline{\delta})$ consisting of 2-cells and 1-delay nodes by Lemma 4.1.7 and by the equivalence between γ and the \circ_i -compositions (2.1.6.1).
- (3) By definition α (4.1.4.1) has one input box and no delay nodes. There is a decomposition $\alpha = \pi_1 \circ \pi_2$ by Lemma 4.2.6. The outer wiring diagram π_1 is either a colored unit or has a stratified presentation $(\underline{\lambda})$ consisting of 1-loops by Lemma 4.2.7.
- (4) Furthermore, by Lemma 4.3.5 there is a decomposition $\pi_2 = \beta_1 \circ \beta_2 \circ \beta_3$ in which:
 - β_1 is a colored unit or has a stratified presentation $(\underline{\omega})$ consisting of 1-wasted wires by Lemma 4.3.6.

- β_2 is a colored unit or has a stratified presentation ($\underline{\sigma}_*$) consisting of in-splits by Lemma 4.3.8.
- β_3 is a colored unit or has a stratified presentation ($\underline{\sigma}^*$) consisting of out-splits by Lemma 4.3.10.

Using the decomposition

$$\psi = \pi_1 \circ \beta_1 \circ \beta_2 \circ \beta_3 \circ \varphi$$

together with Convention 4.2.4, we obtain the desired stratified presentation of type (2) for ψ when $N + r \geq 1$. \square

5.2. Finite Presentation for Wiring Diagrams

The purpose of this section is to establish the second part of the finite presentation theorem for the operad WD. First we define precisely what it means for two presentations of the same wiring diagram to be related to each other. Recall the 28 elementary relations (Def. 3.3.30) and the definition of a colored operad (Def. 2.1.4). In what follows, we will regard each operad associativity or unity axiom as an equality. We remind the reader of Notation 5.1.2 regarding simplices in WD.

Definition 5.2.1. Suppose Ψ is an n -simplex in WD as in Def. 5.1.1.

- (1) A *subsimplex* of Ψ is a simplex in WD defined inductively as follows.
 - If Ψ is a 1-simplex, then a *subsimplex* of Ψ is Ψ itself.
 - Suppose $n \geq 2$ and $\Psi = (\underline{\psi}, i, \underline{\phi})$ for some $i \geq 1$, p -simplex $\underline{\psi}$, and q -simplex $\underline{\phi}$ with $p + q = n$. Then a *subsimplex* of Ψ is
 - a subsimplex of $\underline{\psi}$,
 - a subsimplex of $\underline{\phi}$, or
 - Ψ itself.

If Ψ' is a subsimplex of Ψ , then we write $\Psi' \subseteq \Psi$.

- (2) An *elementary subsimplex* Ψ' of Ψ is a subsimplex of one of two forms:
 - (i) Ψ' is one side (either left or right) of a specified elementary relation (Def. 3.3.30).
 - (ii) Ψ' is one side (either left or right) of a specified operad associativity or unity axiom—(2.1.4.3), (2.1.4.4), (2.1.4.5), or (2.1.4.6)—involving only the generating wiring diagrams (Def. 3.1.9).
- (3) Suppose Φ is another simplex in WD. Then Ψ and Φ are said to be *equivalent* if their compositions are equal; i.e., $|\Psi| = |\Phi| \in \text{WD}$.
- (4) Suppose:
 - $\Psi' \subseteq \Psi$ is an elementary subsimplex corresponding to one side of R , which is either an elementary relation or an operad associativity/unity axiom for the generating wiring diagrams.
 - Ψ'' is the simplex given by the other side of R .

- Ψ^1 is the simplex obtained from Ψ by replacing the subsimplex Ψ' by Ψ'' .

We say that Ψ and Ψ^1 are *elementarily equivalent*. Note that elementarily equivalent simplices are also equivalent.

- (5) If Ψ and Φ are elementarily equivalent, we write $\Psi \sim \Phi$ and call this an *elementary equivalence*.
- (6) Suppose Ψ_0, \dots, Ψ_r are simplices for some $r \geq 1$ and that there exist elementary equivalences

$$\Psi_0 \sim \Psi_1 \sim \dots \sim \Psi_r.$$

Then we say that Ψ_0 and Ψ_r are *connected by a finite sequence of elementary equivalences*. Note that in this case Ψ_0 and Ψ_r are equivalent.

Remark 5.2.2. In the definition of an elementary subsimplex and an elementary equivalence, we did *not* use the operad equivariance axiom (2.1.4.7). The reason is that the associativity and commutativity properties of 2-cells—namely, the elementary relations (3.3.9.1) and (3.3.10.1)—are enough to guarantee the operad equivariance axiom involving only the generating wiring diagrams.

Example 5.2.3. In a 3-simplex $(\psi_1 \circ_i \psi_2) \circ_j \psi_3$, both

$$(\psi_1, \psi_2) = \psi_1 \circ_i \psi_2 \quad \text{and} \quad (\psi_1, \psi_2, \psi_3) = (\psi_1 \circ_i \psi_2) \circ_j \psi_3$$

are subsimplices. However, (ψ_2, ψ_3) is not a subsimplex.

Example 5.2.4. A given wiring diagram may have many different equivalent presentations. For example, suppose $X \in \text{Box}_S$. Then the 1-simplex consisting of the X -colored unit $\mathbb{1}_X$ (2.3.2.1) is elementarily equivalent to:

- (1) the 2-simplex $\theta_{X, \emptyset} \circ_2 \epsilon$ by (3.3.8.1);
- (2) the 3-simplex $(\lambda_{Z, x}) \circ (\omega_{Z, x_1}) \circ (\sigma^{Y, x^1, x^2})$ by (3.3.20.1);
- (3) the 2-simplex $(\sigma_{Y, x, y}) \circ (\omega_{Y, y})$ by (3.3.25.1).

Any two of these three simplices are connected by a finite sequence of elementary equivalences. Note that elementarily equivalent simplices may have different lengths.

Example 5.2.5. Suppose:

- $\theta_{X, Y} \in \text{WD}(\frac{X \sqcup Y}{X, Y})$ is a 2-cell (Def. 3.1.4).
- $\theta_{V, W} \in \text{WD}(\frac{X}{V, W})$ is a 2-cell with $X = V \sqcup W \in \text{Box}_S$.
- $\sigma_{T, t_1, t_2} \in \text{WD}(\frac{Y}{T})$ is an in-split (Def. 3.1.6).

Then the 3-simplices

$$(\theta_{X, Y} \circ_1 \theta_{V, W}) \circ_3 \sigma_{T, t_1, t_2} \quad \text{and} \quad (\theta_{X, Y} \circ_2 \sigma_{T, t_1, t_2}) \circ_1 \theta_{V, W}$$

are elementarily equivalent by the horizontal associativity axiom (2.1.4.3).

Convention 5.2.6. In what follows, to simplify the presentation, elementary equivalences corresponding to an operad associativity/unity axiom—(2.1.4.3), (2.1.4.4), (2.1.4.5), or (2.1.4.6)—for the generating wiring diagrams will often be applied tacitly wherever necessary. For instance, an elementary equivalence given by replacing one of the 3-simplices in Example 5.2.5 by the other one will often *not* be mentioned explicitly.

Our next goal is to show that any two equivalent simplices are connected by a finite sequence of elementary equivalences. In other words, with respect to the generating wiring diagrams, the 28 elementary relations and the operad associativity/unity axioms—(2.1.4.3), (2.1.4.4), (2.1.4.5), and (2.1.4.6)—for the generating wiring diagrams generate *all* the relations in WD. The first step is to show that every simplex is connected to a stratified simplex in the following sense.

Lemma 5.2.7. *Every simplex is either a stratified simplex or is connected to an equivalent stratified simplex by a finite sequence of elementary equivalences (Def. 5.2.1).*

Proof. Using Notation 5.1.2 suppose $\Psi = (\psi_1, \dots, \psi_n)$ is a simplex with composition $|\Psi| = \psi \in \text{WD}(\underline{X})$ as in Assumption 4.1.1. So ψ has input boxes $\underline{X} = (X_1, \dots, X_N)$ and delay nodes $\text{DN}_\psi = \{d_1, \dots, d_r\}$. Suppose Ψ is not a stratified simplex. We will show that Ψ is connected to an equivalent stratified simplex by a finite sequence of elementary equivalences.

Using the five elementary relations (3.3.3.1)–(3.3.7.1), first we move all the name changes (Def. 3.1.3) in Ψ , if there are any, to the left. Then we use the elementary relation (3.3.2.1) repeatedly to compose them down into one name change. Therefore, after a finite sequence of elementary equivalences, we may assume that there is at most one name change in Ψ , which is the left-most entry. If there are further elementary equivalences later that create name changes, we will perform the same procedure without explicitly mentioning it.

The empty wiring diagram $\epsilon \in \text{WD}(\emptyset)$ (Def. 3.1.1) and the 1-delay nodes $\delta_d \in \text{WD}^d$ (Def. 3.1.2) have no input boxes, so no operadic composition of the forms $\epsilon \circ_i$ – or $\delta_d \circ_i$ – can be defined. Therefore, after a finite sequence of elementary equivalences corresponding to the horizontal associativity axiom (2.1.4.3), we may assume that Ψ has the form

$$\left(\tau, \Psi^1, \underline{\epsilon}, \underline{\delta} \right)$$

in which:

- τ is a name change;
- all the 1-delay nodes $\underline{\delta}$ are at the right-most entries;
- all the empty wiring diagrams $\underline{\epsilon}$ are just to their left;

- Ψ^1 is either empty or is a subsimplex involving 2-cells (Def. 3.1.4), 1-loops (Def. 3.1.5), in-splits (Def. 3.1.6), out-splits (Def. 3.1.7), and 1-wasted wires (Def. 3.1.8).

Next we use the elementary relations (3.3.11.1)–(3.3.14.1) to move all the 2-cells in Ψ to just the left of $\underline{\epsilon}$. Then we use the elementary relations (3.3.16.1)–(3.3.18.1) to move all the remaining 1-loops to just the right of the name change τ . After that, we use the elementary relations (3.3.24.1) and (3.3.28.1) to move all the 1-wasted wires to just the right of the 1-loops. Then we use the elementary relation (3.3.23.1) to move all the in-splits to just the right of the 1-wasted wires. So after a finite sequence of elementary equivalences, we may assume that the simplex Ψ has the form

$$\left(\tau, \underline{\lambda}, \underline{\omega}, \underline{\sigma}_*, \underline{\sigma}^*, \underline{\theta}, \underline{\epsilon}, \underline{\delta} \right). \quad (5.2.7.1)$$

If the string $\underline{\epsilon}$ of empty wiring diagrams is empty, then we are done because this is now a stratified simplex of type (2).

So suppose the string $\underline{\epsilon}$ in (5.2.7.1) is non-empty. Using finitely many elementary equivalences corresponding to the elementary relations (3.3.8.1)–(3.3.10.1), we may cancel all the unnecessary empty wiring diagrams in (5.2.7.1). If there are no empty wiring diagrams left after the cancellation, then we have a stratified simplex of type (2).

Suppose that, after the cancellation in the previous paragraph, the resulting string $\underline{\epsilon}$ is still non-empty. Then it must contain a single empty wiring diagram ϵ , and there are no 2-cells $\underline{\theta}$ and no 1-delay nodes $\underline{\delta}$ in the resulting simplex Ψ . Since the output box of ϵ is the empty box, the current simplex Ψ cannot have any 1-loops $\underline{\lambda}$, in-splits $\underline{\sigma}_*$, or out-splits $\underline{\sigma}^*$. Therefore, in this case the simplex (5.2.7.1) has the form

$$\left(\tau, \underline{\omega}, \epsilon \right). \quad (5.2.7.2)$$

There are now two cases. First suppose the string $\underline{\omega}$ in (5.2.7.2) is empty. Since the output box of ϵ is the empty box, in the simplex (τ, ϵ) the name change τ must be the colored unit of the empty box. So by the left unity axiom (2.1.4.5), the simplex $(\mathbb{1}_\emptyset, \epsilon)$ is elementarily equivalent to the simplex (ϵ) , which is a stratified simplex of type (1).

Next suppose the string $\underline{\omega}$ in (5.2.7.2) is non-empty. Using finitely many elementary equivalences corresponding to the elementary relation (3.3.7.1), the simplex (5.2.7.2) is connected to a simplex of the form

$$\left(\underline{\omega}, \tau, \epsilon \right) \quad (5.2.7.3)$$

with $\tau \circ \epsilon$ as one of the operadic compositions. As in the previous case, the composition $\tau \circ \epsilon$ forces τ to be the colored unit of the empty box. So the simplex $(\underline{\omega}, \mathbb{1}_\emptyset, \epsilon)$

in (5.2.7.3) is elementarily equivalent to the simplex $(\underline{\omega}, \epsilon)$, which is a stratified simplex of type (1). \square

The next step is to show that equivalent stratified simplices are connected. We begin with stratified simplices of type (1).

Lemma 5.2.8. *Any two equivalent stratified simplices of type (1) are either equal or are connected by a finite sequence of elementary equivalences (Def. 5.2.1).*

Proof. Suppose $\Psi^1 = (\underline{\omega}^1, \epsilon)$ and $\Psi^2 = (\underline{\omega}^2, \epsilon)$ are equivalent stratified simplices of type (1) with common composition ψ . Then ψ has no input boxes and no delay nodes, and its output box contains only external wasted wires as in Lemma 4.1.2. Each 1-wasted wire in each Ψ^i creates one external wasted wire in ψ . So the 1-wasted wire strings $\underline{\omega}^1$ and $\underline{\omega}^2$ have the same length. It follows that the simplices Ψ^1 and Ψ^2 are connected by a finite sequence of elementary equivalences corresponding to the elementary relation (3.3.29.1) and the vertical associativity axiom (2.1.4.4). \square

Lemma 5.2.9. *Any two equivalent stratified simplices of type (2) are either equal or are connected by a finite sequence of elementary equivalences (Def. 5.2.1).*

Proof. The proof consists of a series of reductions. Suppose Ψ^1 and Ψ^2 are distinct but equivalent stratified simplices of type (2) with common composition $\psi \in \text{WD}(\underline{X}^Y)$. Using elementary equivalences corresponding to

- the operad unity axioms (2.1.4.5) and (2.1.4.6),
- the elementary relations (3.3.8.1), (3.3.20.1), and (3.3.25.1) regarding colored units, and
- other elementary relations that move the generating wiring diagrams around the simplices,

we may assume that there are no unnecessary generating wiring diagrams in these stratified simplices. Here *unnecessary* refers to either a colored unit or generating wiring diagrams whose (iterated) operadic composition is a colored unit.

The name change τ^1 in Ψ^1 has output box Y and input box uniquely determined by ψ , and the same is true for the name change τ^2 in Ψ^2 . It follows that τ^1 is equal to τ^2 . So we may assume that there are no name changes in the two stratified simplices Ψ^i .

The string of delay nodes $\underline{\delta}^i$ in each simplex Ψ^i represents the set of delay nodes in ψ . Therefore, the two Ψ^i without their strings of delay nodes are also equivalent. Moreover, if these simplices without delay nodes are connected by a finite sequence of elementary equivalences, then so are the two Ψ^i themselves by the horizontal associativity axiom (2.1.4.3). So we may assume that the wiring diagram ψ and the

two simplices Ψ^i have no delay nodes. At this stage, each stratified simplex Ψ^i has the form

$$(\underline{\lambda}^i, \underline{\omega}^i, \underline{\sigma}_*^i, \underline{\sigma}^{*i}, \underline{\theta}^i).$$

The composition of the string of 2-cells $|\underline{\theta}^i|$ in each simplex Ψ^i has the same input boxes as ψ . So using finitely many elementary equivalences corresponding to the elementary relations (3.3.9.1) and (3.3.10.1), we may assume that the wiring diagram ψ has only one input box and that the simplices Ψ^i have no 2-cells. At this stage, each stratified simplex Ψ^i has the form

$$(\underline{\lambda}^i, \underline{\omega}^i, \underline{\sigma}_*^i, \underline{\sigma}^{*i}).$$

Observe that for each $i \in \{1, 2\}$, the string of 1-wasted wires $\underline{\omega}^i$ in the simplex Ψ^i corresponds to precisely the set $\psi_-^w \sqcup \psi_+^w$ of external and internal wasted wires in the wiring diagram ψ (Def. 2.2.9). Here an internal wasted wire in ψ is created by applying a 1-loop to a 1-wasted wire as in (3.2.2.1). Therefore, using finitely many elementary equivalences corresponding to the elementary relations (3.3.15.1) and (3.3.18.1), we may assume that the wiring diagram ψ and the two simplices Ψ^i have no 1-wasted wires. At this stage, each stratified simplex Ψ^i has the form

$$(\underline{\lambda}^i, \underline{\sigma}_*^i, \underline{\sigma}^{*i}).$$

Using finitely many elementary equivalences corresponding to the elementary relation (3.3.19.1), we may assume that each loop element in the wiring diagram ψ (Def. 4.2.1) corresponds to precisely one 1-loop λ in each simplex Ψ^i . At this stage, the 1-loops in each simplex Ψ^i are in bijection with the loop elements in ψ . Moreover, the two stratified subsimplices $(\underline{\sigma}_*^1, \underline{\sigma}^{*1}) \subseteq \Psi^1$ and $(\underline{\sigma}_*^2, \underline{\sigma}^{*2}) \subseteq \Psi^2$ are equivalent. Therefore, using finitely many elementary equivalences corresponding to the elementary relation (3.3.15.1), we may assume that the wiring diagram ψ has no loop elements and that the simplices Ψ^i have no 1-loops. So each stratified simplex Ψ^i now has the form

$$(\underline{\sigma}_*^i, \underline{\sigma}^{*i}).$$

The two stratified subsimplices $(\underline{\sigma}_*^i) \subseteq \Psi^i$ of in-splits for $i \in \{1, 2\}$ are also equivalent. They are connected by a finite sequence of elementary equivalences corresponding to the elementary relations (3.3.21.1) and (3.3.22.1). Likewise, the stratified subsimplices $(\underline{\sigma}^{*i}) \subseteq \Psi^i$ of out-splits for $i \in \{1, 2\}$ are connected by a finite sequence of elementary equivalences corresponding to the elementary relations (3.3.26.1) and (3.3.27.1). So the two simplices Ψ^i are also connected by a finite sequence of elementary equivalences. \square

We are now ready for the finite presentation theorem for wiring diagrams. It describes the wiring diagram operad WD (Theorem 2.3.8) in terms of finitely many generators and finitely many relations.

Theorem 5.2.10. *Consider the operad WD of wiring diagrams.*

- (1) *Every wiring diagram can be obtained from finitely many generating wiring diagrams (Def. 3.1.9) via iterated operadic compositions (Def. 2.1.4).*
- (2) *Any two equivalent simplices are either equal or are connected by a finite sequence of elementary equivalences (Def. 5.2.1).*

Proof. The first statement is a special case of Theorem 5.1.7. The second statement is a combination of Remark 5.1.6, Lemma 5.2.7 twice, Lemma 5.2.8, and Lemma 5.2.9. \square

5.3. Finite Presentation for Normal Wiring Diagrams

In this section, we establish a finite presentation theorem for the operad of wiring diagrams without delay nodes. Such wiring diagrams are used in [Spi15, Spi15b] to study mode-dependent networks and dynamical systems. Recall Def. 2.2.9, Def. 2.2.11, and Convention 2.2.12 regarding wiring diagrams.

Definition 5.3.1. Fix a class S .

- (1) A wiring diagram is said to be *normal* if its set of delay nodes is empty.
- (2) The collection of normal wiring diagrams is denoted by WD_\bullet . If we want to emphasize S , then we will write WD_\bullet^S .

Example 5.3.2. Among the 8 generating wiring diagrams (section 3.1):

- (1) A 1-delay node δ_a (Def. 3.1.2) is not normal.
- (2) The empty wiring diagram ϵ (Def. 3.1.1), a name change $\tau_{X,Y}$ (Def. 3.1.3), a 2-cell $\theta_{X,Y}$ (Def. 3.1.4), a 1-loop $\lambda_{X,x}$ (Def. 3.1.5), an in-split σ_{X,x_1,x_2} (Def. 3.1.6), an out-split σ^{Y,y_1,y_2} (Def. 3.1.7), and a 1-wasted wire $\omega_{Y,y}$ (Def. 3.1.8) are normal.

In particular, there is a proper inclusion $\text{WD}_\bullet \subsetneq \text{WD}$. Furthermore, the 1-internal wasted wire $\omega^{X,x}$ (Def. 3.2.1) is normal.

Example 5.3.3. All the wiring diagrams that appear in the 28 elementary relations (section 3.3) are normal.

Example 5.3.4. Among the wiring diagrams in Chapter 4:

- (1) φ (4.1.3.1) is not normal, unless $r = 0$.
- (2) ψ in (4.1.2.1), α (4.1.4.1), π_1 (4.2.5.1), π_2 (4.2.5.2), β_1 (4.3.3.1), β_2 (4.3.3.2), and β_3 (4.3.3.3) are normal.

Proposition 5.3.5. *With respect to*

- the equivariant structure in Def. 2.3.1,
- the colored units in Def. 2.3.2, and
- the \circ_i -compositions in Def. 2.3.3,

WD_\bullet is a Box_S -colored operad, called the operad of normal wiring diagrams.

Proof. We can reuse the proof of Theorem 2.3.8—that WD is a Box_S -colored operad—as long as we know that the relevant structure is well-defined in WD_\bullet .

The collection WD_\bullet is closed under the equivariant structure map (2.3.1.1). Furthermore, each colored unit $\mathbb{1}_Y$ (2.3.2.1) is in WD_\bullet .

Suppose both φ and ψ are normal wiring diagrams such that $\varphi \circ_i \psi \in \text{WD}$ is defined. Then $\varphi \circ_i \psi$ is also normal because

$$\text{DN}_{\varphi \circ_i \psi} = \text{DN}_\varphi \sqcup \text{DN}_\psi = \emptyset.$$

Therefore, Lemmas 2.3.5, 2.3.6, and 2.3.7 all apply to WD_\bullet to show that it is an operad. \square

Our next objective is to obtain a version of the finite presentation theorem for WD_\bullet . For this purpose, we will use the following definitions.

Definition 5.3.6. Consider the operad WD_\bullet of normal wiring diagrams.

- (1) A *normal generating wiring diagram* is a generating wiring diagram (Def. 3.1.9) except for 1-delay nodes δ_d (Def. 3.1.2).
- (2) A *normal simplex* is defined as in Def. 5.1.1 using normal generating wiring diagrams and WD_\bullet in place of WD .
- (3) A *normal stratified simplex* and a *normal stratified presentation* are defined as in Def. 5.1.5 with WD_\bullet in place of WD , except that a normal stratified simplex of type (2) has the form $(\tau, \underline{\lambda}, \underline{\omega}, \underline{\sigma}_*, \underline{\sigma}^*, \underline{\theta})$.
- (4) All of Def. 5.2.1 is repeated with normal generating wiring diagrams and WD_\bullet in place of WD .

The following result is the finite presentation theorem for normal wiring diagrams.

Theorem 5.3.7. Consider the operad WD_\bullet of normal wiring diagrams.

- (1) Every normal wiring diagram has a normal stratified presentation.
- (2) Every normal wiring diagram can be obtained from finitely many normal generating wiring diagrams via iterated operadic compositions (Def. 2.1.4).
- (3) Any two equivalent normal simplices are connected by a finite sequence of elementary equivalences (Def. 5.2.1).

Proof. For statement (1), we reuse the proof of Theorem 5.1.7 while assuming $r = 0$. Statement (2) is a special case of statement (1).

For statement (3) we reuse the proof of Theorem 5.2.10(2). In other words, we simply reuse the proofs of Lemma 5.2.7, Lemma 5.2.8, and Lemma 5.2.9 while assuming $r = 0$ throughout. The key observation is that, for normal simplices, elementary equivalences as in Def. 5.2.1 involve either:

- elementary relations (Def. 3.3.30), none of which involves delay nodes, or
- an operad associativity or unity axiom—(2.1.4.3), (2.1.4.4), (2.1.4.5), or (2.1.4.6)—for the normal generating wiring diagrams.

So in the WD_\bullet versions of these Lemmas, we simply ignore all the delay nodes in the original proofs. \square

5.4. Finite Presentation for Strict Wiring Diagrams

In this section, we establish a finite presentation theorem for the operad of strict wiring diagrams. Such wiring diagrams are used in [VSL14] to study open dynamical systems.

Definition 5.4.1. Fix a class S .

- (1) A wiring diagram (Def. 2.2.11) is said to be *strict* if
 - (i) it is normal (Def. 5.3.1) and
 - (ii) its supplier assignment is a bijection.
- (2) The collection of strict wiring diagrams is denoted by WD_0 . If we want to emphasize S , then we will write WD_0^S .

Remark 5.4.2. What we call a strict wiring diagram is simply called a wiring diagram in [VSL14] (Def. 3.5). In [VSL14] (Remark 2.7) S is a *set* of representatives of isomorphism classes of second-countable smooth manifolds. The non-instantaneity requirement (2.2.9.2) in this case is called the *no passing wires* requirement in [VSL14]. As noted in [VSL14] (Remark 3.6), strictness implies the non-existence of external wasted wires, internal wasted wires (Def. 2.2.9), and split wires, i.e., multiple (at least two) demand wires having the same supply wire. So strict wiring diagrams are much simpler than a general wiring diagram.

Example 5.4.3. Among the 8 generating wiring diagrams (section 3.1):

- (1) A 1-delay node δ_d (Def. 3.1.2) is not normal (Def. 5.3.1), hence also not strict.
- (2) The empty wiring diagram ϵ (Def. 3.1.1), a name change $\tau_{X,Y}$ (Def. 3.1.3), a 2-cell $\theta_{X,Y}$ (Def. 3.1.4), and a 1-loop $\lambda_{X,x}$ (Def. 3.1.5) are strict.

- (3) An in-split σ_{X,x_1,x_2} (Def. 3.1.6), an out-split σ^{Y,y_1,y_2} (Def. 3.1.7), and a 1-wasted wire $\omega_{Y,y}$ (Def. 3.1.8) are normal but not strict.

In particular, there are proper inclusions $\text{WD}_0 \subsetneq \text{WD}_\bullet \subsetneq \text{WD}$. Furthermore, the 1-internal wasted wire $\omega^{X,x}$ (Def. 3.2.1) is normal but not strict.

Example 5.4.4. Among the wiring diagrams that appear in the 28 elementary relations (section 3.3):

- (1) (3.3.2.1), (3.3.3.1), (3.3.4.1), (3.3.8.1), (3.3.9.1), (3.3.10.1), (3.3.11.1), (3.3.15.1), (3.3.20.1), and (3.3.25.1) are strict wiring diagrams.
- (2) The other 18 are normal but not strict.
- (3) Only (3.3.2.1), (3.3.3.1), (3.3.4.1), (3.3.8.1), (3.3.9.1), (3.3.10.1), (3.3.11.1), and (3.3.15.1) involve only strict wiring diagrams on both sides. Indeed, both (3.3.20.1) and (3.3.25.1) involve a 1-wasted wire, which is not strict.

Example 5.4.5. Among the wiring diagrams in Chapter 4:

- (1) ψ in (4.1.2.1) is normal but not strict.
- (2) α (4.1.4.1), π_2 (4.2.5.2), β_1 (4.3.3.1), β_2 (4.3.3.2), and β_3 (4.3.3.3) are normal but not strict in general.
- (3) π_1 (4.2.5.1) is a strict wiring diagram by Lemma 4.2.7.

Proposition 5.4.6. *With respect to*

- *the equivariant structure in Def. 2.3.1,*
- *the colored units in Def. 2.3.2, and*
- *the \circ_i -compositions in Def. 2.3.3,*

WD_0 is a Box_S -colored operad, called the operad of strict wiring diagrams.

Proof. The argument is essentially identical to the proof of Prop. 5.3.5 with a minor modification. Suppose both φ and ψ are strict wiring diagrams such that $\varphi \circ_i \psi \in \text{WD}$ is defined. Then $\varphi \circ_i \psi$ is also strict. Indeed, we already know that it is normal. Next, one can check directly from the definition of the supplier assignment $s_{\varphi \circ_i \psi}$ (2.3.3.1) that it is a bijection because, in all cases, it is defined as a composition of the bijections s_φ and s_ψ . Therefore, Lemmas 2.3.5, 2.3.6, and 2.3.7 all apply to WD_0 to show that it is an operad. \square

Our next objective is to obtain a version of the finite presentation theorem for WD_0 . For this purpose, we will use the following definitions.

Definition 5.4.7. Consider the operad WD_0 of strict wiring diagrams.

- (1) A *strict generating wiring diagram* means the empty wiring diagram ϵ (Def. 3.1.1), a name change $\tau_{X,Y}$ (Def. 3.1.3), a 2-cell $\theta_{X,Y}$ (Def. 3.1.4), or a 1-loop $\lambda_{X,x}$ (Def. 3.1.5).
- (2) A *strict simplex* is defined as in Def. 5.1.1 using strict generating wiring diagrams and WD_0 in place of WD .
- (3) A *strict stratified simplex* is a stratified simplex (Def. 5.1.5) of the form (ϵ) or $(\tau, \underline{\lambda}, \underline{\theta})$.
- (4) If Ψ is a strict stratified simplex, then we call it a *strict stratified presentation* of the strict wiring diagram $|\Psi|$.
- (5) A *strict elementary relation* means one of the 8 elementary relations that involve only strict wiring diagrams on both sides, namely, (3.3.2.1), (3.3.3.1), (3.3.4.1), (3.3.8.1), (3.3.9.1), (3.3.10.1), (3.3.11.1), and (3.3.15.1). See Example 5.4.4.
- (6) All of Def. 5.2.1 is repeated with WD_0 in place of WD using strict generating wiring diagrams, strict simplices, and strict elementary relations. The resulting notions are called *strict elementary equivalences*, and so forth.

The following result is the finite presentation theorem for strict wiring diagrams.

Theorem 5.4.8. *Consider the operad WD_0 of strict wiring diagrams.*

- (1) *Every strict wiring diagram has a strict stratified presentation.*
- (2) *Every strict wiring diagram can be obtained from finitely many strict generating wiring diagrams via iterated operadic compositions (Def. 2.1.4).*
- (3) *Any two equivalent strict simplices are connected by a finite sequence of strict elementary equivalences.*

Proof. As in the proof of Theorem 5.3.7, for statement (1), we reuse the proof of Theorem 5.1.7 while assuming the wiring diagram ψ is strict. In this case, ψ is either the empty wiring diagram ϵ or has a decomposition (using (4.1.5.1) and (4.2.6.1))

$$\psi = \pi_1 \circ \pi_2 \circ \varphi$$

in which π_2 (4.2.5.2) is a name change. The desired strict stratified presentation follows from Convention 4.2.4 and the facts that:

- π_1 is either a colored unit or has a stratified presentation $(\underline{\lambda})$ by Lemma 4.2.7;
- φ is either a colored unit or has a stratified presentation $(\underline{\theta})$ by Lemma 4.1.7.

Statement (2) is a special case of statement (1).

For statement (3) we use the strict versions of the proofs of Lemma 5.2.7, Lemma 5.2.8, and Lemma 5.2.9. The key observation is that, in this case, only strict generating wiring diagrams and strict elementary equivalences are used in these proofs. \square

Finite Presentation for Algebras over Wiring Diagrams

The main purpose of this chapter is to provide finite presentations for algebras over the operads WD (Theorem 2.3.8), WD_\bullet (Prop. 5.3.5), and WD_0 (Prop. 5.4.6). The advantage of such a finite presentation is that sometimes the general structure map of an operad algebra can be a bit difficult to write down and understand. On the other hand, our generating structure maps and generating axioms are all fairly easy to write down and understand, as we will illustrate with examples in Sections 6.3, 6.5, and 6.7.

In Section 6.1 we recall the basics of algebras over an operad.

In Section 6.2 we first define a WD -algebra in terms of 8 generating structure maps and 28 generating axioms corresponding to the generating wiring diagrams (Def. 3.1.9) and the elementary relations (Def. 3.3.30), respectively. Then we observe that this finite presentation for a WD -algebra is in fact equivalent to the general definition of a WD -algebra (Theorem 6.2.2). This is an application of the finite presentation theorem for the operad WD (Theorem 5.2.10).

In Section 6.3 we provide a finite presentation for the WD -algebra called the propagator algebra. In its original form, the propagator algebra was the main example in [RS13].

In Section 6.4 we observe that algebras over the operad WD_\bullet of normal wiring diagrams have a similar finite presentation with 7 generating structure maps and

28 generating axioms. In Section 6.5 we provide a finite presentation for the WD_\bullet -algebra called the algebra of discrete systems. In its original form, this algebra was one of the main examples in [Spi15b].

In Section 6.6 we observe that algebras over the operad WD_0 of strict wiring diagrams admit a finite presentation with 4 generating structure maps and 8 generating axioms. In Section 6.7 we provide a finite presentation for the WD_0 -algebra called the algebra of open dynamical systems. In its original form, this algebra was one of the main examples in [VSL14].

6.1. Operad Algebras

Let us first recall the definition of an algebra over an operad. The following definition can be found in [Yau16] (Def. 13.2.3). In its original 1-colored topological form, it was first given in [May72]. Fix a class S as before.

Definition 6.1.1. Suppose $(O, \mathbb{1}, \gamma)$ is an S -colored operad as in Def. 2.1.2. An O -algebra is a pair (A, μ) consisting of the following data.

- (1) For each $c \in S$, A is equipped with a class A_c called the c -colored entry of A .
- (2) For each $d \in S$, $\underline{c} = (c_1, \dots, c_n) \in \text{Prof}(S)$, and $\zeta \in O(\underline{c}, d)$, A is equipped with a structure map

$$A_{\underline{c}} \stackrel{\text{def}}{=} \prod_{i=1}^n A_{c_i} \xrightarrow{\mu_\zeta} A_d \quad (6.1.1.1)$$

in which an empty product, for the case $n = 0$, means the one-point set $\{*\}$.

This data is required to satisfy the following associativity, unity, and equivariance axioms.

Associativity: Suppose $(\underline{c}, d) \in \text{Prof}(S) \times S$ is as above with $n \geq 1$, $\zeta_0 \in O(\underline{c}, d)$, $\zeta_i \in O(\underline{b}_i, c_i)$ for each $1 \leq i \leq n$ with $\underline{b}_i \in \text{Prof}(S)$, and $\underline{b} = (\underline{b}_1, \dots, \underline{b}_n)$ as in (2.1.2.2). Write $\zeta = \gamma(\zeta_0; \zeta_1, \dots, \zeta_n) \in O(\underline{b}, d)$. Then the diagram

$$\begin{array}{ccc} A_{\underline{b}} & \xrightarrow{\mu_\zeta} & A_d \\ \downarrow = & & \uparrow \mu_{\zeta_0} \\ A_{\underline{b}_1} \times \dots \times A_{\underline{b}_n} & \xrightarrow{\prod \mu_{\zeta_i}} & A_{c_1} \times \dots \times A_{c_n} = A_{\underline{c}} \end{array} \quad (6.1.1.2)$$

is commutative.

Unity: For each $c \in S$, the structure map

$$A_c \xrightarrow{\mu_{\mathbb{1}_c}} A_c \quad (6.1.1.3)$$

is the identity map, where $\mathbb{1}_c \in O(c, c)$ is the c -colored unit of O .

Equivariance: Suppose $\zeta \in O(\underline{c})^d$ as in (6.1.1.1), $\sigma \in \Sigma_n$, and $\zeta^\sigma \in O(\underline{c}^\sigma)^d$ is the image of ζ under the right action (2.1.2.1). Then the diagram

$$\begin{array}{ccc} A_{\underline{c}} & \xrightarrow{\sigma^{-1}} & A_{\underline{c}^\sigma} \\ \mu_\zeta \downarrow & & \downarrow \mu_{\zeta^\sigma} \\ A_d & \xrightarrow{=} & A_d \end{array} \quad (6.1.1.4)$$

is commutative. Here the top σ^{-1} permutes the factors of $A_{\underline{c}}$ from the left, and $\underline{c}^\sigma = (c_{\sigma(1)}, \dots, c_{\sigma(n)})$.

To simplify the notations, we will sometimes denote an O-algebra by just A and denote the structure map μ_ζ by ζ .

Just as operads can be equivalently expressed in terms of the \circ_i -compositions (Prop. 2.1.6), so can operad algebras.

Definition 6.1.2. Suppose $(O, \mathbb{1}, \circ)$ is an S -colored operad as in Def. 2.1.4. An O-algebra (A, μ) is defined exactly as in Def. 6.1.1 except that the associativity axiom (6.1.1.2) is replaced by the following axiom.

Associativity: Suppose:

- $d \in S$, $\underline{c} = (c_1, \dots, c_n) \in \text{Prof}(S)$ with $n \geq 1$, and $1 \leq i \leq n$;
- $\underline{b} \in \text{Prof}(S)$ and $\underline{c} \circ_i \underline{b}$ as in (2.1.4.2);
- $\zeta \in O(\underline{c})^d$, $\xi \in O(\underline{b})^{c_i}$, and $\zeta \circ_i \xi \in O(\underline{c} \circ_i \underline{b})^d$.

Then the diagram

$$\begin{array}{ccc} A_{\underline{c} \circ_i \underline{b}} & \xrightarrow{\mu_{\zeta \circ_i \xi}} & A_d \\ \downarrow = & & \uparrow \mu_\zeta \\ A_{(c_1, \dots, c_{i-1})} \times A_{\underline{b}} \times A_{(c_{i+1}, \dots, c_n)} & \xrightarrow{(\text{Id}, \mu_\xi, \text{Id})} & A_{(c_1, \dots, c_{i-1})} \times A_{c_i} \times A_{(c_{i+1}, \dots, c_n)} = A_{\underline{c}} \end{array} \quad (6.1.2.1)$$

is commutative.

Notation 6.1.3. To simplify the notations, we will sometimes denote the structure map μ_ζ by ζ . We will also write the composition in the diagram (6.1.2.1) as $\mu_\zeta \circ_i \mu_\xi$, called the \circ_i -composition of μ_ζ and μ_ξ . So this associativity axiom states that

$$\mu_{\zeta \circ_i \xi} = \mu_\zeta \circ_i \mu_\xi.$$

In other words, the structure map of the \circ_i -composition $\zeta \circ_i \xi$ is the \circ_i -composition of the structure maps corresponding to ζ and ξ .

Using the associativity and the unity axioms in Def. 2.1.2 and Def. 2.1.4, it is not hard to check that Def. 6.1.1 and Def. 6.1.2 are in fact equivalent. A proof of this equivalence can be found in [Yau16] (Prop. 16.7.8 and Exercises 10 and 11 in Chapter 16).

Remark 6.1.4. In Def. 6.1.1 and Def. 6.1.2, each entry of an operad algebra has no structure beyond being a class. We could have just as easily defined operad algebras in a symmetric monoidal category, which is in fact the setting in [Yau16] (Def. 13.2.3). One simply replaces the product with the symmetric monoidal product and the one-point set with the monoidal unit. However, to keep the presentation simple, we chose to define operad algebras whose entries are just classes. This is sufficient for the main examples in Sections 6.3, 6.5, and 6.7.

6.2. Algebras over the Operad of Wiring Diagrams

The purpose of this section is to provide a finite presentation for WD-algebras. We begin by defining a WD-algebra in terms of the generating wiring diagrams and the elementary relations. Immediately afterwards we will establish its equivalence with Def. 6.1.2 when $O = \text{WD}$. Recall that WD is a Box_S -colored operad (Theorem 2.3.8).

Definition 6.2.1. A WD-algebra A consists of the following data.

- (1) For each $X \in \text{Box}_S$, A is equipped with a class A_X called the X -colored entry of A .
- (2) It is equipped with the following 8 generating structure maps corresponding to the generating wiring diagrams (Def. 3.1.9).
 - (i) Corresponding to the empty wiring diagram $\epsilon \in \text{WD}(\emptyset)$ (Def. 3.1.1), it has a structure map

$$* \xrightarrow{\epsilon} A_{\emptyset}, \quad (6.2.1.1)$$

i.e., a chosen element in A_{\emptyset} .

- (ii) Corresponding to each 1-delay node $\delta_d \in \text{WD}^d$ (Def. 3.1.2), it has a structure map

$$* \xrightarrow{\delta_d} A_d, \quad (6.2.1.2)$$

i.e., a chosen element in A_d .

- (iii) Corresponding to each name change $\tau_{X,Y} \in \text{WD}(\overset{Y}{X})$ (Def. 3.1.3), it has a structure map

$$A_X \xrightarrow{\tau_{X,Y}} A_Y \quad (6.2.1.3)$$

that is, furthermore, the identity map if $\tau_{X,X}$ is the colored unit $\mathbb{1}_X$ (2.3.2.1).

- (iv) Corresponding to each 2-cell $\theta_{X,Y} \in \text{WD}(\overset{X \cup Y}{X,Y})$ (Def. 3.1.4), it has a structure map

$$A_X \times A_Y \xrightarrow{\theta_{X,Y}} A_{X \cup Y}. \quad (6.2.1.4)$$

- (v) Corresponding to each 1-loop $\lambda_{X,x} \in \text{WD}(\frac{X \setminus x}{X})$ (Def. 3.1.5), it has a structure map

$$A_X \xrightarrow{\lambda_{X,x}} A_{X \setminus x} . \quad (6.2.1.5)$$

- (vi) Corresponding to each in-split $\sigma_{X,x_1,x_2} \in \text{WD}(\frac{Y}{X})$ (Def. 3.1.6), it has a structure map

$$A_X \xrightarrow{\sigma_{X,x_1,x_2}} A_Y . \quad (6.2.1.6)$$

- (vii) Corresponding to each out-split $\sigma^{Y,y_1,y_2} \in \text{WD}(\frac{Y}{X})$ (Def. 3.1.7), it has a structure map

$$A_X \xrightarrow{\sigma^{Y,y_1,y_2}} A_Y . \quad (6.2.1.7)$$

- (viii) Corresponding to each 1-wasted wire $\omega_{Y,y} \in \text{WD}(\frac{Y}{X})$ (Def. 3.1.8), it has a structure map

$$A_X \xrightarrow{\omega_{Y,y}} A_Y . \quad (6.2.1.8)$$

The following 28 diagrams, called the *generating axioms*, which correspond to the elementary relations (Def. 3.3.30), are required to be commutative.

- (1) In the setting of (3.3.2.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\tau_{X,Y}} & A_Y \\ & \searrow \tau_{X,Z} & \downarrow \tau_{Y,Z} \\ & & A_Z \end{array} \quad (6.2.1.9)$$

is commutative.

- (2) In the setting of (3.3.3.1), the diagram

$$\begin{array}{ccc} A_X \times A_Y & \xrightarrow{\theta_{X,Y}} & A_{X \sqcup Y} \\ (\tau_{X,X'}, \tau_{Y,Y'}) \downarrow & & \downarrow \tau_{X \sqcup Y, X' \sqcup Y'} \\ A_{X'} \times A_{Y'} & \xrightarrow{\theta_{X',Y'}} & A_{X' \sqcup Y'} \end{array} \quad (6.2.1.10)$$

is commutative.

- (3) In the setting of (3.3.4.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\lambda_{X,x}} & A_{X \setminus x} \\ \tau_{X,Y} \downarrow & & \downarrow \tau_{X \setminus x, Y \setminus y} \\ A_Y & \xrightarrow{\lambda_{Y,y}} & A_{Y \setminus y} \end{array} \quad (6.2.1.11)$$

is commutative.

(4) In the setting of (3.3.5.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\sigma_{X,x_1,x_2}} & A_{X'} \\ \tau_{X,Y} \downarrow & & \downarrow \tau_{X',Y'} \\ A_Y & \xrightarrow{\sigma_{Y,y_1,y_2}} & A_{Y'} \end{array}$$

is commutative.

(5) In the setting of (3.3.6.1), the diagram

$$\begin{array}{ccc} A_{X'} & \xrightarrow{\sigma^{X,x_1,x_2}} & A_X \\ \tau_{X',Y'} \downarrow & & \downarrow \tau_{X,Y} \\ A_{Y'} & \xrightarrow{\sigma^{Y,y_1,y_2}} & A_Y \end{array}$$

is commutative.

(6) In the setting of (3.3.7.1), the diagram

$$\begin{array}{ccc} A_{X'} & \xrightarrow{\omega_{X,x}} & A_X \\ \tau_{X',Y'} \downarrow & & \downarrow \tau_{X,Y} \\ A_{Y'} & \xrightarrow{\omega_{Y,y}} & A_Y \end{array}$$

is commutative.

(7) In the setting of (3.3.8.1), the diagram

$$\begin{array}{ccc} A_X \times * & \xrightarrow{(\text{Id}, \epsilon)} & A_X \times A_\emptyset \\ \downarrow = & & \downarrow \theta_{X,\emptyset} \\ A_X & \xrightarrow{=} & A_{X \sqcup \emptyset} \end{array} \quad (6.2.1.12)$$

is commutative.

(8) In the setting of (3.3.9.1), the diagram

$$\begin{array}{ccc} A_X \times A_Y \times A_Z & \xrightarrow{(\text{Id}, \theta_{Y,Z})} & A_X \times A_{Y \sqcup Z} \\ (\theta_{X,Y}, \text{Id}) \downarrow & & \downarrow \theta_{X,Y \sqcup Z} \\ A_{X \sqcup Y} \times A_Z & \xrightarrow{\theta_{X \sqcup Y, Z}} & A_{X \sqcup Y \sqcup Z} \end{array} \quad (6.2.1.13)$$

is commutative.

(9) In the setting of (3.3.10.1), the diagram

$$\begin{array}{ccc}
 A_Y \times A_X & \xrightarrow{\text{permute}} & A_X \times A_Y \\
 \theta_{Y,X} \downarrow & & \downarrow \theta_{X,Y} \\
 A_{Y \sqcup X} & \xrightarrow{=} & A_{X \sqcup Y}
 \end{array} \tag{6.2.1.14}$$

is commutative.

(10) In the setting of (3.3.11.1), the diagram

$$\begin{array}{ccc}
 A_X \times A_Y & \xrightarrow{\theta_{X,Y}} & A_{X \sqcup Y} \\
 (\lambda_{X,x}, \text{Id}) \downarrow & & \downarrow \lambda_{X \sqcup Y, x} \\
 A_{X \setminus x} \times A_Y & \xrightarrow{\theta_{X \setminus x, Y}} & A_{(X \sqcup Y) \setminus \{x\}}
 \end{array} \tag{6.2.1.15}$$

is commutative.

(11) In the setting of (3.3.12.1), the diagram

$$\begin{array}{ccc}
 A_X \times A_Y & \xrightarrow{\theta_{X,Y}} & A_{X \sqcup Y} \\
 (\sigma_{X,x_1,x_2}, \text{Id}) \downarrow & & \downarrow \sigma_{X \sqcup Y, x_1, x_2} \\
 A_{X'} \times A_Y & \xrightarrow{\theta_{X',Y}} & A_{X' \sqcup Y}
 \end{array}$$

is commutative.

(12) In the setting of (3.3.13.1), the diagram

$$\begin{array}{ccc}
 A_{X'} \times A_Y & \xrightarrow{\theta_{X',Y}} & A_{X' \sqcup Y} \\
 (\sigma^{X,x_1,x_2}, \text{Id}) \downarrow & & \downarrow \sigma^{X \sqcup Y, x_1, x_2} \\
 A_X \times A_Y & \xrightarrow{\theta_{X,Y}} & A_{X \sqcup Y}
 \end{array}$$

is commutative.

(13) In the setting of (3.3.14.1), the diagram

$$\begin{array}{ccc}
 A_{X'} \times A_Y & \xrightarrow{\theta_{X',Y}} & A_{X' \sqcup Y} \\
 (\omega_{X,x_0}, \text{Id}) \downarrow & & \downarrow \omega_{X \sqcup Y, x_0} \\
 A_X \times A_Y & \xrightarrow{\theta_{X,Y}} & A_{X \sqcup Y}
 \end{array}$$

is commutative.

(14) In the setting of (3.3.15.1), the diagram

$$\begin{array}{ccc}
 A_X & \xrightarrow{\lambda_{X,x^2}} & A_{X \setminus x^2} \\
 \lambda_{X,x^1} \downarrow & & \downarrow \lambda_{X \setminus x^2, x^1} \\
 A_{X \setminus x^1} & \xrightarrow{\lambda_{X \setminus x^1, x^2}} & A_{X \setminus x}
 \end{array} \tag{6.2.1.16}$$

is commutative.

(15) In the setting of (3.3.16.1), the diagram

$$\begin{array}{ccc}
 A_X & \xrightarrow{\lambda_{X,x}} & A_{X \setminus x} \\
 \sigma_{X,x_1,x_2} \downarrow & & \downarrow \sigma_{X \setminus x, x_1, x_2} \\
 A_{X'} & \xrightarrow{\lambda_{X',x}} & A_{X' \setminus x}
 \end{array}$$

is commutative.

(16) In the setting of (3.3.17.1), the diagram

$$\begin{array}{ccc}
 A_{X'} & \xrightarrow{\sigma^{X,x_1,x_2}} & A_X \\
 \lambda_{X',x} \downarrow & & \downarrow \lambda_{X,x} \\
 A_{X' \setminus x} & \xrightarrow{\sigma^{X \setminus x, x_1, x_2}} & A_{X \setminus x}
 \end{array}$$

is commutative.

(17) In the setting of (3.3.18.1), the diagram

$$\begin{array}{ccc}
 A_{X'} & \xrightarrow{\omega_{X,x_0}} & A_X \\
 \lambda_{X',x} \downarrow & & \downarrow \lambda_{X,x} \\
 A_{X' \setminus x} & \xrightarrow{\omega_{X \setminus x, x_0}} & A_{X \setminus x}
 \end{array}$$

is commutative.

(18) In the setting of (3.3.19.1), the diagram

$$\begin{array}{ccccc}
 A_X & \xrightarrow{\sigma^{Y,x^1,x^2}} & A_Y & \xrightarrow{\lambda_{Y,x(1)}} & A_{Y \setminus x(1)} \\
 \sigma_{X,x_1,x_2} \downarrow & & & & \downarrow \lambda_{Y \setminus x(1), x(2)} \\
 A_{X'} & \xrightarrow{\lambda_{X',x}} & & & A_{X^*}
 \end{array} \tag{6.2.1.17}$$

is commutative.

(19) In the setting of (3.3.20.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{=} & A_X \\ \sigma^{Y,x_1,x_2} \downarrow & & \uparrow \lambda_{Z,x} \\ A_Y & \xrightarrow{\omega_{Z,x_1}} & A_Z \end{array}$$

is commutative.

(20) In the setting of (3.3.21.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\sigma_{X,x_2,x_3}} & A_{X_{23}} \\ \sigma_{X,x_1,x_2} \downarrow & & \downarrow \sigma_{X_{23},x_1,x_{23}} \\ A_{X_{12}} & \xrightarrow{\sigma_{X_{12},x_{12},x_3}} & A_Y \end{array}$$

is commutative.

(21) In the setting of (3.3.22.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\sigma_{X,x_3,x_4}} & A_{X_{34}} \\ \sigma_{X,x_1,x_2} \downarrow & & \downarrow \sigma_{X_{34},x_1,x_2} \\ A_{X_{12}} & \xrightarrow{\sigma_{X_{12},x_3,x_4}} & A_Y \end{array}$$

is commutative.

(22) In the setting of (3.3.23.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\sigma_{Z,z^1,z^2}} & A_Z \\ \sigma_{X,z_1,z_2} \downarrow & & \downarrow \sigma_{Z,z_1,z_2} \\ A_W & \xrightarrow{\sigma_{Y,z^1,z^2}} & A_Y \end{array}$$

is commutative.

(23) In the setting of (3.3.24.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\omega_{Z,z}} & A_Z \\ \sigma_{X,z_1,z_2} \downarrow & & \downarrow \sigma_{Z,z_1,z_2} \\ A_W & \xrightarrow{\omega_{Y,z}} & A_Y \end{array}$$

is commutative.

(24) In the setting of (3.3.25.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\omega_{Y,y}} & A_Y \\ & \searrow = & \downarrow \sigma_{Y,x,y} \\ & & A_X \end{array}$$

is commutative.

(25) In the setting of (3.3.26.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\sigma^{Y^{23},y^1,y^{23}}} & A_{Y^{23}} \\ \sigma^{Y^{12},y^{12},y^3} \downarrow & & \downarrow \sigma^{Y,y^2,y^3} \\ A_{Y^{12}} & \xrightarrow{\sigma^{Y,y^1,y^2}} & A_Y \end{array}$$

is commutative.

(26) In the setting of (3.3.27.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\sigma^{Y^{34},y^1,y^2}} & A_{Y^{34}} \\ \sigma^{Y^{12},y^3,y^4} \downarrow & & \downarrow \sigma^{Y,y^3,y^4} \\ A_{Y^{12}} & \xrightarrow{\sigma^{Y,y^1,y^2}} & A_Y \end{array}$$

is commutative.

(27) In the setting of (3.3.28.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\omega_{W,y}} & A_W \\ \sigma^{Z,y^1,y^2} \downarrow & & \downarrow \sigma^{Y,y^1,y^2} \\ A_Z & \xrightarrow{\omega_{Y,y}} & A_Y \end{array}$$

is commutative.

(28) In the setting of (3.3.29.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\omega_{Y_2,y_1}} & A_{Y_2} \\ \omega_{Y_1,y_2} \downarrow & & \downarrow \omega_{Y,y_2} \\ A_{Y_1} & \xrightarrow{\omega_{Y,y_1}} & A_Y \end{array}$$

is commutative.

This finishes the definition of a WD-algebra.

At this moment we have two definitions of a WD-algebra.

- On the one hand, in Def. 6.1.2 with $O = \text{WD}$, a WD-algebra has a structure map μ_ζ (6.1.1.1) for each wiring diagram ζ . This structure map satisfies the associativity axiom (6.1.2.1) for a general operadic composition in WD, together with the unity and the equivariance axioms in Def. 6.1.1.
- On the other hand, in Def. 6.2.1 a WD-algebra has 8 generating structure maps and satisfies 28 generating axioms.

We now observe that these two definitions are equivalent, so WD-algebras indeed have a finite presentation as in Def. 6.2.1.

Theorem 6.2.2. *For the operad of wiring diagrams WD (Theorem 2.3.8), Def. 6.1.2 with $O = \text{WD}$ and Def. 6.2.1 of a WD-algebra are equivalent.*

Proof. First suppose (A, μ) is a WD-algebra in the sense of Def. 6.1.2. To see that it is also a WD-algebra in the sense of Def. 6.2.1, first note that the structure map μ_ζ (6.1.1.1) gives the eight generating structure maps (6.2.1.1)–(6.2.1.8). Moreover, the generating structure map μ_{1_x} (6.2.1.3) is the identity map by the unity axiom (6.1.1.3).

The generating axiom (6.2.1.14) is a special case of the equivariance diagram (6.1.1.4), so it is commutative. Each of the other 27 generating axioms corresponds to an elementary relation that describes two different ways to construct the same wiring diagram as an iterated operadic composition of generating wiring diagrams. Each such generating axiom asserts that the two corresponding compositions of generating structure maps—defined using the composition in the diagram (6.1.2.1)—are equal. The associativity axiom (6.1.2.1) of (A, μ) applied twice guarantees that two such compositions are indeed equal.

Conversely, suppose A is a WD-algebra in the sense of Def. 6.2.1, so it has eight generating structure maps that satisfy 28 generating axioms. We must show that it is a WD-algebra in the sense of Def. 6.1.2 For a wiring diagram $\psi \in \text{WD}$ with a presentation Ψ (Def. 5.1.1), we define its structure map μ_ψ (6.1.1.1) inductively as follows.

- (1) If Ψ is a 1-simplex, then $\Psi = (\psi)$, and ψ is a generating wiring diagram by the definition of a simplex. In this case, we define μ_ψ as the corresponding generating structure map (6.2.1.1)–(6.2.1.8) of A .
- (2) Inductively, suppose Ψ is an n -simplex for some $n \geq 2$, so $\Psi = (\Phi, i, \Theta)$ for some $i \geq 1$, p -simplex Φ , and q -simplex Θ with $p + q = n$. Since $1 \leq p, q < n$, by the induction hypothesis, the structure maps $\mu_{|\Phi|}$ and $\mu_{|\Theta|}$ are already defined. Then we define the structure map

$$\mu_\psi = \mu_{|\Phi|} \circ_i \mu_{|\Theta|} \tag{6.2.2.1}$$

as in Notation 6.1.3.

By Theorem 5.1.7 every wiring diagram has a stratified presentation, hence a presentation. To see that the structure map μ_ψ as above is well-defined, we need to show that the map μ_ψ is independent of the choice of a presentation Ψ . Any two presentations of a wiring diagram are by definition equivalent simplices. By Theorem 5.2.10(2) (= the relations part of the finite presentation theorem for WD), any two equivalent simplices are either equal or are connected by a finite sequence of elementary equivalences. Therefore, it suffices to show that every elementary equivalence in WD yields a commutative diagram involving the generating structure maps of A , where \circ_i is interpreted as in Notation 6.1.3. Recall from Def. 5.2.1 that an elementary equivalence comes from either an elementary relation or an operad associativity/unity axiom for the generating wiring diagrams.

It follows from a direct inspection that the operad associativity and unity axioms—(2.1.4.3), (2.1.4.4), (2.1.4.5), and (2.1.4.6)—for the generating wiring diagrams yield commutative diagrams involving the generating structure maps of A . In fact, the diagrams involving the horizontal and the vertical associativity axioms (2.1.4.3) and (2.1.4.4) are commutative because composition of functions is associative. The diagrams for the two unity axioms (2.1.4.5) and (2.1.4.6) are commutative because the generating structure map for a colored unit (6.2.1.3) is required to be the identity map.

By definition each of the 28 generating axioms of A corresponds to an elementary relation (Def. 3.3.30) and is a commutative diagram. Therefore, the structure map μ_ψ for each wiring diagram ψ is well-defined.

It remains to check that the structure map μ satisfies the required unity, equivariance, and associativity axioms. The unity axiom (6.1.1.3) holds because it is part of the assumption on the generating structure map corresponding to a name change (6.2.1.3).

The associativity axiom (6.1.2.1) holds because the structure map μ_ψ is defined above (6.2.2.1) by requiring that the diagram (6.1.2.1) be commutative.

For the equivariance axiom (6.1.1.4), first note that it is enough to check it when the wiring diagram in question is an iterated operadic composition of 2-cells. This is because 2-cells are the only binary generating wiring diagrams (Remark 3.1.10). All other generating wiring diagrams are either 0-ary or unary, for which equivariance is trivial.

So now suppose ζ in the equivariance axiom (6.1.1.4) is an iterated operadic composition of 2-cells. If ζ is a 2-cell and the permutation σ is the transposition $(1\ 2) \in \Sigma_2$, then the equivariance axiom (6.1.1.4) is true by the generating axiom (6.2.1.14). The general case now follows from this special case using:

- the generating axiom (6.2.1.13) corresponding to the associativity property of 2-cells (3.3.9.1);

- the operad associativity axioms (2.1.4.3) and (2.1.4.4) when applied to 2-cells;
- the fact that the transpositions $(i, i + 1)$ for $1 \leq i \leq n - 1$ generate the symmetric group Σ_n .

So (A, μ) is a WD-algebra in the sense of Def. 6.1.2. \square

6.3. Finite Presentation for the Propagator Algebra

As an illustration of Theorem 6.2.2, in this section we provide a finite presentation for the WD-algebra called the *propagator algebra* that was first introduced in [RS13] (section 3). As explained in [RS13] (section 3.4), the propagator algebra can be used, for example, to provide an iterative description of the Fibonacci sequence. In contrast to the original definition in [RS13], we will define the propagator algebra using finitely many generating structure maps and axioms—8 generating structure maps and 28 generating axioms to be exact. Since our generating structure maps are rather simple, our description of the propagator algebra is less involved than the original definition and verification in [RS13]. The equivalence between the two definitions of the propagator algebra is explained in Remark 6.3.13.

Assumption 6.3.1. Throughout this section, S denotes the class of pointed sets, with respect to which S -boxes (Def. 2.2.4) and the operad WD are defined (Theorem 2.3.8). In a pointed set, the base point is denoted by $*$.

Recall the concept and notations regarding profiles from Def. 2.1.1. Let us first recall a few definitions from [RS13] (section 3).

Definition 6.3.2. Suppose T and U are pointed sets and $k \geq 0$.

- (1) Define the *truncation* $\partial_T : \text{Prof}^{\geq 1}(T) \longrightarrow \text{Prof}(T)$ as the function

$$\partial_T(t_1, \dots, t_n) = (t_1, \dots, t_{n-1}). \quad (6.3.2.1)$$

We will often omit the subscript and just write ∂ .

- (2) A *k-historical propagator* from T to U is a function $f : \text{Prof}(T) \longrightarrow \text{Prof}(U)$ such that:

- (i) $|f(\underline{t})| = |\underline{t}| + k$ for all $\underline{t} \in \text{Prof}(T)$;
- (ii) If $\underline{t} \in \text{Prof}(T)$ has length $|\underline{t}| \geq 1$, then

$$\partial_U f(\underline{t}) = f(\partial_T \underline{t}). \quad (6.3.2.2)$$

The condition (6.3.2.2) is called *historicity*.

- (3) The set of *k-historical propagators* from T to U is denoted by $\text{Hist}^k(T, U)$.
- (4) A *historical propagator* from T to U is an *m-historical propagator* from T to U for some $m \geq 0$.

Before we can define the propagator algebra, we first need to define its entries.

Definition 6.3.3. Suppose $X = (X^{\text{in}}, X^{\text{out}}) \in \text{Box}_S$ (Def. 2.2.4).

(1) Define the pointed sets

$$X_v^{\text{in}} = \prod_{x \in X^{\text{in}}} v(x) \quad \text{and} \quad X_v^{\text{out}} = \prod_{x \in X^{\text{out}}} v(x) \quad (6.3.3.1)$$

in which each $v(x)$, a pointed set, is the value of x (Def. 2.2.3) and an empty product means the one-point set.

(2) Define the set

$$P_X = \text{Hist}^1(X_v^{\text{in}}, X_v^{\text{out}}) \quad (6.3.3.2)$$

of 1-historical propagators of type X .

So a 1-historical propagator of type X is a function that takes each X_v^{in} -profile to an X_v^{out} -profile whose length is one higher than before and that satisfies historicity (6.3.2.2).

The generating structure map of the propagator algebra associated to a 1-loop requires a few notations in its definition. So here we define this map first. The reader should keep in mind that the following definition as well as all the proofs in this section involve simple inductions on the length of some profiles.

Definition 6.3.4. Suppose $X \in \text{Box}_S$, $x_- \in X^{\text{in}}$, and $x_+ \in X^{\text{out}}$ such that $v(x_-) = v(x_+)$ as pointed sets. The box $X \setminus x \in \text{Box}_S$ is obtained from X by removing $x = \{x_\pm\}$. For $\underline{t} \in \text{Prof}(X_v^{\text{out}})$, we will write:

- (i) $\underline{t}_{x_+} \in \text{Prof}(v(x_+))$ for the profile obtained from \underline{t} by taking only the $v(x_+)$ -entry;
- (ii) $\underline{t}_{\setminus x_+} \in \text{Prof}((X \setminus x)_v^{\text{out}})$ for the profile obtained from \underline{t} by removing the $v(x_+)$ -entry.

Suppose $g \in P_X$ (6.3.3.2). Define two functions

$$\text{Prof}((X \setminus x)_v^{\text{in}}) \xrightarrow{\lambda g} \text{Prof}((X \setminus x)_v^{\text{out}}) \quad (6.3.4.1)$$

and

$$\text{Prof}((X \setminus x)_v^{\text{in}}) \xrightarrow{G_g} \text{Prof}(v(x_+)) \quad (6.3.4.2)$$

with the properties

$$|(\lambda g)(?)| = |?| + 1 = |G_g(?)| \quad (6.3.4.3)$$

inductively as follows.

(i) For the empty profile, define

$$\begin{aligned} (\lambda g)(\emptyset) &= g(\emptyset)_{\setminus x_+} \in \text{Prof}((X \setminus x)_v^{\text{out}}) \\ G_g(\emptyset) &= g(\emptyset)_{x_+} \in \text{Prof}(v(x_+)). \end{aligned} \quad (6.3.4.4)$$

In each definition in (6.3.4.4), the first \emptyset is the empty $(X \setminus x)_v^{\text{in}}$ -profile, and the second \emptyset , to which g applies, is the empty X_v^{in} -profile. The profile $g(\emptyset)$ has length 1 because $g \in \text{Hist}^1(X_v^{\text{in}}, X_v^{\text{out}})$. So both $(\lambda g)(\emptyset)$ and $G_g(\emptyset)$ have length 1.

(ii) Inductively, suppose $\underline{w} \in \text{Prof}((X \setminus x)_v^{\text{in}})$ has length $n \geq 1$. Define

$$\begin{aligned} (\lambda g)(\underline{w}) &= g(\underline{w}, G_g(\partial \underline{w}))_{\setminus x_+} \in \text{Prof}((X \setminus x)_v^{\text{out}}) \\ G_g(\underline{w}) &= g(\underline{w}, G_g(\partial \underline{w}))_{x_+} \in \text{Prof}(v(x_+)). \end{aligned} \quad (6.3.4.5)$$

Here ∂ is the truncation (6.3.2.1), so the profile

$$G_g(\partial \underline{w}) \in \text{Prof}(v(x_+)) = \text{Prof}(v(x_-))$$

is already defined and has length n by the induction hypothesis. In each definition in (6.3.4.5),

$$(\underline{w}, G_g(\partial \underline{w})) \in \text{Prof}(X_v^{\text{in}})$$

has length n , so its image under g has length $n + 1$. Therefore, both $(\lambda g)(\underline{w})$ and $G_g(\underline{w})$ have length $n + 1$.

We say that λg and G_g are *defined with respect to* $x = \{x_{\pm}\}$.

The following observation will use Def. 6.3.2 about historical propagators.

Lemma 6.3.5. *In the context of Def. 6.3.4 with $g \in P_X$, the following statements hold.*

- (1) $G_g \in \text{Hist}^1((X \setminus x)_v^{\text{in}}, v(x_+))$.
- (2) $\lambda g \in \text{Hist}^1((X \setminus x)_v^{\text{in}}, (X \setminus x)_v^{\text{out}}) = P_{X \setminus x}$.

Proof. In this proof, we will abbreviate G_g to G . For statement (1), we are trying to show that G is a 1-historical propagator from $(X \setminus x)_v^{\text{in}}$ to $v(x_+)$. In view of the property (6.3.4.3), it remains to check historicity (6.3.2.2) for G , which we will do by induction. Suppose $\underline{w} \in \text{Prof}((X \setminus x)_v^{\text{in}})$ has length ≥ 1 .

If $|\underline{w}| = 1$, then $\partial \underline{w} = \emptyset$. Using the definitions (6.3.4.4) and (6.3.4.5) we have:

$$\begin{aligned} \partial G(\underline{w}) &= \partial g(\underline{w}, G(\emptyset))_{x_+} \\ &= g(\partial(\underline{w}, g(\emptyset)_{x_+}))_{x_+} \quad \text{by historicity of } g \\ &= g(\emptyset)_{x_+} = G(\emptyset). \end{aligned}$$

Inductively, suppose $|\underline{w}| \geq 2$. Using the definition (6.3.4.5), we have:

$$\begin{aligned} \partial G(\underline{w}) &= \partial g(\underline{w}, G(\partial \underline{w}))_{x_+} \\ &= g(\partial \underline{w}, \partial G(\partial \underline{w}))_{x_+} \quad \text{by historicity of } g \\ &= g(\partial \underline{w}, G(\partial \partial \underline{w}))_{x_+} \quad \text{by the induction hypothesis on } G \\ &= G(\partial \underline{w}). \end{aligned}$$

This finishes the proof of statement (1).

Statement (2) is proved by essentially the same argument as above, except that, in view of the definitions (6.3.4.4) and (6.3.4.5), the various right-most subscripts x_+ are replaced by $\setminus x_+$. \square

We are now ready to define the propagator algebra in terms of finitely many generating structure maps and generating axioms as in Def. 6.2.1. Most of the generating structure maps below are easily seen to be well-defined. The only exception is the generating structure map associated to a 1-loop, which we dealt with in Lemma 6.3.5 above.

Definition 6.3.6. Define the *propagator algebra* P as the WD-algebra, in the sense of Def. 6.2.1, with X -colored entry

$$P_X = \text{Hist}^1(X_v^{\text{in}}, X_v^{\text{out}})$$

as in (6.3.3.2) for each $X \in \text{Box}_S$. Its 8 generating structure maps are defined as follows.

- (1) Corresponding to the empty wiring diagram $\epsilon \in \text{WD}^{(\emptyset)}$ (Def. 3.1.1), the structure map

$$\{*\} \xrightarrow{\epsilon} P_{\emptyset} = \text{Hist}^1(\{*\}, \{*\}) = \{*\} \quad (6.3.6.1)$$

sends $*$ to the unique function

$$(\epsilon*) \left(\underbrace{(*, \dots, *)}_m \right) = \left(\underbrace{(*, \dots, *)}_{m+1} \right).$$

- (2) Corresponding to each 1-delay node $\delta_d \in \text{WD}^{(d)}$ (Def. 3.1.2) with d a pointed set, the structure map

$$\{*\} \xrightarrow{\delta_d} P_d = \text{Hist}^1(d, d) \quad (6.3.6.2)$$

sends $*$ to the function

$$(\delta_d*)(\underline{t}) = (*, \underline{t})$$

for each $\underline{t} \in \text{Prof}(d)$. Here the $*$ on the right is the base point in d .

- (3) Corresponding to each name change $\tau_{X,Y} \in \text{WD}(\overset{Y}{X})$ (Def. 3.1.3), the structure map

$$\text{Hist}^1(X_v^{\text{in}}, X_v^{\text{out}}) = P_X \xrightarrow{\tau_{X,Y}} P_Y = \text{Hist}^1(Y_v^{\text{in}}, Y_v^{\text{out}}) \quad (6.3.6.3)$$

is the identity map. Here we are using the fact that, if $x \in X^{\text{in}} \sqcup X^{\text{out}}$ and $y \in Y^{\text{in}} \sqcup Y^{\text{out}}$ corresponds to x under $\tau_{X,Y}$, then $v(x) = v(y)$ as pointed sets.

- (4) Corresponding to each 2-cell $\theta_{X,Y} \in \text{WD}(\overset{X \sqcup Y}{X,Y})$ (Def. 3.1.4), the structure map

$$P_X \times P_Y = \text{Hist}^1(X_v^{\text{in}}, X_v^{\text{out}}) \times \text{Hist}^1(Y_v^{\text{in}}, Y_v^{\text{out}}) \quad (6.3.6.4)$$

$$\downarrow \theta_{X,Y}$$

$$P_{X \sqcup Y} = \text{Hist}^1((X \sqcup Y)_v^{\text{in}}, (X \sqcup Y)_v^{\text{out}}) = \text{Hist}^1(X_v^{\text{in}} \times Y_v^{\text{in}}, X_v^{\text{out}} \times Y_v^{\text{out}})$$

is given by

$$\theta_{X,Y}(f_X, f_Y) = f_X \times f_Y$$

for $f_X \in \text{Hist}^1(X_v^{\text{in}}, X_v^{\text{out}})$ and $f_Y \in \text{Hist}^1(Y_v^{\text{in}}, Y_v^{\text{out}})$.

- (5) Corresponding to each 1-loop $\lambda_{X,x} \in \text{WD}(\overset{X \setminus x}{X})$ (Def. 3.1.5), the structure map

$$P_X \xrightarrow{\lambda_{X,x}} P_{X \setminus x} \quad (6.3.6.5)$$

sends each $g \in P_X$ to $\lambda g \in P_{X \setminus x}$ (6.3.4.1), which is well-defined by Lemma 6.3.5.

- (6) Corresponding to each in-split $\sigma_{X,x_1,x_2} \in \text{WD}(\overset{Y}{X})$ (Def. 3.1.6), the structure map

$$P_X \xrightarrow{\sigma_{X,x_1,x_2}} P_Y \quad (6.3.6.6)$$

is given by

$$(\sigma_{X,x_1,x_2} g)(\underline{y}) = g(\pi \underline{y})$$

for $g \in P_X$ and $\underline{y} \in \text{Prof}(Y_v^{\text{in}})$. Here $\pi \underline{y} \in \text{Prof}(X_v^{\text{in}})$ is the same as \underline{y} except that its $v(x_1)$ -entry and $v(x_2)$ -entry are both given by the $v(x_{12})$ -entry of \underline{y} .

- (7) Corresponding to each out-split $\sigma^{Y,y_1,y_2} \in \text{WD}(\overset{Y}{X})$ (Def. 3.1.7), the structure map

$$P_X \xrightarrow{\sigma^{Y,y_1,y_2}} P_Y \quad (6.3.6.7)$$

is given by

$$(\sigma^{Y,y_1,y_2} g)(\underline{y}) = \pi g(\underline{y})$$

for $g \in P_X$ and $\underline{y} \in \text{Prof}(Y_v^{\text{in}}) = \text{Prof}(X_v^{\text{in}})$. Here $\pi g(\underline{y}) \in \text{Prof}(Y_v^{\text{out}})$ is the same as $g(\underline{y}) \in \text{Prof}(X_v^{\text{out}})$ except that its $v(y_1)$ -entry and $v(y_2)$ -entry are both given by the $v(y_{12})$ -entry of $g(\underline{y})$.

- (8) Corresponding to each 1-wasted wire $\omega_{Y,y} \in \text{WD}(X^Y)$ (Def. 3.1.8), the structure map

$$P_X \xrightarrow{\omega_{Y,y}} P_Y \quad (6.3.6.8)$$

is given by

$$(\omega_{Y,y}g)(\underline{t}) = g(\underline{t}_{\setminus y})$$

for $g \in P_X$ and $\underline{t} \in \text{Prof}(Y_v^{\text{in}})$. Here $\underline{t}_{\setminus y} \in \text{Prof}(X_v^{\text{in}})$ is obtained from \underline{t} by removing the $v(y)$ -entry.

The following observation is the finite presentation theorem for the propagator algebra.

Theorem 6.3.7. *The propagator algebra in Def. 6.3.6 is actually a WD-algebra in the sense of Def. 6.2.1, hence also in the sense of Def. 6.1.2 by Theorem 6.2.2.*

Proof. We need to check the 28 generating axioms in Def. 6.2.1. The 8 generating structure maps are all rather simple functions except for $\lambda_{X,x}$ (6.3.6.5). The only generating axioms that are not obvious are the ones that involve a composition of two such generating structure maps, namely (6.2.1.16) and (6.2.1.17). These two generating axioms are verified in Lemma 6.3.10 and Lemma 6.3.12 below. \square

In preparation for Lemma 6.3.10, we will need a few definitions and notations. Recall that the generating axiom (6.2.1.16) is really the WD-algebra manifestation of Prop. 3.3.15. The next definition is essentially the double-loop version of Def. 6.3.4.

Definition 6.3.8. Suppose:

- $X \in \text{Box}_S$, $x_-^1 \neq x_-^2 \in X^{\text{in}}$, and $x_+^1 \neq x_+^2 \in X^{\text{out}}$ such that $v(x_+^i) = v(x_-^i)$ as pointed sets for each $i \in \{1, 2\}$.
- $X \setminus x^1$, $X \setminus x^2$, and $X \setminus x \in \text{Box}_S$ are obtained from X by removing $x^1 = \{x_\pm^1\}$, $x^2 = \{x_\pm^2\}$, and $x = \{x_\pm^1, x_\pm^2\}$, respectively.

Suppose $\underline{t} \in \text{Prof}(X_v^{\text{out}})$.

- (i) Write $v(x_+) = v(x_+^1) \times v(x_+^2)$ and $v(x_-) = v(x_-^1) \times v(x_-^2)$.
- (ii) Write $\underline{t}_{x_+} \in \text{Prof}(v(x_+))$ for the profile obtained from \underline{t} by taking only the $v(x_+)$ -entries.
- (iii) For $i \in \{1, 2\}$, write $\underline{t}_{x_+^i} \in \text{Prof}(v(x_+^i))$ for the profile obtained from \underline{t} by taking only the $v(x_+^i)$ -entry.

(iv) The profile $\underline{z}_{x_+^i}$ is also defined as long as

$$\underline{z} \in \text{Prof} \left(\prod_{u \in T} v(u) \right)$$

for some subset $\{x_+^1, x_+^2\} \subseteq T \subseteq X^{\text{out}}$.

(v) Write $\underline{t}_{\setminus x_+} \in \text{Prof}((X \setminus x)_v^{\text{out}})$ for the profile obtained from \underline{t} by removing the $v(x_+)$ -entries.

(vi) For $i \in \{1, 2\}$, write $\underline{t}_{\setminus x_+^i} \in \text{Prof}((X \setminus x^i)_v^{\text{out}})$ for the profile obtained from \underline{t} by removing the $v(x_+^i)$ -entry.

Suppose $g \in P_X$. Define two functions

$$\text{Prof}((X \setminus x)_v^{\text{in}}) \xrightarrow{\lambda^2 g} \text{Prof}((X \setminus x)_v^{\text{out}}) \quad (6.3.8.1)$$

and

$$\text{Prof}((X \setminus x)_v^{\text{in}}) \xrightarrow{G_g^2} \text{Prof}(v(x_+)) \quad (6.3.8.2)$$

with the properties

$$|(\lambda^2 g)(?)| = |?| + 1 = |G_g^2(?)| \quad (6.3.8.3)$$

inductively as follows.

(i) For the empty profile, define

$$\begin{aligned} (\lambda^2 g)(\emptyset) &= g(\emptyset)_{\setminus x_+} \in \text{Prof}((X \setminus x)_v^{\text{out}}) \\ G_g^2(\emptyset) &= g(\emptyset)_{x_+} \in \text{Prof}(v(x_+)). \end{aligned} \quad (6.3.8.4)$$

In each definition in (6.3.8.4), the first \emptyset is the empty $(X \setminus x)_v^{\text{in}}$ -profile, and the second \emptyset , to which g applies, is the empty X_v^{in} -profile. The profile $g(\emptyset)$ has length 1 because $g \in \text{Hist}^1(X_v^{\text{in}}, X_v^{\text{out}})$. So both $(\lambda^2 g)(\emptyset)$ and $G_g^2(\emptyset)$ have length 1.

(ii) Inductively, suppose $\underline{w} \in \text{Prof}((X \setminus x)_v^{\text{in}})$ has length $n \geq 1$. Define

$$\begin{aligned} (\lambda^2 g)(\underline{w}) &= g(\underline{w}, G_g^2(\partial \underline{w}))_{\setminus x_+} \in \text{Prof}((X \setminus x)_v^{\text{out}}) \\ G_g^2(\underline{w}) &= g(\underline{w}, G_g^2(\partial \underline{w}))_{x_+} \in \text{Prof}(v(x_+)). \end{aligned} \quad (6.3.8.5)$$

Here ∂ is the truncation (6.3.2.1), so the profile

$$G_g^2(\partial \underline{w}) \in \text{Prof}(v(x_+)) = \text{Prof}(v(x_-))$$

is already defined and has length n by the induction hypothesis. In each definition in (6.3.8.5),

$$(\underline{w}, G_g^2(\partial \underline{w})) \in \text{Prof}(X_v^{\text{in}})$$

has length n , so its image under g has length $n + 1$. Therefore, both $(\lambda^2 g)(\underline{w})$ and $G_g^2(\underline{w})$ have length $n + 1$.

The generating axiom (6.2.1.16) for the propagator algebra P claims that the diagram

$$\begin{array}{ccc} P_X & \xrightarrow{\lambda_{X,x^2}} & P_{X \setminus x^2} \\ \lambda_{X,x^1} \downarrow & & \downarrow \lambda_{X \setminus x^2, x^1} \\ P_{X \setminus x^1} & \xrightarrow{\lambda_{X \setminus x^1, x^2}} & P_{X \setminus x} \end{array} \quad (6.3.8.6)$$

is commutative. We will consider the top-right composition, so let us use the abbreviations

$$\lambda_2 = \lambda_{X,x^2} \quad \text{and} \quad \lambda_1 = \lambda_{X \setminus x^2, x^1}. \quad (6.3.8.7)$$

For the proof of Lemma 6.3.10, we will need the following observation. It provides an explicit formula for the function G_g^2 (6.3.8.2) in terms of G_g (defined with respect to x^2) and $G_{\lambda_2 g}$ (6.3.4.2) (defined with respect to x^1) for each $g \in P_X$.

Lemma 6.3.9. *In the context of Def. 6.3.8, suppose $g \in P_X$ and $\underline{w} \in \text{Prof}((X \setminus x)_v^{\text{in}})$ with length at least 1. Then the following equalities hold.*

$$\begin{aligned} G_g^2(\partial \underline{w})_{x_+^1} &= G_{\lambda_2 g}(\partial \underline{w}) \in \text{Prof}(v(x_+^1)) \\ G_g^2(\partial \underline{w})_{x_+^2} &= G_g(\partial \underline{w}, \partial G_{\lambda_2 g}(\partial \underline{w})) \in \text{Prof}(v(x_+^2)) \end{aligned} \quad (6.3.9.1)$$

In the above equalities:

- (1) ∂ is the truncation (6.3.2.1).
- (2) $\lambda_2 g \in P_{X \setminus x^2}$ by Lemma 6.3.5(2).
- (3) The function

$$\text{Prof}((X \setminus x)_v^{\text{in}}) \xrightarrow{G_{\lambda_2 g}} \text{Prof}(v(x_+^1))$$

is defined with respect to $x^1 = \{x_+^1, x_-^1\}$ (6.3.4.2).

- (4) The function

$$\text{Prof}((X \setminus x^2)_v^{\text{in}}) \xrightarrow{G_g} \text{Prof}(v(x_+^2))$$

is defined with respect to $x^2 = \{x_+^2, x_-^2\}$.

Proof. The proof of (6.3.9.1) is by induction on $|\underline{w}| \geq 1$. If $|\underline{w}| = 1$, then $\partial \underline{w} = \emptyset$. So by (6.3.4.4) and (6.3.8.4) we have

$$G_{\lambda_2 g}(\emptyset) = (\lambda_2 g)(\emptyset)_{x_+^1} = [g(\emptyset)_{\setminus x_+^2}]_{x_+^1} = g(\emptyset)_{x_+^1} = G_g^2(\emptyset)_{x_+^1}.$$

Likewise, we have

$$G_g(\emptyset) = g(\emptyset)_{x_+^2} = G_g^2(\emptyset)_{x_+^2}.$$

This proves the initial case $|\underline{w}| = 1$.

For the induction step, suppose $|\underline{w}| \geq 2$. For the first equality in (6.3.9.1) we have:

$$\begin{aligned}
G_{\lambda_2 g}(\underline{\partial w}) &= (\lambda_2 g)\left(\underline{\partial w}, G_{\lambda_2 g}(\underline{\partial^2 w})\right)_{x_+^1} \quad \text{by (6.3.4.5)} \\
&= g\left(\underline{\partial w}, G_{\lambda_2 g}(\underline{\partial^2 w}), G_g(\underline{\partial^2 w}, \underline{\partial G_{\lambda_2 g}(\underline{\partial^2 w})})\right)_{x_+^1} \quad \text{by (6.3.4.5)} \\
&= g\left(\underline{\partial w}, G_g^2(\underline{\partial^2 w})_{x_+^1}, G_g^2(\underline{\partial^2 w})_{x_+^2}\right)_{x_+^1} \quad \text{by induction hypothesis} \\
&= G_g^2(\underline{\partial w})_{x_+^1} \quad \text{by (6.3.8.5)}.
\end{aligned}$$

In the second equality above, we used the fact that

$$\left\{g(\cdots)_{\setminus x_+^2}\right\}_{x_+^1} = g(\cdots)_{x_+^1}.$$

For the second equality in (6.3.9.1) we have:

$$\begin{aligned}
&G_g(\underline{\partial w}, \underline{\partial G_{\lambda_2 g}(\underline{\partial w})}) \\
&= G_g(\underline{\partial w}, G_{\lambda_2 g}(\underline{\partial^2 w})) \quad \text{by Lemma 6.3.5(1)} \\
&= g\left(\underline{\partial w}, G_{\lambda_2 g}(\underline{\partial^2 w}), G_g(\underline{\partial^2 w}, \underline{\partial G_{\lambda_2 g}(\underline{\partial^2 w})})\right)_{x_+^2} \quad \text{by (6.3.4.5)} \\
&= g\left(\underline{\partial w}, G_g^2(\underline{\partial^2 w})_{x_+^1}, G_g^2(\underline{\partial^2 w})_{x_+^2}\right)_{x_+^2} \quad \text{by induction hypothesis} \\
&= G_g^2(\underline{\partial w})_{x_+^2} \quad \text{by (6.3.8.5)}.
\end{aligned}$$

This finishes the induction. □

Lemma 6.3.10. *The propagator algebra P in Def. 6.3.6 satisfies the generating axiom (6.2.1.16); i.e., the diagram (6.3.8.6) is commutative.*

Proof. We will use the abbreviations (6.3.8.7). By the symmetry between $x^1 = \{x_{\pm}^1\}$ and $x^2 = \{x_{\pm}^2\}$, it suffices to show that

$$(\lambda_1 \lambda_2 g)(\underline{w}) = (\lambda^2 g)(\underline{w}) \quad (6.3.10.1)$$

for $g \in P_X$ and $\underline{w} \in \text{Prof}((X \setminus x)_v^{\text{in}})$, where $\lambda^2 g$ is defined in (6.3.8.1). We prove (6.3.10.1) by induction on the length $|\underline{w}|$.

If $|\underline{w}| = 0$, then by (6.3.4.4) and (6.3.8.4) the left side of (6.3.10.1) is:

$$(\lambda_2 g)(\emptyset)_{\setminus x_+^1} = \left[g(\emptyset)_{\setminus x_+^2} \right]_{\setminus x_+^1} = g(\emptyset)_{\setminus x_+} = (\lambda^2 g)(\emptyset).$$

For the induction step, suppose $|\underline{w}| \geq 1$. Then the left side of (6.3.10.1) is:

$$\begin{aligned}
& (\lambda_2 g)(\underline{w}, G_{\lambda_2 g}(\partial \underline{w}))_{\setminus x_+^1} \quad \text{by (6.3.4.5)} \\
& = g(\underline{w}, G_{\lambda_2 g}(\partial \underline{w}), G_g(\partial \underline{w}, \partial G_{\lambda_2 g}(\partial \underline{w})))_{\setminus x_+} \quad \text{by (6.3.4.5)} \\
& = g(\underline{w}, G_g^2(\partial \underline{w})_{x_+^1}, G_g^2(\partial \underline{w})_{x_+^2})_{\setminus x_+} \quad \text{by (6.3.9.1)} \\
& = (\lambda^2 g)(\underline{w}) \quad \text{by (6.3.8.5)}.
\end{aligned}$$

This finishes the induction. \square

The proof of the generating axiom (6.2.1.17) in Lemma 6.3.12 below will use the following observation. Recall that the generating axiom (6.2.1.17) is really a WD-algebra manifestation of the generating relation (3.3.19.1).

Lemma 6.3.11. *In the context of Prop. 3.3.19, recall that*

$$X = \frac{Y}{(x^1 = x^2)}, \quad X' = \frac{X}{(x_1 = x_2)}, \quad \text{and} \quad X^* = X \setminus \{x^{12}, x_1, x_2\}.$$

Consider the maps:

$$\begin{array}{ccc}
P_X & \xrightarrow{\sigma^\bullet = \sigma^{Y, x^1, x^2}} & P_Y \\
\sigma_\bullet = \sigma_{X, x_1, x_2} \downarrow & & \\
P_{X'} & &
\end{array}$$

Then for $g \in P_X$ and $\underline{w} \in \text{Prof}(X_v^{*\text{in}})$ with length ≥ 1 , the equality

$$G_{\sigma^\bullet g}^2(\partial \underline{w}) = (G_{\sigma_\bullet g}(\partial \underline{w}), G_{\sigma_\bullet g}(\partial \underline{w})) \quad (6.3.11.1)$$

holds. Here:

(1) $\sigma^\bullet g \in P_Y$ and $\sigma_\bullet g \in P_{X'}$.

(2) The function

$$\text{Prof}(X_v^{*\text{in}}) \xrightarrow{G_{\sigma^\bullet g}^2} \text{Prof}(v(x^1) \times v(x^2))$$

is defined as in (6.3.8.2), starting with the box Y and the wires $x^1 \neq x^2 \in Y^{\text{out}}$ and $x_1 \neq x_2 \in Y^{\text{in}}$.

(3) The function

$$\text{Prof}(X_v^{*\text{in}}) \xrightarrow{G_{\sigma_\bullet g}} \text{Prof}(v(x^{12}))$$

is defined as in (6.3.4.2), starting with the box X' and the wires $x_{12} \in X'^{\text{in}}$ and $x^{12} \in X'^{\text{out}}$.

Proof. The proof is by induction on the length of \underline{w} . If $|\underline{w}| = 1$, the $\partial\underline{w} = \emptyset$. So we have:

$$\begin{aligned}
G_{\sigma^\bullet g}^2(\emptyset) &= (\sigma^\bullet g)(\emptyset)_{\{x^1, x^2\}} \quad \text{by (6.3.8.4)} \\
&= \left(g(\emptyset)_{x^{12}}, g(\emptyset)_{x^{12}} \right) \quad \text{by (6.3.6.7)} \\
&= \left((\sigma_\bullet g)(\emptyset)_{x^{12}}, (\sigma_\bullet g)(\emptyset)_{x^{12}} \right) \quad \text{by (6.3.6.6)} \\
&= \left(G_{\sigma_\bullet g}(\emptyset), G_{\sigma_\bullet g}(\emptyset) \right) \quad \text{by (6.3.4.4)}
\end{aligned}$$

For the induction step, suppose $|\underline{w}| \geq 2$. Then we have:

$$\begin{aligned}
G_{\sigma^\bullet g}^2(\partial\underline{w}) &= (\sigma^\bullet g)\left(\partial\underline{w}, G_{\sigma^\bullet g}^2(\partial^2\underline{w})\right)_{\{x^1, x^2\}} \quad \text{by (6.3.8.5)} \\
&= (\sigma^\bullet g)\left(\partial\underline{w}, G_{\sigma_\bullet g}(\partial^2\underline{w}), G_{\sigma_\bullet g}(\partial^2\underline{w})\right)_{\{x^1, x^2\}} \quad \text{by induction hypothesis} \\
&= \left(g(\partial\underline{w}, G_{\sigma_\bullet g}(\partial^2\underline{w}), G_{\sigma_\bullet g}(\partial^2\underline{w}))_{x^{12}}, \text{ same} \right) \quad \text{by (6.3.6.7)} \\
&= \left((\sigma_\bullet g)(\partial\underline{w}, G_{\sigma_\bullet g}(\partial^2\underline{w}))_{x^{12}}, \text{ same} \right) \quad \text{by (6.3.6.6)} \\
&= \left(G_{\sigma_\bullet g}(\partial\underline{w}), G_{\sigma_\bullet g}(\partial\underline{w}) \right) \quad \text{by (6.3.4.5)}
\end{aligned}$$

This finishes the induction. □

Lemma 6.3.12. *The propagator algebra P in Def. 6.3.6 satisfies the generating axiom (6.2.1.17); i.e., the diagram*

$$\begin{array}{ccccc}
P_X & \xrightarrow{\sigma^\bullet = \sigma^{Y, x^1, x^2}} & P_Y & \xrightarrow{\lambda_{(1)} = \lambda_{Y, x(1)}} & P_{Y \setminus x(1)} \\
\sigma_\bullet = \sigma_{X, x^1, x^2} \downarrow & & & & \downarrow \lambda_{(2)} = \lambda_{Y \setminus x(1), x(2)} \\
P_{X'} & \xrightarrow{\lambda = \lambda_{X', x}} & & & P_{X^*}
\end{array}$$

is commutative.

Proof. For $g \in P_X$ and $\underline{w} \in \text{Prof}(X_v^{*in})$, we will prove the desired equality

$$(\lambda \sigma_\bullet g)(\underline{w}) = (\lambda_{(2)} \lambda_{(1)} \sigma^\bullet g)(\underline{w}) \in \text{Prof}(X_v^{*out}) \quad (6.3.12.1)$$

by induction on the length of \underline{w} . If $|\underline{w}| = 0$, then both sides of (6.3.12.1) are equal to $g(\emptyset)_{\setminus x^{12}}$.

For the induction step, suppose $|\underline{w}| \geq 1$. Then we have:

$$\begin{aligned}
(\lambda\sigma \bullet g)(\underline{w}) &= (\sigma \bullet g)\left(\underline{w}, G_{\sigma \bullet g}(\partial \underline{w})\right)_{\setminus x^{12}} \quad \text{by (6.3.4.5)} \\
&= g\left(\underline{w}, G_{\sigma \bullet g}(\partial \underline{w}), G_{\sigma \bullet g}(\partial \underline{w})\right)_{\setminus x^{12}} \quad \text{by (6.3.6.6)} \\
&= g\left(\underline{w}, G_{\sigma \bullet g}^2(\partial \underline{w})\right)_{\setminus x^{12}} \quad \text{by (6.3.11.1)} \\
&= (\sigma \bullet g)\left(\underline{w}, G_{\sigma \bullet g}^2(\partial \underline{w})\right)_{\setminus \{x^1, x^2\}} \quad \text{by (6.3.6.7)} \\
&= (\lambda_{(2)}\lambda_{(1)}\sigma \bullet g)(\underline{w}) \quad \text{by (6.3.8.5) and (6.3.10.1)}
\end{aligned}$$

This finishes the induction. \square

Remark 6.3.13. To see that our definition of the propagator algebra P in Def. 6.3.6 agrees with the one in [RS13] (section 3), recall that our version of the propagator algebra is based on Def. 6.2.1. On the other hand, the propagator algebra in [RS13] is based on Def. 6.1.1, which is equivalent to Def. 6.1.2. A direct inspection of [RS13] (Announcement 3.3.3 and Eq. (17)) reveals that their structure map of P , when applied to the generating wiring diagrams (section 3.1), reduces to our 8 generating structure maps in Def. 6.3.6. Theorem 6.2.2 then guarantees that the two definitions are equivalent.

6.4. Algebras over the Operad of Normal Wiring Diagrams

The purpose of this section is to provide a finite presentation for algebras over the Box_S -colored operad WD_\bullet of normal wiring diagrams (Prop. 5.3.5). We begin by defining these algebras in terms of finitely many generators and relations. Recall from Def. 5.3.6 that a *normal generating wiring diagram* is a generating wiring diagram that is not a 1-delay node δ_d .

Definition 6.4.1. A WD_\bullet -algebra A consists of the following data.

- (1) For each $X \in \text{Box}_S$, A is equipped with a class A_X called the *X-colored entry* of A .
- (2) It is equipped with the 7 *generating structure maps* in Def. 6.2.1 corresponding to the normal generating wiring diagrams.

This data is required to satisfy the same 28 generating axioms in Def. 6.2.1.

The next observation is the WD_\bullet version of Theorem 6.2.2. It guarantees that the two existing definitions of a WD_\bullet -algebra are equivalent. The first one (Def. 6.1.2) is in terms of a general structure map satisfying an associativity axiom for a general operadic composition. The other one (Def. 6.4.1) is in terms of 7 generating structure maps and 28 generating axioms regarding the normal generating wiring diagram. Therefore, algebras over WD_\bullet have a finite presentation.

Theorem 6.4.2. *For the operad WD_\bullet of normal wiring diagrams (Prop. 5.3.5), Def. 6.1.2 with $\mathbf{O} = \text{WD}_\bullet$ and Def. 6.4.1 of a WD_\bullet -algebra are equivalent.*

Proof. Simply restrict the proof of Theorem 6.2.2 to normal (generating) wiring diagrams. Instead of Theorem 5.1.7, here we use Theorem 5.3.7 for the existence of a presentation involving only normal generating wiring diagrams. \square

Remark 6.4.3. In [Spi15b] (Def. 4.1–4.4) several closely related WD_\bullet -algebras were defined, although they appeared in the language of symmetric monoidal categories. By Theorem 6.4.2 each of these WD_\bullet -algebras has a finite presentation with 7 generating structure maps and 28 generating axioms as in Def. 6.4.1. In Section 6.5 we will discuss one of these WD_\bullet -algebras and its finite presentation. In Section 6.7 we will discuss a similar algebra of open dynamical systems over the operad WD_0 of strict wiring diagrams. Essentially the same formalism applies to the other WD_\bullet -algebras in [Spi15b].

6.5. Finite Presentation for the Algebra of Discrete Systems

The purpose of this section is to provide a finite presentation for the algebra of discrete systems introduced in [Spi15b] (Definition 4.9). Let us first recall some definitions from [Spi15b] (Sections 2.1 and 4.1).

Assumption 6.5.1. Throughout this section, S denotes the class of sets. So $\text{Box}_S = \text{Box}_{\text{Set}}$, and WD_\bullet is the Box_{Set} -colored operad of normal wiring diagrams (Prop. 5.3.5).

Definition 6.5.2. Suppose A and B are sets. An (A, B) -discrete system is a triple $(T, f^{\text{rd}}, f^{\text{up}})$ consisting of:

- (1) a set T , called the *state set*;
- (2) a function $f^{\text{rd}} : T \rightarrow B$, called the *readout function*;
- (3) a function $f^{\text{up}} : A \times T \rightarrow T$, called the *update function*.

Definition 6.5.3. Suppose $X = (X^{\text{in}}, X^{\text{out}}) \in \text{Box}_S$ is a box. An X -discrete system is an $(X_v^{\text{in}}, X_v^{\text{out}})$ -discrete system, where

$$X_v^{\text{in}} = \prod_{x \in X^{\text{in}}} v(x) \quad \text{and} \quad X_v^{\text{out}} = \prod_{x \in X^{\text{out}}} v(x) \in \text{Set}$$

as in (6.3.3.1) (but with sets instead of pointed sets). In other words, an X -discrete system is a triple $(T, f^{\text{rd}}, f^{\text{up}})$ such that T is a set and that

$$T \xrightarrow{f^{\text{rd}}} X_v^{\text{out}} \quad \text{and} \quad X_v^{\text{in}} \times T \xrightarrow{f^{\text{up}}} T$$

are functions. The collection of all X -discrete systems is denoted by $\text{DS}(X)$.

Example 6.5.4. If $X = \emptyset \in \text{Box}_S$ is the empty box, then $X_v^{\text{in}} = X_v^{\text{out}} = *$ by convention. A readout function $f^{\text{rd}} : T \longrightarrow *$ gives no information, and $* \times T \cong T$. So

$$\text{DS}(\emptyset) = \left\{ (T, f^{\text{up}}) : T \in \text{Set}, f^{\text{up}} : T \longrightarrow T \text{ a function} \right\}. \quad (6.5.4.1)$$

In particular, the collection $\text{DS}(\emptyset)$ is *not* a set but a proper class. This example explains why in Def. 6.1.1 we defined an entry of an operad algebra to be a class and not a set.

We now define the algebra of discrete systems in terms of 7 very simple generating structure maps.

Definition 6.5.5. The *algebra of discrete systems* is the WD_\bullet -algebra DS in the sense of Def. 6.4.1 defined as follows.

- (1) For each $X \in \text{Box}_S$, the X -colored entry is the class $\text{DS}(X)$ of X -discrete systems in Def. 6.5.3
- (2) The 7 generating structure maps—as in Def. 6.2.1 but without δ_d —are defined as follows.
 - (i) Corresponding to the empty wiring diagram $\epsilon \in \text{WD}_\bullet^{(\emptyset)}$ (Def. 3.1.1), the chosen element in $\text{DS}(\emptyset)$ (6.5.4.1) is the pair $(*, \text{Id})$ with:
 - the one-point set $*$ as its state set;
 - the identity map as its update function.
 - (ii) Corresponding to each name change $\tau_{X,Y} \in \text{WD}_\bullet^{(Y)}(X)$ (Def. 3.1.3), the structure map

$$\text{DS}(X) \xrightarrow[\text{=}]{\tau_{X,Y}} \text{DS}(Y)$$

is the identity map, using the fact that $X_v^{\text{in}} = Y_v^{\text{in}}$ and $X_v^{\text{out}} = Y_v^{\text{out}}$.

- (iii) Corresponding to a 2-cell $\theta_{X,Y} \in \text{WD}_\bullet^{(X \sqcup Y)}(X, Y)$ (Def. 3.1.4), it has the structure map

$$\begin{array}{ccc} \text{DS}(X) \times \text{DS}(Y) & & \left((T_X, f_X^{\text{rd}}, f_X^{\text{up}}), (T_Y, f_Y^{\text{rd}}, f_Y^{\text{up}}) \right) \\ \theta_{X,Y} \downarrow & & \downarrow \\ \text{DS}(X \sqcup Y) & & \left(T_X \times T_Y, f_X^{\text{rd}} \times f_Y^{\text{rd}}, f_X^{\text{up}} \times f_Y^{\text{up}} \right) \end{array}$$

using the fact that

$$(X \sqcup Y)_v^{\text{in}} = X_v^{\text{in}} \times Y_v^{\text{in}} \quad \text{and} \quad (X \sqcup Y)_v^{\text{out}} = X_v^{\text{out}} \times Y_v^{\text{out}}.$$

- (iv) Corresponding to a 1-loop $\lambda_{X,x} \in \text{WD}_\bullet^{(X \setminus x)}(X)$ (Def. 3.1.5) with $x = (x_-, x_+) \in X^{\text{in}} \times X^{\text{out}}$ (so $v(x_+) = v(x_-)$), it has the structure map

$$\text{DS}(X) \xrightarrow{\lambda_{X,x}} \text{DS}(X \setminus x) \quad (T, f^{\text{rd}}, f^{\text{up}}) \longmapsto (T, f_{\setminus x}^{\text{rd}}, f_{\setminus x}^{\text{up}})$$

in which, for $(\underline{y}, t) \in (X \setminus x)_v^{\text{in}} \times T$:

$$f^{\text{rd}}(t) = (f^{\text{rd}}(t)_{\setminus x_+}, f^{\text{rd}}(t)_{x_+}) \in X_v^{\text{out}} = (X \setminus x)_v^{\text{out}} \times v(x_+);$$

$$f_{\setminus x}^{\text{rd}}(t) = f^{\text{rd}}(t)_{\setminus x_+} \in (X \setminus x)_v^{\text{out}};$$

$$f_{\setminus x}^{\text{up}}(\underline{y}, t) = f^{\text{up}}((\underline{y}, f^{\text{rd}}(t)_{x_+}), t).$$

- (v) Corresponding to an in-split $\sigma_{X, x_1, x_2} \in \text{WD}_\bullet(\frac{Y}{X})$ (Def. 3.1.6) with $v(x_1) = v(x_2)$ and $Y = X/(x_1 = x_2)$, it has the structure map

$$\text{DS}(X) \xrightarrow{\sigma_{X, x_1, x_2}} \text{DS}(Y) \quad (T, f^{\text{rd}}, f^{\text{up}}) \longmapsto (T, f^{\text{rd}}, \sigma_\bullet f^{\text{up}})$$

in which the update function is

$$(\sigma_\bullet f^{\text{up}})(\underline{y}, t) = f^{\text{up}}(\sigma_\bullet \underline{y}, t)$$

for $(\underline{y}, t) \in Y_v^{\text{in}} \times T$. Here $\sigma_\bullet \underline{y} \in X_v^{\text{in}}$ is obtained from \underline{y} by using the $v(x_{12})$ -entry of \underline{y} in both the $v(x_1)$ -entry and the $v(x_2)$ -entry, where $x_{12} \in Y^{\text{in}}$ is the identified element of x_1 and x_2 .

- (vi) Corresponding to an out-split $\sigma^{Y, y_1, y_2} \in \text{WD}_\bullet(\frac{Y}{X})$ (Def. 3.1.7) with $v(y_1) = v(y_2)$ and $X = Y/(y_1 = y_2)$, it has the structure map

$$\text{DS}(X) \xrightarrow{\sigma^{Y, y_1, y_2}} \text{DS}(Y) \quad (T, f^{\text{rd}}, f^{\text{up}}) \longmapsto (T, \sigma^\bullet f^{\text{rd}}, f^{\text{up}})$$

in which the readout function is

$$(\sigma^\bullet f^{\text{rd}})(t) = \sigma^\bullet(f^{\text{rd}}(t)) \in Y_v^{\text{out}}$$

for $t \in T$. Here $\sigma^\bullet(f^{\text{rd}}(t))$ is obtained from $f^{\text{rd}}(t) \in X_v^{\text{out}}$ by using its $v(y_{12})$ -entry in both the $v(y_1)$ -entry and the $v(y_2)$ -entry, where $y_{12} \in X^{\text{out}}$ is the identified element of y_1 and y_2 .

- (vii) Corresponding to a 1-wasted wire $\omega_{Y, y} \in \text{WD}_\bullet(\frac{Y}{X})$ (Def. 3.1.8) with $y \in Y^{\text{in}}$ and $X = Y \setminus y$, it has the structure map

$$\text{DS}(X) \xrightarrow{\omega_{Y, y}} \text{DS}(Y) \quad (T, f^{\text{rd}}, f^{\text{up}}) \longmapsto (T, f^{\text{rd}}, \omega f^{\text{up}})$$

in which the update function is

$$(\omega f^{\text{up}})(\underline{z}, t) = f^{\text{up}}(\underline{z}_{\setminus y}, t)$$

for $(\underline{z}, t) \in Y_v^{\text{in}} \times T$. Here $\underline{z}_{\setminus y} \in X_v^{\text{in}}$ is obtained from \underline{z} by removing the $v(y)$ -entry.

Remark 6.5.6. In [Spi15b] (Example 2.7) the image of $\theta_{X, Y}$ is called the *parallel composition*. The structure map $\lambda_{X, x}$ corresponding to a 1-loop was discussed in [Spi15b] (Example 2.9). The structure maps σ_{X, x_1, x_2} and σ^{Y, y_1, y_2} corresponding to an in-split and an out-split were discussed in [Spi15b] (Example 2.8).

The following observation ensures that DS is a well-defined WD_\bullet -algebra, i.e., that it satisfies the generating axioms.

Theorem 6.5.7. *The algebra of discrete systems DS in Def. 6.5.5 is actually a WD_\bullet -algebra in the sense of Def. 6.4.1, hence also in the sense of Def. 6.1.2 by Theorem 6.4.2.*

Proof. We must check that DS satisfies the 28 generating axioms in Def. 6.2.1, which are all trivial to check. For example, the generating axiom (6.2.1.17) says that, in the setting of (3.3.19.1) with $X^* = X \setminus \{x^{12}, x_1, x_2\}$ and $v(x^{12}) = v(x_1) = v(x_2)$, the diagram

$$\begin{array}{ccccc} \text{DS}(X) & \xrightarrow{\sigma_{Y,x^1,x^2}} & \text{DS}(Y) & \xrightarrow{\lambda_{Y,x(1)}} & \text{DS}(Y \setminus x(1)) \\ \sigma_{X,x_1,x_2} \downarrow & & & & \downarrow \lambda_{Y \setminus x(1),x(2)} \\ \text{DS}(X') & \xrightarrow{\lambda_{X',x}} & & & \text{DS}(X^*) \end{array}$$

is commutative. When applied to a typical element $(T, f^{\text{rd}}, f^{\text{up}}) \in \text{DS}(X)$, a simple direct inspection reveals that both compositions in the above diagram yield $(T, g^{\text{rd}}, g^{\text{up}}) \in \text{DS}(X^*)$, in which

$$\begin{aligned} g^{\text{rd}}(t) &= f^{\text{rd}}(t)_{\setminus x^{12}}; \\ g^{\text{up}}(\underline{y}, t) &= f^{\text{up}}\left(\left(\underline{y}, f^{\text{rd}}(t)_{x^{12}}, f^{\text{rd}}(t)_{x^{12}}\right), t\right) \end{aligned}$$

Here for $(\underline{y}, t) \in X_v^{*\text{in}} \times T$, we have

$$\begin{aligned} f^{\text{rd}}(t) &= \left(f^{\text{rd}}(t)_{\setminus x^{12}}, f^{\text{rd}}(t)_{x^{12}}\right) \in X_v^{\text{out}} = X_v^{*\text{out}} \times v(x^{12}); \\ \left(\underline{y}, f^{\text{rd}}(t)_{x^{12}}, f^{\text{rd}}(t)_{x^{12}}\right) &\in X_v^{*\text{in}} \times v(x_1) \times v(x_2) = X_v^{\text{in}}. \end{aligned}$$

The other generating axioms are checked similarly. \square

Remark 6.5.8. Our definition of the algebra of discrete systems DS actually agrees with the one in [Spi15b] (Example 2.7 and Def. 4.9). To see this, note that Spivak's definition is essentially based on Def. 6.1.1, except that it is stated in terms of symmetric monoidal categories. Spivak's structure map of DS, when applied to the 7 normal generating wiring diagrams (Def. 5.3.6(1)), agrees with ours in Def. 6.5.5. So Theorems 6.4.2 and 6.5.7 imply that the two definitions of DS—namely, the one in [Spi15b] and our Def. 6.5.5—are equivalent.

6.6. Algebras over the Operad of Strict Wiring Diagrams

The purpose of this section is to provide a finite presentation for algebras over the Box_S -colored operad WD_0 of strict wiring diagrams (Prop. 5.4.6). We begin by defining these algebras in terms of finitely many generators and relations. Recall from Def. 5.4.7) that:

- (1) The *strict generating wiring diagrams* are the empty wiring diagram ϵ , a name change $\tau_{X,Y}$, a 2-cell $\theta_{X,Y}$, and a 1-loop $\lambda_{X,x}$.
- (2) The *strict elementary relations* are the 8 elementary relations that involve only strict generating wiring diagrams on both sides.

Definition 6.6.1. A WD_0 -algebra A consists of the following data.

- (1) For each $X \in \text{Box}_S$, A is equipped with a class A_X called the *X-colored entry* of A .
- (2) It is equipped with the 4 *generating structure maps* in Def. 6.2.1 corresponding to the strict generating wiring diagrams.

This data is required to satisfy the 8 generating axioms in Def. 6.2.1 corresponding to the strict elementary relations, namely, (6.2.1.9), (6.2.1.10), (6.2.1.11), (6.2.1.12), (6.2.1.13), (6.2.1.14), (6.2.1.15), and (6.2.1.16).

The next observation is the WD_0 version of Theorems 6.2.2 and 6.4.2. It gives a finite presentation for WD_0 -algebras.

Theorem 6.6.2. *For the operad WD_0 of strict wiring diagrams (Prop. 5.4.6), Def. 6.1.2 with $O = WD_0$ and Def. 6.6.1 of a WD_0 -algebra are equivalent.*

Proof. Simply restrict the proof of Theorem 6.2.2 to strict (generating) wiring diagrams. Instead of Theorem 5.1.7, here we use Theorem 5.4.8 for the existence of a presentation involving only strict generating wiring diagrams. \square

6.7. Finite Presentation for the Algebra of Open Dynamical Systems

The purpose of this section is to provide a finite presentation for the algebra of open dynamical systems introduced in [VSL14]. In [VSL14] the algebra of open dynamical systems G was defined and verified using essentially Def. 6.1.1 but in the form of symmetric monoidal categories and monoidal functors. Our definition of G in Def. 6.7.6 is based on Def. 6.6.1, which involves four relatively simple generating structure maps. Our verification that G is actually a WD_0 -algebra in Theorem 6.7.7 boils down to verifying the generating axiom (6.2.1.16) for a double-loop. This is a simple exercise involving the definition of the generating structure map corresponding to a 1-loop (6.7.6.4). The equivalence between the two definitions of the algebra of open dynamical systems is explained in Remark 6.7.8.

Let us first recall the setting of [VSL14]. For the definitions of the basic objects in differential geometry that appear below, the reader may consult, for example, [Hel78] (Ch.1).

Assumption 6.7.1. Throughout this section:

- (1) S is a chosen set of representatives of isomorphism classes of second-countable smooth manifolds, henceforth called *manifolds*.
- (2) The operad of strict wiring diagrams WD_0 (Prop. 5.4.6) is defined using this choice of S .
- (3) All the maps between manifolds are smooth maps.
- (4) For a manifold M , denote by $\pi : TM \longrightarrow M$ the projection map of the tangent bundle.

Definition 6.7.2. Suppose $(M, v) \in \text{Fin}_S$ is an S -finite set (Def. 2.2.3).

- (1) Define

$$M_v = \prod_{m \in M} v(m) \in S. \quad (6.7.2.1)$$

- (2) For a subset $I \subseteq M$ and $\underline{x} = (x_m)_{m \in M} \in M_v$, define

$$\begin{aligned} \underline{x}_I &= (x_m)_{m \in I} \in I_v = \prod_{m \in I} v(m) \\ \underline{x}_{\setminus I} &= (x_m)_{m \in M \setminus I} \in (M \setminus I)_v = \prod_{m \in M \setminus I} v(m). \end{aligned} \quad (6.7.2.2)$$

Definition 6.7.3. An *open dynamical system*, or *ods* for short, is a tuple $(M, U^{\text{in}}, U^{\text{out}}, f)$ consisting of:

- (1) manifolds M, U^{in} , and U^{out} ;
- (2) a pair of maps $f = (f^{\text{in}}, f^{\text{out}})$,

$$\begin{array}{ccc} M \times U^{\text{in}} & \xrightarrow{f^{\text{in}}} & TM \\ & \searrow \text{project} & \downarrow \pi \\ & & M \end{array} \quad \begin{array}{c} M \\ \downarrow f^{\text{out}} \\ U^{\text{out}} \end{array}$$

such that the left diagram is commutative.

Next is [VSL14] (Def. 4.2).

Definition 6.7.4. For each $X = (X^{\text{in}}, X^{\text{out}}) \in \text{Box}_S$, define the class

$$\mathbb{G}_X = \left\{ (M, f) : M \in \text{Fin}_S, (M_v, X_v^{\text{in}}, X_v^{\text{out}}, f) \text{ is an ods} \right\} \quad (6.7.4.1)$$

in which M_v, X_v^{in} , and X_v^{out} are as in (6.7.2.1).

Example 6.7.5. For the empty box $\emptyset = (\emptyset, \emptyset) \in \text{Box}_S$ and an S -finite set M , to say that $(M_v, \emptyset_v = \{*\}, \emptyset_v = \{*\}, f)$ is an open dynamical system means that f is a pair

of maps $f = (f^{\text{in}}, f^{\text{out}})$,

$$\begin{array}{ccc} M_v = M_v \times \{*\} & \xrightarrow{f^{\text{in}}} & TM_v \\ & \searrow \text{Id} & \downarrow \pi \\ & & M_v \end{array} \quad \begin{array}{c} M_v \\ \downarrow f^{\text{out}} \\ \{*\} \end{array}$$

such that the left diagram is commutative. Since f^{out} gives no information, $f = f^{\text{in}}$ is equivalent to a vector field on M_v . So

$$\mathbf{G}_\emptyset = \left\{ (M, f) : M \in \text{Fin}_S, f \text{ is a vector field on } M_v \right\}. \quad (6.7.5.1)$$

We now define the algebra of open dynamical systems in terms of 4 generating structure maps.

Definition 6.7.6. The *algebra of open dynamical systems* is the WD_0 -algebra \mathbf{G} in the sense of Def. 6.6.1 defined as follows.

- (1) For each box $X \in \text{Box}_S$, the X -colored entry is \mathbf{G}_X in (6.7.4.1).
- (2) The 4 generating structure maps (Def. 6.2.1) are defined as follows.
 - (i) Corresponding to the empty wiring diagram $\epsilon \in \text{WD}_0^{(\emptyset)}$ (Def. 3.1.1), the structure map

$$* \xrightarrow{\epsilon} \mathbf{G}_\emptyset \quad (6.7.6.1)$$

sends $*$ to $(\emptyset, *) \in \mathbf{G}_\emptyset$ (6.7.5.1). Here $\emptyset \in \text{Fin}_S$ is the empty set, in which $\emptyset_v = \{*\}$, and in the second entry $*$ is the trivial vector field.

- (ii) Corresponding to a name change $\tau_{X,Y} \in \text{WD}_0^{(X,Y)}$ (Def. 3.1.3), the structure map

$$\mathbf{G}_X \xrightarrow[\text{=}]{\tau_{X,Y}} \mathbf{G}_Y \quad (6.7.6.2)$$

is the identity map, using the fact that $X_v^{\text{in}} = Y_v^{\text{in}}$ and $X_v^{\text{out}} = Y_v^{\text{out}}$.

- (iii) Corresponding to a 2-cell $\theta_{X,Y} \in \text{WD}_0^{(X \sqcup Y)}$ (Def. 3.1.4), it has the structure map

$$\begin{array}{ccc} \mathbf{G}_X \times \mathbf{G}_Y & \left((M_X, f_X), (M_Y, f_Y) \right) & (6.7.6.3) \\ \theta_{X,Y} \downarrow & \downarrow & \\ \mathbf{G}_{X \sqcup Y} & \left(M_X \sqcup M_Y, f_X \times f_Y \right) & \end{array}$$

in which $M_X \sqcup M_Y$ is the coproduct in Fin_S (Def. 2.2.3).

- (iv) Corresponding to a 1-loop $\lambda_{X,x} \in \text{WD}_0(\overset{X \setminus x}{X})$ (Def. 3.1.5) with $x = (x_-, x_+) \in X^{\text{in}} \times X^{\text{out}}$, it has the structure map

$$\mathbf{G}_X \xrightarrow{\lambda_{X,x}} \mathbf{G}_{X \setminus x} \quad (M, f) \longmapsto (M, f_{\setminus x}). \quad (6.7.6.4)$$

The maps $f_{\setminus x} = (f_{\setminus x}^{\text{in}}, f_{\setminus x}^{\text{out}})$ are defined as

$$\begin{aligned} f_{\setminus x}^{\text{in}}(\underline{m}, \underline{y}) &= f^{\text{in}}(\underline{m}, (f^{\text{out}}(\underline{m})_{x_+}, \underline{y})) \in TM_v \\ f_{\setminus x}^{\text{out}}(\underline{m}) &= f^{\text{out}}(\underline{m})_{\setminus x_+} \in (X \setminus x)_v^{\text{out}} \end{aligned}$$

for $\underline{m} \in M_v$ and $\underline{y} \in (X \setminus x)_v^{\text{in}}$. Recalling that $f^{\text{out}}(\underline{m}) \in X_v^{\text{out}}$, the elements

$$\begin{aligned} f^{\text{out}}(\underline{m})_{x_+} \in v(x_+) = v(x_-) \quad \text{and} \quad f^{\text{out}}(\underline{m})_{\setminus x_+} \in (X \setminus x)_v^{\text{out}} \end{aligned}$$

are as in (6.7.2.2).

The following observation ensures that \mathbf{G} is a well-defined WD_0 -algebra, i.e., that it satisfies the generating axioms.

Theorem 6.7.7. *The algebra of open dynamical systems \mathbf{G} in Def. 6.7.6 is actually a WD_0 -algebra in the sense of Def. 6.6.1, hence also in the sense of Def. 6.1.2 by Theorem 6.6.2.*

Proof. We must check the 8 generating axioms corresponding to the strict elementary relations listed in Def. 6.6.1. All of them follow from a quick inspection of the definitions except for (6.2.1.16). This generating axiom says that, in the setting of the elementary relation (3.3.15.1) corresponding to a double-loop, the diagram

$$\begin{array}{ccc} \mathbf{G}_X & \xrightarrow{\lambda_{X,x^2}} & \mathbf{G}_{X \setminus x^2} \\ \lambda_{X,x^1} \downarrow & & \downarrow \lambda_{X \setminus x^2, x^1} \\ \mathbf{G}_{X \setminus x^1} & \xrightarrow{\lambda_{X \setminus x^1, x^2}} & \mathbf{G}_{X \setminus x} \end{array} \quad (6.7.7.1)$$

is commutative.

To prove (6.7.7.1), suppose $(M, f) \in \mathbf{G}_X$. First define the element $(M, f_{\setminus x}) \in \mathbf{G}_{X \setminus x}$ with the maps $f_{\setminus x} = (f_{\setminus x}^{\text{in}}, f_{\setminus x}^{\text{out}})$,

$$\begin{array}{ccc} M_v \times (X \setminus x)_v^{\text{in}} & \xrightarrow{f_{\setminus x}^{\text{in}}} & TM_v \\ & \searrow \text{project} & \downarrow \pi \\ & & M_v \end{array} \quad \begin{array}{c} M_v \\ \downarrow f_{\setminus x}^{\text{out}} \\ (X \setminus x)_v^{\text{out}} \end{array}$$

defined as follows. Given $\underline{m} \in M_v$ and

$$\underline{y} \in (X \setminus x)_v^{\text{in}} = \prod_{y \in X^{\text{in}} \setminus \{x^1, x^2\}} v(y)$$

we define

$$f_{\setminus x}^{\text{in}}(\underline{m}, \underline{y}) = f^{\text{in}}\left(\underline{m}; \left(f^{\text{out}}(\underline{m})_{\{x_+^1, x_+^2\}}, \underline{y}\right)\right) \in TM_v$$

$$f_{\setminus x}^{\text{out}}(\underline{m}) = f^{\text{out}}(\underline{m})_{\setminus \{x_+^1, x_+^2\}} \in (X \setminus x)_v^{\text{out}}.$$

Recalling that $f^{\text{out}}(\underline{m}) \in X_v^{\text{out}}$, the elements

$$f^{\text{out}}(\underline{m})_{\{x_+^1, x_+^2\}} \in v(x_+^1) \times v(x_+^2) = v(x_-^1) \times v(x_-^2)$$

and $f^{\text{out}}(\underline{m})_{\setminus \{x_+^1, x_+^2\}}$ are as in (6.7.2.2).

Now it follows from a direct inspection using the definition (6.7.6.4) that both composites in (6.7.7.1), when applied to (M, f) , yields $(M, f_{\setminus x}) \in G_{X \setminus x}$. This proves the generating axiom (6.7.7.1) for G . \square

Remark 6.7.8. Our definition of the algebra of open dynamical systems G actually agrees with the one in [VSL14] (Def. 4.4 and 4.5). To see this, note that among the four generating structure maps in Def. 6.7.6:

- ϵ (6.7.6.1), $\tau_{X,Y}$ (6.7.6.2), and $\lambda_{X,x}$ (6.7.6.4) agree with [VSL14] (Def. 4.4);
- $\theta_{X,Y}$ (6.7.6.3) agrees with [VSL14] (Def. 4.5).

Theorem 6.6.2 then implies that the two definitions of G —namely, the one in [VSL14] and our Def. 6.7.6—are equivalent.

Part 2

Undirected Wiring Diagrams

The main purpose of this part is to describe the combinatorial structure of the operad UWD of undirected wiring diagrams. The main result is a finite presentation theorem that describes the operad UWD in terms of 6 operadic generators and 17 generating relations.

The operad UWD of undirected wiring diagrams is recalled in Chapter 7. Operadic generators and generating relations for the operad UWD are presented in Chapter 8. Various decompositions of undirected wiring diagrams are given in Chapter 9. Using the results in Chapters 8 and 9, the finite presentation theorem for the operad UWD is proved in Chapter 10. The corresponding finite presentation theorem for UWD-algebras is discussed in Chapter 11. Also given in this chapter is a partial verification of a conjecture of Spivak about the relational algebra.

Undirected Wiring Diagrams

The purposes of this chapter are

- (1) to recall the definition of an undirected wiring diagram (Def. 7.1.3) from [Spi13];
- (2) to give a proof that the collection of undirected wiring diagrams forms an operad (Theorem 7.3.11).

There is a subtlety regarding the definition and the operadic composition of undirected wiring diagrams; see Remark 7.1.4(3) and Example 7.3.7. Many more examples of undirected wiring diagrams and their operadic composition will be given in the next chapter.

Fix a class S for this chapter.

7.1. Defining Undirected Wiring Diagrams

In this section, we recall the definition of an undirected wiring diagram. Recall from Def. 2.2.3 that an S -finite set is a pair (X, v) with X a finite set and $v : X \rightarrow S$ a function, called the *value assignment*. Maps between S -finite sets are functions compatible with the value assignments. The category of S -finite sets is denoted by Fin_S . As in earlier chapters, if there is no danger of confusion, then we write an S -finite set (X, v) simply as X . The number of elements in a finite set T is denoted by $|T|$.

As in Section 2.2 we first define undirected prewiring diagrams. Undirected wiring diagrams are then defined as the appropriate equivalence classes. The following definition is a slight generalization of [Spi13] (Examples 2.1.7 and 4.1.1); see Remark 7.1.4. The reader may want to go to (7.1.6.1) to see a concrete example of an undirected wiring diagram before reading the following definition.

Definition 7.1.1. Suppose S is a class. An *undirected S -prewiring diagram* is a tuple

$$\varphi = (\underline{X}, Y, C, f, g) \quad (7.1.1.1)$$

consisting of the following data.

- (1) $Y \in \text{Fin}_S$, called the *output box* of φ . An element in Y is called an *output wire* for φ .
- (2) $\underline{X} = (X_1, \dots, X_n)$ is a Fin_S -profile for some $n \geq 0$ (Def. 2.1.1); i.e., each $X_i \in \text{Fin}_S$.
 - We call X_i the *i th input box* of φ .
 - An element in each X_i is called an *input wire* for φ .
 - Denote by $X = \coprod_{i=1}^n X_i \in \text{Fin}_S$ the coproduct.
 - Each element in $X \sqcup Y$ is called a *wire*.
- (3) $C \in \text{Fin}_S$, called the *set of cables* of φ . Each element in C is called a *cable*.
- (4) f and g are maps in the diagram, called a *cospan*

$$X_1 \sqcup \dots \sqcup X_n = X \xrightarrow{f} C \xleftarrow{g} Y \quad (7.1.1.2)$$

in Fin_S .

- f is called the *input soldering function* and g the *output soldering function*.
- If $f(x) = c$, then we say that x is *soldered to c* and that c is *soldered to x* via f . If $g(y) = c$, then we say that y is *soldered to c* and that c is *soldered to y* via g .
- If $c \in C$ is a cable and if $m = |f^{-1}(c)|$ and $n = |g^{-1}(c)|$, then c is called an *(m, n) -cable*.
- A $(0, 0)$ -cable is also called a *wasted cable*. In other words, a wasted cable is a cable that is in neither the image of f nor the image of g .

Given Y and \underline{X} , we will denote φ as either the tuple (C, f, g) or the cospan (7.1.1.2).

Remark 7.1.2. In Def. 2.2.4 an S -box is an element in $\text{Fin}_S \times \text{Fin}_S$. In the context of undirected (pre)wiring diagrams, the name *box* refers to an element in Fin_S , such as the output box or one of the input boxes. The context itself should make it clear what box means.

The cables tell us how to wire the input wires and the output wires together. So the names of the cables should not matter. This is made precise in the following definition.

Definition 7.1.3. Suppose $\varphi = (\underline{X}, Y, C, f, g)$ and $\varphi' = (\underline{X}, Y, C', f', g')$ are two undirected S -prewiring diagrams with the same output box Y and input boxes \underline{X} .

- (1) An *equivalence* $h : \varphi \longrightarrow \varphi'$ is an isomorphism $h : C \longrightarrow C' \in \text{Fin}_S$ such that the diagram

$$\begin{array}{ccccc} X & \xrightarrow{f} & C & \xleftarrow{g} & Y \\ & \searrow & \downarrow h & \swarrow & \\ & f' & C' & g' & \end{array}$$

in Fin_S is commutative.

- (2) We say that φ and φ' are *equivalent* if there exists an equivalence $\varphi \longrightarrow \varphi'$.
- (3) An *undirected S -wiring diagram* is an equivalence class of undirected S -prewiring diagrams. If S is clear from the context, we will drop S and just say *undirected wiring diagram*.
- (4) The class of undirected S -wiring diagrams with output box Y and input boxes $\underline{X} = (X_1, \dots, X_n)$ is denoted by

$$\text{UWD}(\underline{X}^Y) \quad \text{or} \quad \text{UWD}_{(X_1, \dots, X_n)}^Y. \quad (7.1.3.1)$$

The class of all undirected S -wiring diagrams is denoted by UWD . If we want to emphasize the class S , we will write UWD^S .

Remark 7.1.4. Consider Def. 7.1.1 and 7.1.3.

- (1) If $S = \{*\}$, a one-point set, then what we call an undirected $\{*\}$ -wiring diagram is called a *singly-typed wiring diagram* in [Spi13] (Example 2.1.7).
- (2) If $S = \text{Set}$, the collection of sets, then what we call an undirected Set -wiring diagram is called a *typed wiring diagram* in [Spi13] (Example 4.1.1).
- (3) In the book [Spi14] (p.464) Spivak's definition of an undirected $\{*\}$ -wiring diagram is slightly different from ours. More precisely, Spivak insisted that the maps (f, g) in the cospan (7.1.1.2) be *jointly surjective*, meaning that there are no wasted cables. However, we point out that joint surjectivity is inconsistent with the operad structure in UWD , to be defined in Section 7.3. In other words, while individual undirected wiring diagrams may have no wasted cables, the operadic composition can actually create wasted cables. So there is no such thing as the operad of undirected wiring diagrams without wasted cables. In Example 7.3.7 and Section 8.3 we will illustrate that the operadic composition of undirected wiring diagrams without wasted cables can have wasted cables.
- (4) Cospans (7.1.1.2) are also used in other work about processes and networks. For example, cospans in a category, rather than just Fin_S , are used

in [Fon15]. That setting is then used in [BF15, BFP15] to study passive linear networks and Markov processes.

Convention 7.1.5. To simplify the presentation, we usually suppress the difference between an undirected prewiring diagram and an undirected wiring diagram. Each undirected wiring diagram $\varphi = (\underline{X}, Y, C, f, g)$ has a unique representative in which:

- each cable is an element in S ;
- the value assignment $v : C \longrightarrow S$ sends each cable to itself.

Unless otherwise specified, we will always use this representative of an undirected wiring diagram.

Example 7.1.6. Suppose S is any class. Consider the undirected wiring diagram $\varphi \in \text{UWD}_{(X_1, X_2)}^Y$ defined as follows.

- The input boxes are $X_1 = \{x_1, x_2, x_3, x_4, x_5, x_6\}$ and $X_2 = \{x^1, x^2\} \in \text{Fin}_S$.
- The output box is $Y = \{y_1, y_2, y_3, y_4, y_5, y_6\} \in \text{Fin}_S$.
- The set of cables is $C = \{c_1, c_2, c_3, c_4, c_5, c_6, c_7\} \in \text{Fin}_S$.

Their value assignments satisfied the following conditions:

- $v(c_1) = v(y_1) = v(y_2) \in S$.
- $v(c_2) = v(x_1) = v(y_3) \in S$.
- $v(c_3) = v(x_2) = v(x_3) = v(x^1) = v(y_4) = v(y_5) \in S$.
- $v(c_4) \in S$ is arbitrary.
- $v(c_5) = v(y_6) \in S$.
- $v(c_6) = v(x_4) = v(x_5) = v(x^2) \in S$.
- $v(c_7) = v(x_6) \in S$.

The input and the output soldering functions


$$X_1 \sqcup X_2 \xrightarrow{f} C \xleftarrow{g} Y$$

are defined as follows:

- $c_1 = g(y_1) = g(y_2)$ is a $(0, 2)$ -cable.
- $c_2 = f(x_1) = g(y_3)$ is a $(1, 1)$ -cable.
- $c_3 = f(x_2) = f(x_3) = f(x^1) = g(y_4) = g(y_5)$ is a $(3, 2)$ -cable.
- c_4 is a $(0, 0)$ -cable, i.e., a wasted cable.
- $c_5 = g(y_6)$ is a $(0, 1)$ -cable.

- $c_6 = f(x_4) = f(x_5) = f(x^2)$ is a $(3,0)$ -cable.
- $c_7 = f(x_6)$ is a $(1,0)$ -cable.

Graphically we represent this undirected wiring diagram $\varphi \in \text{UWD}_{(X_1, X_2)}^Y$ as follows.



The input boxes $X_1 = \{x_1, \dots, x_6\}$ and $X_2 = \{x^1, x^2\}$ are drawn as the smaller boxes inside. The output box $Y = \{y_1, \dots, y_6\}$ is drawn as the outer rectangle. Each element within each box is drawn along the boundary, either just inside (as in X_1 and X_2) or just outside (as in Y). Note that no orientation is attached to the sides of these squares and rectangles. For example, we could have drawn $y_6 \in Y$ on the bottom side of the outer rectangle. Each cable $c_i \in C$ is drawn as a small gray disk, which is not to be confused with a delay node in a wiring diagram (such as d in (2.2.14.1)). The soldering functions f and g tell us how to connect the wires in $X = X_1 \sqcup X_2$ and Y to the cables. We will revisit this example in Example 9.1.2 below.

7.2. Pushouts

The operadic composition on the collection of undirected wiring diagrams UWD (Def. 7.1.3) involves the basic categorical concept of a pushout, which we recall in this section. The reader may consult [Awo10] (5.6) and [Mac98] (p.65-66) for more discussion of pushouts. Roughly speaking, a pushout is a way of summing two objects with some identification. We will only use the following definition when the category is Fin_S (Def. 2.2.3), so the reader may simply take the category \mathcal{C} below to be Fin_S and objects and maps to be those in Fin_S .

Definition 7.2.1. Suppose \mathcal{C} is a category (Def. 2.2.1), and

$$Y \xleftarrow{f} X \xrightarrow{g} Z \tag{7.2.1.1}$$

is a diagram in \mathcal{C} . Then a *pushout* of this diagram is a tuple (W, α, β) consisting of an object $W \in \mathcal{C}$ and maps $\alpha : Y \rightarrow W$ and $\beta : Z \rightarrow W$ in \mathcal{C} such that the following two conditions hold.

(1) The square

$$\begin{array}{ccc} X & \xrightarrow{g} & Z \\ f \downarrow & & \downarrow \beta \\ Y & \xrightarrow{\alpha} & W \end{array}$$

in \mathcal{C} is commutative, i.e., $\alpha f = \beta g$.

(2) Suppose (W', α', β') is another such tuple, i.e., $\alpha' f = \beta' g$. Then there exists a unique map $h : W \rightarrow W'$ in \mathcal{C} such that the diagram

$$\begin{array}{ccc} X & \xrightarrow{g} & Z \\ f \downarrow & & \downarrow \beta \\ Y & \xrightarrow{\alpha} & W \\ & & \searrow h \\ & & W' \end{array} \quad \begin{array}{l} \nearrow \beta' \\ \nearrow \alpha' \end{array} \quad (7.2.1.2)$$

in \mathcal{C} is commutative, i.e., $\alpha' = h\alpha$ and $\beta' = h\beta$.

If a pushout exists, then by definition it is unique up to unique isomorphisms. In a general category, a pushout may not exist for a diagram of the form (7.2.1.1). Even if it exists, it may be difficult to describe. Luckily, for S -finite sets (Def. 2.2.3), pushouts always exist and are easy to describe, as the following observation shows.

Proposition 7.2.2. *In the category Fin_S of S -finite sets, each diagram of the form (7.2.1.1) has a pushout given by the quotient*

$$W = \frac{Y \sqcup Z}{\{f(x) = g(x) : x \in X\}} \quad (7.2.2.1)$$

taken in Fin_S .

Proof. The maps $\alpha : Y \rightarrow W$ and $\beta : Z \rightarrow W$ are the obvious maps, each being the inclusion into $Y \sqcup Z$ followed by the quotient map to W . Then the tuple (W, α, β) has the required universal property of a pushout in Fin_S . \square

Example 7.2.3. A commutative square with opposite identity maps is a pushout square. In other words, a pushout of the diagram

$$X \xleftarrow{=} X \xrightarrow{g} Z$$

in any category is given by the commutative square

$$\begin{array}{ccc} X & \xrightarrow{g} & Z \\ = \downarrow & & \downarrow = \\ X & \xrightarrow{g} & Z \end{array}$$

as can be checked by a direct inspection.

7.3. Operad Structure

Fix a class S . In this section we define the Fin_S -colored operad structure (Def. 2.1.4) on the collection of undirected wiring diagrams UWD (Def. 7.1.3). When S is either $\{*\}$ or the collection of sets, this operad structure on UWD was first introduced in [Spi13] using the structure map γ (2.1.2.2).


Definition 7.3.1 (Equivariance in UWD). Suppose $Y \in \text{Fin}_S$, $\underline{X} = (X_1, \dots, X_n)$ is a Fin_S -profile of length n , and $\sigma \in \Sigma_n$ is a permutation. Define the function

$$\text{UWD}_{(X_1, \dots, X_n)}^Y = \text{UWD}_{(\underline{X})}^Y \xrightarrow[\cong]{\sigma} \text{UWD}_{(\underline{X}\sigma)}^Y = \text{UWD}_{(X_{\sigma(1)}, \dots, X_{\sigma(n)})}^Y \quad (7.3.1.1)$$

by sending $\varphi = (C, f, g) \in \text{UWD}_{(\underline{X})}^Y$ to $\varphi = (C, f, g) \in \text{UWD}_{(\underline{X}\sigma)}^Y$, using the fact that $\coprod_{i=1}^n X_i = \coprod_{i=1}^n X_{\sigma(i)}$.

In other words, the equivariant structure in UWD simply relabels the input boxes.


Next we define the colored units in UWD . The Y -colored unit in UWD , for $Y \in \text{Fin}_S$, may be depicted as follows.



Definition 7.3.2 (Units in UWD). For each $Y \in \text{Fin}_S$, the Y -colored unit is defined as the undirected wiring diagram

$$\mathbb{1}_Y = \left(Y \xrightarrow{=} Y \xleftarrow{=} Y \right) \in \text{UWD}_{(Y)}^Y. \quad (7.3.2.1)$$

Next we define the \circ_i -composition in UWD . The operadic composition $\varphi \circ_i \psi$ can be visualized in the following picture.



$$(7.3.2.2)$$

Intuitively, to form the operadic composition $\varphi \circ_i \psi$ in UWD, we replace the i th input box X_i in φ by the input boxes in ψ . The set of cables in ψ is added to the set of cables in φ , with appropriate identification from the input and the output soldering functions in φ and ψ .

The following notation will be useful in the definition of the \circ_i -composition.

Notation 7.3.3. Suppose $\underline{X} = (X_1, \dots, X_n)$ is a Fin_S -profile.

- (1) Write $X = X_1 \sqcup \dots \sqcup X_n \in \text{Fin}_S$.
- (2) For integers i and j , define

$$X_{[i,j]} = \begin{cases} X_i \sqcup \dots \sqcup X_j & \text{if } 1 \leq i \leq j \leq n; \\ \emptyset & \text{otherwise.} \end{cases} \quad (7.3.3.1)$$

Definition 7.3.4 (\circ_i -Composition in UWD). Suppose:

- $\varphi = \left\{ X \xrightarrow{f_\varphi} C_\varphi \xleftarrow{g_\varphi} Y \right\} \in \text{UWD}(\underline{X})$ with $\underline{X} = (X_1, \dots, X_n)$, $n \geq 1$, and $1 \leq i \leq n$;
- $\psi = \left\{ W \xrightarrow{f_\psi} C_\psi \xleftarrow{g_\psi} X_i \right\} \in \text{UWD}(\underline{X}_i)$ with $|W| = m \geq 0$.

Define the undirected wiring diagram

$$\varphi \circ_i \psi = (C, f, g) \in \text{UWD}(\underline{X} \circ_i \underline{W})$$

as the cospan

$$\begin{array}{ccc} & & Y \\ & & \downarrow g_\varphi \\ & X_1 \sqcup \dots \sqcup X_n & \xrightarrow{f_\varphi} C_\varphi \\ & \downarrow (\text{Id}, g_\psi, \text{Id}) & \downarrow \\ X_{[1,i-1]} \sqcup W \sqcup X_{[i+1,n]} & \xrightarrow{(\text{Id}, f_\psi, \text{Id})} X_{[1,i-1]} \sqcup C_\psi \sqcup X_{[i+1,n]} & \xrightarrow{f} C \\ & & \uparrow g \end{array} \quad (7.3.4.1)$$

in Fin_S . Here:

- The square is a pushout in Fin_S , which always exists by Prop. 7.2.2.
- The S -finite sets W , $X_{[1,i-1]}$, and $X_{[i+1,n]}$ are as in Notation 7.3.3.
- The Fin_S -profile

$$\underline{X} \circ_i \underline{W} = (X_1, \dots, X_{i-1}, \underline{W}, X_{i+1}, \dots, X_n)$$

is as in (2.1.4.2).

- The map f is the bottom horizontal composition, and the map g is the right vertical composition.

In the following observation, we describe the undirected wiring diagram $\varphi \circ_i \psi$ more explicitly.

Proposition 7.3.5. *Consider the diagram (7.3.4.1).*

- (1) *A choice of a pushout C is the quotient*

$$C = \frac{C_\varphi \sqcup C_\psi}{\{f_\varphi(x) = g_\psi(x) : x \in X_i\}} \quad (7.3.5.1)$$

in Fin_S . The following statements use this choice of C .

- (2) *The maps $C_\varphi \longrightarrow C$ and $C_\psi \longrightarrow C$ are the obvious maps, each being the inclusion into $C_\varphi \sqcup C_\psi$ followed by the quotient map to C .*
- (3) *In the map f and in the horizontal unnamed map, for $j \neq i$, the map $X_j \longrightarrow C$ is the composition*

$$X_j \xrightarrow{f_\varphi} C_\varphi \longrightarrow C .$$

- (4) *On W the map f is the composition*

$$W \xrightarrow{f_\psi} C_\psi \longrightarrow C .$$

Proof. A direct inspection shows that the first three statements indeed describe a pushout of the square in the diagram (7.3.4.1). The last assertion follows from the definition of f as the bottom horizontal composition. \square

Remark 7.3.6. Consider Def. 7.3.4.


- (1) Pushouts are unique up to unique isomorphisms. Since undirected wiring diagrams are defined as equivalence classes of undirected prewiring diagrams (Def. 7.1.3), the undirected wiring diagram $\varphi \circ_i \psi$ is well-defined.
- (2) In [Spi13] S was taken to be either the one-point set or the collection of sets. The operadic composition in UWD was defined in terms of the operadic composition γ (2.1.2.2). By Prop. 2.1.6 the two descriptions—i.e., the one in [Spi13] and Def. 7.3.4—are equivalent.

Recall from Def. 7.1.1 that a *wasted cable* in an undirected wiring diagram is a cable that is not in the image of the input and the output soldering functions.


Example 7.3.7. In this example, we observe that wasted cables can be created by the \circ_i -composition, even if the original undirected wiring diagrams have no wasted cables. Suppose:

- $S = \{*\}$ and $X = \{x_1, x_2\} \in \text{Fin}$ is a two-element set.
- $\varphi = \{ X \longrightarrow \{*\} \longleftarrow \emptyset \} \in \text{UWD}(\emptyset^X)$.
- $\psi = \{ \emptyset \longrightarrow X \longleftarrow^= X \} \in \text{UWD}(\emptyset^X)$.

Note that neither φ nor ψ has a wasted cable. On the other hand, the undirected wiring diagram $\varphi \circ_1 \psi \in \text{UWD}(\emptyset^{\emptyset})$ is the cospan



in Fin , in which the square is a pushout by Example 7.2.3. The following picture gives a visualization of this \circ_1 -composition.




In particular, the unique cable in $\varphi \circ_1 \psi$ is a wasted cable. This example illustrates that the \circ_i -composition of two undirected wiring diagrams without wasted cables may have wasted cables. We will revisit this example in Section 8.3 and Example 10.1.4 below.

We now prove that the collection UWD of undirected wiring diagrams is a Fin_S -colored operad in the sense of Def. 2.1.4.

Lemma 7.3.8. *The \circ_i -composition in Def. 7.3.4 satisfies the left unity axiom (2.1.4.5), the right unity axiom (2.1.4.6), and the equivariance axiom (2.1.4.7).*

Proof. The equivariance axiom holds because the equivariant structure (7.3.1) simply relabels the input boxes. The unity axioms follow from the definitions of the colored units in UWD (7.3.2.1) and Example 7.2.3. □

The horizontal associativity axiom in UWD may be visualized as follows.



To keep the picture simple, we omitted drawing the wires and the cables. Note that this is basically the undirected version of the picture (2.3.5.1).

Lemma 7.3.9. *The \circ_i -composition in Def. 7.3.4 satisfies the horizontal associativity axiom (2.1.4.3).*

Proof. Suppose:

- $\varphi = (C_\varphi, f_\varphi, g_\varphi) \in \text{UWD}(\underline{Z})$ with $|\underline{Y}| = n \geq 2$ and $1 \leq i < j \leq n$;
- $\psi = (C_\psi, f_\psi, g_\psi) \in \text{UWD}(\underline{Y}_i)$ with $|\underline{W}| = l$;
- $\zeta = (C_\zeta, f_\zeta, g_\zeta) \in \text{UWD}(\underline{Y}_j)$ with $|\underline{X}| = m$.

We must show that

$$(\varphi \circ_j \zeta) \circ_i \psi = (\varphi \circ_i \psi) \circ_{j-1+l} \zeta \in \text{UWD}(\underline{(Y \circ_i X) \circ_j W}). \quad (7.3.9.1)$$

Consider the undirected wiring diagram

$$(C, f, g) \in \text{UWD}(\underline{(Y \circ_i X) \circ_j W})$$

given by the cospan

$$Y_{[1, i-1]} \sqcup W \sqcup Y_{[i+1, j-1]} \sqcup X \sqcup Y_{[j+1, n]} \xrightarrow{f} C \xleftarrow{g} Z$$

in Fin_S , where Notation 7.3.3 was used. In this cospan:

- The set of cables is the quotient


$$C = \frac{C_\varphi \sqcup C_\psi \sqcup C_\zeta}{\{f_\varphi(y_i) = g_\psi(y_i), f_\varphi(y_j) = g_\zeta(y_j) : y_i \in Y_i, y_j \in Y_j\}}.$$

- The output soldering function g is the composition $Z \xrightarrow{g_\varphi} C_\varphi \longrightarrow C$.
- For the input soldering function f :

- The restriction to Y_k is the composition $Y_k \xrightarrow{f_\varphi} C_\varphi \longrightarrow C$ for $k \neq i, j$.
- The restriction to W is the composition $W \xrightarrow{f_\psi} C_\psi \longrightarrow C$.
- The restriction to X is the composition $X \xrightarrow{f_\zeta} C_\zeta \longrightarrow C$.

Using the description of \circ_i in Prop. 7.3.5, a direct inspection reveals that both sides of (7.3.9.1) are equal to (C, f, g) . \square

The vertical associativity axiom in UWD may be visualized as follows.



As before, to keep the picture simple, we did not draw the wires and the cables. Note that this is basically the undirected version of the picture (2.3.6.2).

Lemma 7.3.10. *The \circ_i -composition in Def. 7.3.4 satisfies the vertical associativity axiom (2.1.4.4).*

Proof. Suppose:

- $\varphi = (C_\varphi, f_\varphi, g_\varphi) \in \text{UWD}(\underline{Z})$ with $|\underline{Y}| = n \geq 1$ and $1 \leq i \leq n$;
- $\psi = (C_\psi, f_\psi, g_\psi) \in \text{UWD}(\underline{X})$ with $|\underline{X}| = m \geq 1$ and $1 \leq j \leq m$;
- $\zeta = (C_\zeta, f_\zeta, g_\zeta) \in \text{UWD}(\underline{W})$ with $|\underline{W}| = l$.

We must show that

$$(\varphi \circ_i \psi) \circ_{i-1+j} \zeta = \varphi \circ_i (\psi \circ_j \zeta) \in \text{UWD}(\underline{(Y \circ_i X)^Z}_{(Y \circ_i X)^{\circ_{i-1+j}} W}). \quad (7.3.10.1)$$

Consider the undirected wiring diagram

$$(C, f, g) \in \text{UWD}(\underline{(Y \circ_i X)^Z}_{(Y \circ_i X)^{\circ_{i-1+j}} W})$$

given by the cospan

$$Y_{[1,i-1]} \sqcup X_{[1,j-1]} \sqcup W \sqcup X_{[j+1,m]} \sqcup Y_{[i+1,n]} \xrightarrow{f} C \xleftarrow{g} Z$$

in Fin_S , where Notation 7.3.3 was used. In this cospan:

- The set of cables is the quotient

$$C = \frac{C_\varphi \sqcup C_\psi \sqcup C_\zeta}{\{f_\varphi(y) = g_\psi(y), f_\psi(x) = g_\zeta(x) : y \in Y_i, x \in X_j\}}.$$

- The output soldering function g is the composition $Z \xrightarrow{g_\varphi} C_\varphi \longrightarrow C$.
- For the input soldering function f :
 - The restriction to Y_l is the composition $Y_l \xrightarrow{f_\varphi} C_\varphi \longrightarrow C$ for $l \neq i$.
 - The restriction to X_k is the composition $X_k \xrightarrow{f_\psi} C_\psi \longrightarrow C$ for $k \neq j$.
 - The restriction to W is the composition $W \xrightarrow{f_\zeta} C_\zeta \longrightarrow C$.

Using the description of \circ_i in Prop. 7.3.5, a direct inspection reveals that both sides of (7.3.10.1) are equal to (C, f, g) . \square

Theorem 7.3.11. *For any class S , when equipped with the structure in Def. 7.3.1–7.3.4, UWD in Def. 7.1.3 is a Fin_S -colored operad, called the operad of undirected wiring diagrams.*

Proof. In view of Def. 2.1.4, this follows from Lemmas 7.3.8, 7.3.9, and 7.3.10. \square

Example 7.3.12. Consider Theorem 7.3.11.

- (1) If $S = \{*\}$, a one-point set, then our Fin -colored operad UWD is called the operad of singly-typed wiring diagrams in [Spi13] (Example 2.1.7).
- (2) If $S = \text{Set}$, the collection of sets, then our Fin_{Set} -colored operad UWD is called the operad of typed wiring diagrams in [Spi13] (Example 4.1.1).

We defined the operad UWD in terms of the \circ_i -compositions (Def. 7.3.4). The following observation expresses the operad UWD in terms of the operadic composition γ (2.1.2.2). In [Spi13] the operad structure on undirected wiring diagrams was actually defined in terms of γ .

Proposition 7.3.13. *Suppose:*

- $\varphi = (C_\varphi, f_\varphi, g_\varphi) \in \text{UWD}(\underline{Y})$ with $\underline{X} = (X_1, \dots, X_n)$ for some $n \geq 1$ and $X = X_1 \sqcup \dots \sqcup X_n$.

- For each $1 \leq i \leq n$, $\psi_i = (C_i, f_i, g_i) \in \text{UWD}(\frac{X_i}{W_i})$ with $\underline{W}_i = (W_{i,1}, \dots, W_{i,k_i})$ for some $k_i \geq 0$.
- $\underline{W} = (\underline{W}_1, \dots, \underline{W}_n)$, $W_i = W_{i,1} \sqcup \dots \sqcup W_{i,k_i}$, and $W = \coprod_{1 \leq i \leq n} W_i$.

Then

$$\gamma(\varphi; \psi_1, \dots, \psi_n) = (C, f, g) \in \text{UWD}(\frac{Y}{W})$$

is given by the cospan

$$\begin{array}{ccccc}
 & & & & Y \\
 & & & & \downarrow g_\varphi \\
 & & X & \xrightarrow{f_\varphi} & C_\varphi \\
 & & \downarrow \sqcup g_i & & \downarrow \\
 W & \xrightarrow{\sqcup f_i} & C_1 \sqcup \dots \sqcup C_n & \longrightarrow & C \\
 & & & & \uparrow g \\
 & & & & Y
 \end{array}
 \tag{7.3.13.1}$$

in Fin_S , in which the square is a pushout. In this diagram:

- (1) C is the quotient

$$C = \frac{C_\varphi \sqcup C_1 \sqcup \dots \sqcup C_n}{\{f_\varphi(x) = g_i(x) : x \in X_i, 1 \leq i \leq n\}}$$

in Fin_S .

- (2) The maps $C_\varphi \longrightarrow C$ and $C_i \longrightarrow C$ are the obvious maps, each being an inclusion followed by a quotient map to C .
- (3) The restriction of f to W_i is the composition of $f_i : W_i \longrightarrow C_i$ and $C_i \longrightarrow C$.

Proof. This follows from (i) the correspondence (2.1.6.1) between γ and the \circ_i -compositions and (ii) the description of \circ_i given in Proposition 7.3.5. \square

Generators and Relations

Fix a class S , and consider the Fin_S -colored operad UWD of undirected wiring diagrams (Theorem 7.3.11). The purpose of this chapter is to describe a finite number of undirected wiring diagrams that we will later show to be sufficient to describe the entire operad UWD. One may also regard this chapter as consisting of a long list of examples of undirected wiring diagrams.

In Section 8.1 we describe 6 undirected wiring diagrams, called the *generating undirected wiring diagrams*. Later we will show that they generate the operad UWD of undirected wiring diagrams. This means that every undirected wiring diagram can be obtained from finitely many generating undirected wiring diagrams via iterated operadic compositions. For now one may think of the generating undirected wiring diagrams as examples of undirected wiring diagrams.

In Section 8.2 we describe 17 *elementary relations* among the generating undirected wiring diagrams. Later we will show that these elementary relations together with the operad associativity and unity axioms—(2.1.4.3), (2.1.4.4), (2.1.4.5), and (2.1.4.6)—for the generating undirected wiring diagrams generate *all* the relations in the operad UWD of undirected wiring diagrams. In other words, suppose an arbitrary undirected wiring diagram can be built in two ways using the generating undirected wiring diagrams. Then there exists a finite sequence of steps connecting them in which each step is given by one of the 17 elementary relations or an operad associativity/unity axiom for the generating undirected wiring diagrams. For now one may think of the elementary relations as examples of the operadic composition in the operad UWD.

8.1. Generating Undirected Wiring Diagrams

Recall the definition of an undirected wiring diagram (Def. 7.1.3). In this section, we introduce 6 undirected wiring diagrams, called the generating undirected wiring diagrams. They will be used in later chapters to give a finite presentation for the operad UWD of undirected wiring diagrams. The undirected wiring diagrams in this section all have directed analogues in Section 3.1.


The following undirected wiring diagram is an undirected analogue of the empty wiring diagram (Def. 3.1.1).

Definition 8.1.1. Define the *empty cell*

$$\epsilon = \left(\emptyset \longrightarrow \emptyset \longleftarrow \emptyset \right) \in \text{UWD}(\emptyset),$$

where \emptyset is the empty S -finite set. Note that the empty cell is a 0-ary element in UWD.

Next we define the undirected wiring diagram




with no input boxes and whose unique cable is a $(0, 1)$ -cable. This is an undirected analogue of a 1-wasted wire (Def. 3.1.8). To simplify the typography, we will often write x for the one-point set $\{x\}$.

Definition 8.1.2. Suppose $*$ \in Fin_S is a one-element S -finite set. Define the *1-output wire*

$$\omega_* = \left(\emptyset \longrightarrow * \longleftarrow * \right) \in \text{UWD}(*).$$

Note that a 1-output wire is a 0-ary element in UWD.

Next we define the undirected wiring diagram




with 1 input box and whose cables are all $(1, 1)$ -cables. This is an undirected analogue of a name change (Def. 3.1.3).

Definition 8.1.3. Suppose $f : X \longrightarrow Y \in \text{Fin}_S$ is a bijection. Define the *undirected name change*

$$\tau_f = \left(X \xrightarrow[\cong]{f} Y \longleftarrow Y \right) \in \text{UWD}(Y).$$

If the bijection f is clear from the context, then we write τ_f as $\tau_{X,Y}$ or just τ . If there is no danger of confusion, then we will call τ_f a *name change*.

Next we define the undirected wiring diagram




with 2 input boxes and whose cables are all $(1,1)$ -cables. This is an undirected analogue of a 2-cell (Def. 3.1.4).

Definition 8.1.4. Suppose $X, Y \in \text{Fin}_S$ and $X \sqcup Y$ is their coproduct. Define the *undirected 2-cell*

$$\theta_{(X,Y)} = \left(X \sqcup Y \xrightarrow{=} X \sqcup Y \xleftarrow{=} X \sqcup Y \right) \in \text{UWD}^{(X \sqcup Y)}_{(X,Y)}.$$

If there is no danger of confusion, then we will call it a 2-cell.

Next we define the undirected wiring diagram



with a $(2,0)$ -cable, all other cables being $(1,1)$ -cables. This is an undirected analogue of a 1-loop (Def. 3.1.5).


Definition 8.1.5. Suppose:

- $X \in \text{Fin}_S$, and $x_+, x_- \in X$ are two distinct elements with $v(x_+) = v(x_-) \in S$.
- $X \setminus x_{\pm} \in \text{Fin}_S$ is obtained from X by removing x_+ and x_- .
- $X/(x_+ = x_-) \in \text{Fin}_S$ is the quotient of X with x_+ and x_- identified.

Define the *loop*

$$\lambda_{(X,x_{\pm})} = \left(X \xrightarrow{\text{projection}} \frac{X}{(x_+=x_-)} \xleftarrow{\text{inclusion}} X \setminus x_{\pm} \right) \in \text{UWD}^{(X \setminus x_{\pm})}_{(X)}.$$

Next we define the undirected wiring diagram



with a (1,2)-cable, all other cables being (1,1)-cables. This is an undirected analogue of an out-split (Def. 3.1.7).

Definition 8.1.6. Suppose:

- $X \in \text{Fin}_S$, and x_1, x_2 are two distinct elements in X with $v(x_1) = v(x_2) \in S$.
- $X' \in \text{Fin}_S$, and $x \in X'$ such that $v(x) = v(x_1)$ and that $X' \setminus \{x\} = X \setminus \{x_1, x_2\}$.

Define the *split*

$$\sigma^{(X, x_1, x_2)} = \left(X' \xrightarrow{=} X' \longleftarrow X \right) \in \text{UWD}\left(\frac{X}{X'}\right)$$

in which the output soldering function $X \longrightarrow X'$ sends $x_1, x_2 \in X$ to $x \in X'$ and is the identity function on $X \setminus \{x_1, x_2\}$.

Definition 8.1.7. The 6 undirected wiring diagrams in Def. 8.1.1–8.1.6 will be referred to as *generating undirected wiring diagrams*. If the context is clear, we will simply call them *generators*.

Remark 8.1.8. Among the generating undirected wiring diagrams:

- (1) None has a wasted cable (Def. 7.1.1). As we will see in Section 8.3, wasted cables can be created by the generators.
- (2) The empty cell ϵ (Def. 8.1.1) and a 1-output wire ω_* (Def. 8.1.2) are 0-ary elements in UWD.
- (3) A name change τ (Def. 8.1.3), a loop $\lambda_{(X, x_\pm)}$ (Def. 8.1.5), and a split $\sigma^{(X, x^1, x^2)}$ (Def. 8.1.6) are unary elements in UWD.
- (4) A 2-cell $\theta_{(X, Y)}$ (Def. 8.1.4) is a binary element in UWD.

8.2. Elementary Relations

The purpose of this section is to introduce 17 elementary relations among the generating undirected wiring diagrams (Def. 8.1.7). Each elementary relation is proved using Prop. 7.3.5 and Example 7.2.3 and by a simple inspection of the relevant definitions of the generating undirected wiring diagrams and operadic compositions. Each proof is similar to Example 7.3.7 and the proofs of Lemma 7.3.9 and Lemma 7.3.10. Therefore, we will omit the proofs, providing a picture instead in most cases. Some, but not all, of the following relations have directed analogues in Section 3.3.

Recall the operadic composition in the Fin_S -colored operad UWD (Def. 7.3.4) and Notation 3.3.1 for (iterated) \circ_1 . The first five relations are about name changes (Def. 8.1.3). The first one says that two consecutive name changes can be composed down into one name change.

Proposition 8.2.1. *Suppose:*

- $f : X \longrightarrow Y$ and $g : Y \longrightarrow Z \in \text{Fin}_S$ are bijections.
- $\tau_f \in \text{UWD}(\overset{Y}{\underset{X}{\square}})$, $\tau_g \in \text{UWD}(\overset{Z}{\underset{Y}{\square}})$, and $\tau_{gf} \in \text{UWD}(\overset{Z}{\underset{X}{\square}})$ are the corresponding name changes.

Then

$$\tau_g \circ \tau_f = \tau_{gf} \in \text{UWD}(\overset{Z}{\underset{X}{\square}}). \quad (8.2.1.1)$$

The next relation says that a name change of a 1-output wire (Def. 8.1.2) is again a 1-output wire.

Proposition 8.2.2. *Suppose:*

- $X = \{x\}$ and $Y = \{y\}$ are two 1-element S -finite sets with $v(x) = v(y) \in S$.
- $\omega_x \in \text{UWD}(\overset{x}{\square})$ and $\omega_y \in \text{UWD}(\overset{y}{\square})$ are the corresponding 1-output wires.
- $\tau_{X,Y} \in \text{UWD}(\overset{Y}{\underset{X}{\square}})$ is the name change corresponding to the bijection $X \longrightarrow Y \in \text{Fin}_S$.

Then

$$\tau_{X,Y} \circ \omega_x = \omega_y \in \text{UWD}(\overset{y}{\square}). \quad (8.2.2.1)$$

The next relation says that name changes inside a 2-cell (Def. 8.1.4) can be rewritten as a name change of a 2-cell.

Proposition 8.2.3. *Suppose:*

- $f_1 : X_1 \longrightarrow Y_1$ and $f_2 : X_2 \longrightarrow Y_2 \in \text{Fin}_S$ are bijections.
- $f_1 \sqcup f_2 : X_1 \sqcup X_2 \longrightarrow Y_1 \sqcup Y_2 \in \text{Fin}_S$ is their coproduct.
- $\tau_{f_1} \in \text{UWD}(\overset{Y_1}{\underset{X_1}{\square}})$, $\tau_{f_2} \in \text{UWD}(\overset{Y_2}{\underset{X_2}{\square}})$, and $\tau_{f_1 \sqcup f_2} \in \text{UWD}(\overset{Y_1 \sqcup Y_2}{\underset{X_1 \sqcup X_2}{\square}})$ are the corresponding name changes.
- $\theta_{(X_1, X_2)} \in \text{UWD}(\overset{X_1 \sqcup X_2}{\underset{X_1, X_2}{\square}})$ and $\theta_{(Y_1, Y_2)} \in \text{UWD}(\overset{Y_1 \sqcup Y_2}{\underset{Y_1, Y_2}{\square}})$ are 2-cells.

Then

$$\left(\theta_{(Y_1, Y_2)} \circ_1 \tau_{f_1} \right) \circ_2 \tau_{f_2} = \tau_{f_1 \sqcup f_2} \circ \theta_{(X_1, X_2)} \in \text{UWD}(\overset{Y_1 \sqcup Y_2}{\underset{X_1 \sqcup X_2}{\square}}). \quad (8.2.3.1)$$

The next relation says that a name change inside a loop (Def. 8.1.5) can be rewritten as a name change of a loop.

Proposition 8.2.4. *Suppose:*

- $X \in \text{Fin}_S$, and $x_+, x_- \in X$ are two distinct elements with $v(x_+) = v(x_-) \in S$.
- $f : X \longrightarrow Y \in \text{Fin}_S$ is a bijection with $y_+ = f(x_+)$ and $y_- = f(x_-)$.
- $X \setminus x_{\pm} \in \text{Fin}_S$ and $Y \setminus y_{\pm} \in \text{Fin}_S$ are obtained from X and Y by removing the indicated elements.

- $f' : X \setminus x_{\pm} \longrightarrow Y \setminus y_{\pm}$ is the corresponding bijection.
- $\tau_f \in \text{UWD}(\overset{Y}{X})$ and $\tau_{f'} \in \text{UWD}(\overset{Y \setminus y_{\pm}}{X \setminus x_{\pm}})$ are name changes.
- $\lambda_{(X, x_{\pm})} \in \text{UWD}(\overset{X \setminus x_{\pm}}{X})$ and $\lambda_{(Y, y_{\pm})} \in \text{UWD}(\overset{Y \setminus y_{\pm}}{Y})$ are loops.

Then

$$\lambda_{(Y, y_{\pm})} \circ \tau_f = \tau_{f'} \circ \lambda_{(X, x_{\pm})} \in \text{UWD}(\overset{Y \setminus y_{\pm}}{X}). \tag{8.2.4.1}$$

The next relation says that a name change inside a split (Def. 8.1.6) can be rewritten as a name change of a split.


Proposition 8.2.5. *Suppose:*

- $X \in \text{Fin}_S$, and x_1, x_2 are two distinct elements in X with $v(x_1) = v(x_2) \in S$.
- $X' \in \text{Fin}_S$, and $x \in X'$ such that $v(x) = v(x_1)$ and that $X' \setminus \{x\} = X \setminus \{x_1, x_2\}$.
- $f : X \longrightarrow Y \in \text{Fin}_S$ is a bijection with $y_1 = f(x_1)$ and $y_2 = f(x_2)$.
- $Y' \in \text{Fin}_S$, and $y \in Y'$ such that $v(y) = v(y_1) \in S$ and that $Y' \setminus \{y\} = Y \setminus \{y_1, y_2\}$.
- $f' : X' \longrightarrow Y' \in \text{Fin}_S$ is a bijection such that $f'(x) = y$ and that its restriction to $X' \setminus \{x\} = X \setminus \{x_1, x_2\}$ is equal to that of f .
- $\tau_f \in \text{UWD}(\overset{Y}{X})$ and $\tau_{f'} \in \text{UWD}(\overset{Y'}{X'})$ are name changes.
- $\sigma^{(X, x_1, x_2)} \in \text{UWD}(\overset{X}{X'})$ and $\sigma^{(Y, y_1, y_2)} \in \text{UWD}(\overset{Y}{Y'})$ are splits.


Then

$$\sigma^{(Y, y_1, y_2)} \circ \tau_{f'} = \tau_f \circ \sigma^{(X, x_1, x_2)} \in \text{UWD}(\overset{Y}{X'}). \tag{8.2.5.1}$$

The following two relations involve 1-output wires in somewhat subtle ways. The next relation says that the undirected wiring diagram



with a (1,0)-cable, all other cables being (1,1)-cables, can be obtained from the generators as either one of the following two (iterated) operadic compositions.



As in Section 7.3, the gray boxes here indicate an operadic composition.

- On the left, a 1-output wire ω_y is substituted into a 2-cell $\theta_{(X,y)}$, which is then substituted into a loop $\lambda_{(Y,x,y)}$.
- On the right, a split $\sigma^{(Y,x,y)}$ is substituted into a loop $\lambda_{(Y,x,y)}$.


Proposition 8.2.6. *Suppose:*

- $Y \in \text{Fin}_S$, and $x, y \in Y$ are distinct elements with $v(x) = v(y) \in S$.
- $X = Y \setminus y \in \text{Fin}_S$ is obtained from Y by removing y .
- $\omega_y \in \text{UWD}^{(y)}$ is the 1-output wire for y .
- $\theta_{(X,y)} \in \text{UWD}_{(X,y)}^{(Y)}$ is a 2-cell.
- $\lambda_{(Y,x,y)} \in \text{UWD}_{(Y,x,y)}^{(W)}$ is a loop, where $W = Y \setminus \{x, y\} = X \setminus x$.
- $\sigma^{(Y,x,y)} \in \text{UWD}_{(X)}^{(Y)}$ is a split.

Then

$$\lambda_{(Y,x,y)} \circ (\theta_{(X,y)} \circ_2 \omega_y) = \lambda_{(Y,x,y)} \circ \sigma^{(Y,x,y)} \in \text{UWD}_{(X)}^{(W)}. \quad (8.2.6.1)$$

The next relation says that the X -colored unit (Def. 7.3.2) can be obtained from the generators as the following iterated operadic composition.



More precisely, it says that the X -colored unit $\mathbb{1}_X$ can be obtained by substituting a 1-output wire ω_y into a 2-cell $\theta_{(X,y)}$, then into a split $\sigma^{(W,x,w)}$, and then into a loop $\lambda_{(W,w,y)}$.

Proposition 8.2.7. *Suppose:*

- $W \in \text{Fin}_S$, and w, x, y are distinct elements in W with $v(w) = v(x) = v(y) \in S$.
- $Y = W \setminus w \in \text{Fin}_S$ is obtained from W by removing w .
- $X = Y \setminus y \in \text{Fin}_S$ is obtained from Y by removing y .
- $\omega_y \in \text{UWD}^{(y)}$ is the 1-output wire for y .
- $\theta_{(X,y)} \in \text{UWD}_{(X,y)}^{(Y)}$ is a 2-cell.
- $\sigma^{(W,x,w)} \in \text{UWD}_{(Y)}^{(W)}$ is a split.
- $\lambda_{(W,w,y)} \in \text{UWD}_{(W)}^{(X)}$ is a loop.

Then

$$\lambda_{(W,w,y)} \circ \sigma^{(W,x,w)} \circ (\theta_{(X,y)} \circ_2 \omega_y) = \mathbb{1}_X \in \text{UWD}(\overset{X}{X}), \quad (8.2.7.1)$$

in which $\mathbb{1}_X$ is the X -colored unit (Def. 7.3.2).

The next five relations are about 2-cells (Def. 8.1.4). The following relation is the unity property of 2-cells.


Proposition 8.2.8. *Suppose:*

- $\theta_{(X,\emptyset)} \in \text{UWD}(\overset{X}{X,\emptyset})$ is a 2-cell.
- $\epsilon \in \text{UWD}(\emptyset)$ is the empty cell (Def. 8.1.1).

Then

$$\theta_{(X,\emptyset)} \circ_2 \epsilon = \mathbb{1}_X \in \text{UWD}(\overset{X}{X}). \quad (8.2.8.1)$$

The next relation is the associativity property of 2-cells. It gives two different ways to construct the following undirected wiring diagram using two 2-cells.



Proposition 8.2.9. *Suppose:*

- $\theta_{(X \cup Y, Z)} \in \text{UWD}(\overset{X \cup Y \cup Z}{X \cup Y, Z})$ and $\theta_{(X, Y)} \in \text{UWD}(\overset{X \cup Y}{X, Y})$ are 2-cells.
- $\theta_{(X, Y \cup Z)} \in \text{UWD}(\overset{X \cup Y \cup Z}{X, Y \cup Z})$ and $\theta_{(Y, Z)} \in \text{UWD}(\overset{Y \cup Z}{Y, Z})$ are 2-cells.

Then

$$\theta_{(X \cup Y, Z)} \circ_1 \theta_{(X, Y)} = \theta_{(X, Y \cup Z)} \circ_2 \theta_{(Y, Z)} \in \text{UWD}(\overset{X \cup Y \cup Z}{X, Y, Z}). \quad (8.2.9.1)$$

The next relation is the commutativity property of 2-cells. It uses the equivariant structure (7.3.1) in UWD.


Proposition 8.2.10. *Suppose:*

- $\theta_{X, Y} \in \text{UWD}(\overset{X \cup Y}{X, Y})$ is a 2-cell.
- $(1\ 2) \in \Sigma_2$ is the non-trivial permutation.

Then

$$\theta_{(X, Y)}(1\ 2) = \theta_{(Y, X)} \in \text{UWD}(\overset{Y \cup X}{Y, X}). \quad (8.2.10.1)$$

The next relation is the commutativity property between a 2-cell and a loop. It gives two different ways to construct the following undirected wiring diagram.




Proposition 8.2.11. *Suppose:*

- $Y \in \text{Fin}_S$, and y_+, y_- are distinct elements in Y with $v(y_+) = v(y_-) \in S$.
- $Y' = Y \setminus y_{\pm} \in \text{Fin}_S$ is obtained from Y by removing y_+ and y_- .
- $\lambda_{(Y, y_{\pm})} \in \text{UWD}(Y')$ is a loop.
- $\theta_{(X, Y)} \in \text{UWD}(X \sqcup Y)$ and $\theta_{(X, Y')} \in \text{UWD}(X \sqcup Y')$ are 2-cells for some $X \in \text{Fin}_S$.
- $\lambda_{(X \sqcup Y, y_{\pm})} \in \text{UWD}(X \sqcup Y')$ is a loop.

Then

$$\theta_{(X, Y')} \circ_2 \lambda_{(Y, y_{\pm})} = \lambda_{(X \sqcup Y, y_{\pm})} \circ \theta_{(X, Y)} \in \text{UWD}(X \sqcup Y'). \quad (8.2.11.1)$$

The next relation is the commutativity between a 2-cell and a split. It gives two different ways to construct the following undirected wiring diagram.




Proposition 8.2.12. *Suppose:*

- $Y \in \text{Fin}_S$, and y_1, y_2 are distinct elements in Y with $v(y_1) = v(y_2) \in S$.
- $Y' \in \text{Fin}_S$, and $y \in Y'$ such that $v(y) = v(y_1)$ and that $Y' \setminus \{y\} = Y \setminus \{y_1, y_2\}$.
- $\sigma^{(Y, y_1, y_2)} \in \text{UWD}(Y')$ is a split.
- $\theta_{(X, Y)} \in \text{UWD}(X \sqcup Y)$ and $\theta_{(X, Y')} \in \text{UWD}(X \sqcup Y')$ are 2-cells for some $X \in \text{Fin}_S$.
- $\sigma^{(X \sqcup Y, y_1, y_2)} \in \text{UWD}(X \sqcup Y')$ is a split.

Then

$$\theta_{(X, Y')} \circ_2 \sigma^{(Y, y_1, y_2)} = \sigma^{(X \sqcup Y, y_1, y_2)} \circ \theta_{(X, Y)} \in \text{UWD}(X \sqcup Y'). \quad (8.2.12.1)$$

The following four relations are about splits. The next relation is the commutativity property of splits. It gives two different ways to construct the following undirected wiring diagram using two splits.




Proposition 8.2.13. *Suppose:*

- $X \in \text{Fin}_S$, and y_1, y_2, z_1, z_2 are distinct elements such that $v(y_1) = v(y_2)$ and $v(z_1) = v(z_2) \in S$.
- $X' \in \text{Fin}_S$, and y and z are distinct elements in X' such that
 - $v(y) = v(y_1)$ and $v(z) = v(z_1)$;
 - $X' \setminus \{y, z\} = X \setminus \{y_1, y_2, z_1, z_2\}$.
- $Y = [X' \setminus \{y\}] \sqcup \{y_1, y_2\}$ and $Z = [X' \setminus \{z\}] \sqcup \{z_1, z_2\} \in \text{Fin}_S$
- $\sigma^{(X, y_1, y_2)} \in \text{UWD}(\frac{X}{Z})$ and $\sigma^{(Z, z_1, z_2)} \in \text{UWD}(\frac{Z}{X'})$ are splits.
- $\sigma^{(X, z_1, z_2)} \in \text{UWD}(\frac{X}{Y})$ and $\sigma^{(Y, y_1, y_2)} \in \text{UWD}(\frac{Y}{X'})$ are splits.

Then

$$\sigma^{(X, y_1, y_2)} \circ \sigma^{(Z, z_1, z_2)} = \sigma^{(X, z_1, z_2)} \circ \sigma^{(Y, y_1, y_2)} \in \text{UWD}(\frac{X}{X'}). \quad (8.2.13.1)$$

The next relation is the associativity property of splits. It gives two different ways to construct the following undirected wiring diagram using two splits.




Proposition 8.2.14. *Suppose:*

- $Y \in \text{Fin}_S$, and y_1, y_2, y_3 are distinct elements in Y with $v(y_1) = v(y_2) = v(y_3) \in S$.
- $X \in \text{Fin}_S$, and $x \in X$ such that
 - $v(x) = v(y_1)$;
 - $X \setminus \{x\} = Y \setminus \{y_1, y_2, y_3\}$.
- $Y_1 = Y/(y_1 = y_2) \in \text{Fin}_S$ is the quotient of Y with y_1 and y_2 identified, called $y_{12} \in Y_1$.
- $Y_2 = Y/(y_2 = y_3) \in \text{Fin}_S$ is the quotient of Y with y_2 and y_3 identified, called $y_{23} \in Y_2$.
- $\sigma^{(Y, y_1, y_2)} \in \text{UWD}(\frac{Y}{Y_1})$ and $\sigma^{(Y_1, y_{12}, y_3)} \in \text{UWD}(\frac{Y_1}{X})$ are splits.
- $\sigma^{(Y, y_2, y_3)} \in \text{UWD}(\frac{Y}{Y_2})$ and $\sigma^{(Y_2, y_1, y_{23})} \in \text{UWD}(\frac{Y_2}{X})$ are splits.

Then

$$\sigma^{(Y,y_1,y_2)} \circ \sigma^{(Y_1,y_{12},y_3)} = \sigma^{(Y,y_2,y_3)} \circ \sigma^{(Y_2,y_1,y_{23})} \in \text{UWD}(\frac{Y}{X}). \quad (8.2.14.1)$$

The next relation is the commutativity property between a split and a loop. It gives two different ways to construct the following undirected wiring diagram using a split and a loop.




Proposition 8.2.15. *Suppose:*

- $Y \in \text{Fin}_S$, and y_1 and y_2 are distinct elements in Y with $v(y_1) = v(y_2) \in S$.
- $X \in \text{Fin}_S$, and x, x_+, x_- are distinct elements in X such that
 - $v(x) = v(y_1)$;
 - $v(x_+) = v(x_-)$;
 - $X \setminus \{x, x_+, x_-\} = Y \setminus \{y_1, y_2\}$.
- $Y' = [X \setminus \{x\}] \sqcup \{y_1, y_2\}$ and $X' = X \setminus \{x_+, x_-\}$.
- $\sigma^{(Y',y_1,y_2)} \in \text{UWD}(\frac{Y'}{X'})$ and $\sigma^{(Y,y_1,y_2)} \in \text{UWD}(\frac{Y}{X})$ are splits.
- $\lambda_{(Y',x_{\pm})} \in \text{UWD}(\frac{Y'}{Y'})$ and $\lambda_{(X,x_{\pm})} \in \text{UWD}(\frac{X'}{X'})$ are loops.


Then

$$\lambda_{(Y',x_{\pm})} \circ \sigma^{(Y',y_1,y_2)} = \sigma^{(Y,y_1,y_2)} \circ \lambda_{(X,x_{\pm})} \in \text{UWD}(\frac{Y}{X}). \quad (8.2.15.1)$$

The next relation says that the undirected wiring diagram



can be obtained by substituting a split inside a loop as in the picture



or in the counterpart in which x_+ and x_- are switched. In (8.2.16.1) below, this picture corresponds to the left side, and its counterpart corresponds to the right side.


Proposition 8.2.16. *Suppose:*

- $X \in \text{Fin}_S$, and x_+ and x_- are distinct elements in X with $v(x_+) = v(x_-) \in S$.
- $Y \in \text{Fin}_S$, and $y \in Y$ such that $v(y) = v(x_+)$ and that $X \setminus x_{\pm} = Y \setminus y$.
- $W = X \sqcup y = Y \sqcup x_{\pm} \in \text{Fin}_S$.
- $\sigma^{(W,y,x_+)} \in \text{UWD}(\frac{W}{X})$ and $\sigma^{(W,y,x_-)} \in \text{UWD}(\frac{W}{X})$ are splits.
- $\lambda_{(W,x_{\pm})} \in \text{UWD}(\frac{Y}{W})$ is a loop.

Then

$$\lambda_{(W,x_{\pm})} \circ \sigma^{(W,y,x_+)} = \lambda_{(W,x_{\pm})} \circ \sigma^{(W,y,x_-)} \in \text{UWD}(\frac{Y}{X}). \quad (8.2.16.1)$$

The final relation is the commutativity property of loops. It gives two different ways to construct the following undirected wiring diagram using two loops.



Proposition 8.2.17. *Suppose:*

- $X \in \text{Fin}_S$, and x_1, x_2, x_3, x_4 are distinct elements in X with $v(x_1) = v(x_2)$ and $v(x_3) = v(x_4) \in S$.
- $W = X \setminus \{x_1, x_2\}$, $Z = X \setminus \{x_3, x_4\}$, and $Y = X \setminus \{x_1, x_2, x_3, x_4\} \in \text{Fin}_S$.
- $\lambda_{(W,x_3,x_4)} \in \text{UWD}(\frac{Y}{W})$ and $\lambda_{(X,x_1,x_2)} \in \text{UWD}(\frac{W}{X})$ are loops.
- $\lambda_{(Z,x_1,x_2)} \in \text{UWD}(\frac{Y}{Z})$ and $\lambda_{(X,x_3,x_4)} \in \text{UWD}(\frac{Z}{X})$ are loops.

Then

$$\lambda_{(W,x_3,x_4)} \circ \lambda_{(X,x_1,x_2)} = \lambda_{(Z,x_1,x_2)} \circ \lambda_{(X,x_3,x_4)} \in \text{UWD}(\frac{Y}{X}). \quad (8.2.17.1)$$

Definition 8.2.18. The 17 relations (8.2.1.1)–(8.2.17.1) are called *elementary relations* in UWD. If there is no danger of confusion, we will call them *elementary relations*.

8.3. Wasted Cables

The purpose of this section is to consider several examples of how the generators in the operad UWD can create wasted cables (Def. 7.1.1). Example 8.3.4 provides an illustration of some of the elementary relations in UWD. The examples in this

section provide a good warm-up exercise for the discussion in Chapter 10 about stratified presentations and elementary equivalences.

Recall from Remark 8.1.7 that none of the generators has a wasted cable.

Example 8.3.1. In the context of Example 7.3.7 with $X = \{x_1, x_2\}$:

- (1) $\varphi = \left\{ X \longrightarrow * \longleftarrow \emptyset \right\} \in \text{UWD}(\emptyset_X)$ is the loop $\lambda_{(X, x_1, x_2)}$.
- (2) $\psi = \left\{ \emptyset \longrightarrow X \longleftarrow X \right\} \in \text{UWD}(\emptyset_X)$ is the iterated operadic composition


$$\psi = \left[\left(\theta_{(\emptyset, X)} \circ_2 \theta_{(x_1, x_2)} \right) \circ_2 \omega_{x_1} \right] \circ_2 \omega_{x_2}$$

involving two 2-cells and two 1-output wires.

So the composition

$$\varphi \circ \psi = \left(\emptyset \longrightarrow * \longleftarrow \emptyset \right) \in \text{UWD}(\emptyset),$$

which is depicted as



and has one wasted cable, is the iterated operadic composition


$$\lambda_{(X, x_1, x_2)} \circ \left[\left(\left(\theta_{(\emptyset, X)} \circ_2 \theta_{(x_1, x_2)} \right) \circ_2 \omega_{x_1} \right) \circ_2 \omega_{x_2} \right] \tag{8.3.1.1}$$

involving 5 generators.

Example 8.3.2. As a variation of the previous example, consider any box $Y \in \text{Fin}_S$ and the undirected wiring diagram with one wasted cable

$$\zeta_Y = \left(Y \xrightarrow{\text{inclusion}} Y \amalg * \xleftarrow{\text{inclusion}} Y \right) \in \text{UWD}(Y).$$


It is depicted as follows.



This undirected wiring diagram can be created by replacing the empty box \emptyset in the 2-cell $\theta_{(\emptyset, X)}$ by Y and the loop $\lambda_{(X, x_1, x_2)}$ by the loop $\lambda_{(Y \amalg X, x_1, x_2)}$ in (8.3.1.1) above. The resulting operadic composition


$$\zeta_Y = \lambda_{(Y \amalg X, x_1, x_2)} \circ \left[\left(\left(\theta_{(Y, X)} \circ_2 \theta_{(x_1, x_2)} \right) \circ_2 \omega_{x_1} \right) \circ_2 \omega_{x_2} \right] \in \text{UWD}(Y) \tag{8.3.2.1}$$

involves 5 generators: one loop, two 2-cells, and two 1-output wires. It corresponds to the following picture.



The intermediate gray box is $Y \sqcup X = Y \sqcup \{x_1, x_2\}$. Roughly speaking, the operadic composition (8.3.2.1) says that a wasted cable can be created by applying a loop to two 1-output wires. Additional wasted cables can similarly be created using more 2-cells, 1-output wires, and loops.

Example 8.3.3. The undirected wiring diagram ζ_Y in Example 8.3.2 can also be created as in the following picture.



The inner gray box is $Y \sqcup x_1$, and the outer gray box is $Y \sqcup X$. In terms of the generators, the above picture is realized as the operadic composition

$$\zeta_Y = \left[\lambda_{(Y \sqcup X, x_1, x_2)} \circ \sigma^{(Y \sqcup X, x_1, x_2)} \right] \circ \left[\theta_{(Y, x_1)} \circ_2 \omega_{x_1} \right] \in \text{UWD}(\overset{Y}{\downarrow}). \tag{8.3.3.1}$$

It involves one loop, one split, one 2-cell, and one 1-output wire. Roughly speaking, the operadic composition (8.3.3.1) says that a wasted cable can be created by applying a loop to a split that is attached to a 1-output wire.

Example 8.3.4. As an illustration of using the elementary relations in UWD, recall the undirected wiring diagram $\zeta_Y \in \text{UWD}(\overset{Y}{\downarrow})$ in Examples 8.3.2 and 8.3.3. It can be generated by the generators as either one of the two iterated operadic compositions (8.3.2.1) and (8.3.3.1). These two decompositions of ζ_Y are actually connected as

follows.

$$\begin{aligned}
& \lambda_{(Y \amalg X, x_1, x_2)} \circ \left[\left(\left(\theta_{(Y, X)} \circ_2 \theta_{(x_1, x_2)} \right) \circ_2 \omega_{x_1} \right) \circ_2 \omega_{x_2} \right] \quad \text{by (8.3.2.1)} \\
&= \lambda_{(Y \amalg X, x_1, x_2)} \circ \left[\left(\left(\theta_{(Y \amalg x_1, x_2)} \circ_1 \theta_{(Y, x_1)} \right) \circ_2 \omega_{x_1} \right) \circ_2 \omega_{x_2} \right] \quad \text{by elem. rel. (8.2.9.1)} \\
&= \lambda_{(Y \amalg X, x_1, x_2)} \circ \left[\left(\theta_{(Y \amalg x_1, x_2)} \circ_1 \left(\theta_{(Y, x_1)} \circ_2 \omega_{x_1} \right) \right) \circ_2 \omega_{x_2} \right] \quad \text{by vertical ass. (2.1.4.4)} \\
&= \lambda_{(Y \amalg X, x_1, x_2)} \circ \left[\left(\theta_{(Y \amalg x_1, x_2)} \circ_2 \omega_{x_2} \right) \circ_1 \left(\theta_{(Y, x_1)} \circ_2 \omega_{x_1} \right) \right] \quad \text{by horizontal ass. (2.1.4.3)} \\
&= \left[\lambda_{(Y \amalg X, x_1, x_2)} \circ \left(\theta_{(Y \amalg x_1, x_2)} \circ_2 \omega_{x_2} \right) \right] \circ \left[\theta_{(Y, x_1)} \circ_2 \omega_{x_1} \right] \quad \text{by vertical ass. (2.1.4.4)} \\
&= \left[\lambda_{(Y \amalg X, x_1, x_2)} \circ \sigma^{(Y \amalg X, x_1, x_2)} \right] \circ \left[\theta_{(Y, x_1)} \circ_2 \omega_{x_1} \right] \quad \text{by elem. rel. (8.2.6.1)}
\end{aligned}$$

The last iterated operadic composition above is (8.3.3.1). In other words, one can go from the decomposition (8.3.2.1) of ζ_Y to (8.3.3.1) using two elementary relations, the operad vertical associativity axiom twice, and the operad horizontal associativity axiom once. In the terminology of Chapter 10, we say that (8.3.2.1) and (8.3.3.1) are stratified presentations (Def. 10.1.6) of ζ_Y , and they are connected by a finite sequence of elementary equivalences (Def. 10.2.1).

Decomposition of Undirected Wiring Diagrams

This chapter is the undirected analogue of Chapter 4. As part of the finite presentation theorem for the operad UWD of undirected wiring diagrams (Theorem 7.3.11), in Theorem 10.1.10 we will observe that each undirected wiring diagram has a highly structured decomposition in terms of generators (Def. 8.1.7), called a stratified presentation (Def. 10.1.6). Stratified presentations are also needed to establish the second part of the finite presentation theorem for the operad UWD regarding relations (Theorem 10.2.7). The purpose of this chapter is to provide all the steps needed to establish the existence of a stratified presentation for each undirected wiring diagram. We remind the reader about Notation 3.3.1 for (iterated) operadic compositions.

Fix a class S , with respect to which the operad UWD of undirected wiring diagrams (Def. 7.3.11) is defined.

9.1. A Sample Decomposition

Before we establish the desired decomposition of a general undirected wiring diagram, in this section we consider an elaborate example that will serve as a guide and motivation for the construction later in this chapter for the general case. The point of this decomposition is to break the complexity of a general undirected wiring diagram into several stratified pieces, each of which is easy to understand and visualize.

The following notations regarding subsets of cables will be used frequently in this chapter. Recall that an (m, n) -cable is a cable to which exactly m input wires and exactly n output wires are soldered (Def. 7.1.1).


Notation 9.1.1. Suppose $\psi = (C_\psi, f_\psi, g_\psi)$ is an undirected wiring diagram and $m, n \geq 0$. Define:

- $C_\psi^{(m,n)} \subseteq C_\psi$ as the subset of (m, n) -cables. In particular, $C_\psi^{(0,0)}$ is the set of wasted cables.
- $C_\psi^{(\geq m,n)} \subseteq C_\psi$ as the subset of (l, n) -cables with $l \geq m$.
- $C_\psi^{(m,\geq n)} \subseteq C_\psi$ as the subset of (m, k) -cables with $k \geq n$.
- $C_\psi^{(\geq m,\geq n)} \subseteq C_\psi$ as the subset of (j, k) -cables with $j \geq m$ and $k \geq n$.
- $C_\psi^{\geq 3} \subseteq C_\psi$ as the subset of (k, l) -cables with $k, l \geq 1$ and $k + l \geq 3$.

A cable in $C_\psi^{(\geq m,n)}$ is called an $(\geq m, n)$ -cable, and similarly for cables in the other subsets defined above.

As in the case of wiring diagrams (see Convention 4.2.4), name changes (Def. 8.1.3) are easy to deal with. Therefore, in the following example, to keep the presentation simple, we will ignore name changes.


Example 9.1.2. Consider $\varphi = (C_\varphi, f_\varphi, g_\varphi) \in \text{UWD}_{(X_1, X_2)}^Y$ in (7.1.6.1), which is visualized as



with $X_1 = \{x_1, \dots, x_6\}$ and $X_2 = \{x^1, x^2\}$. We can decompose it as

$$\varphi = \varphi_1 \circ \varphi_2 \tag{9.1.2.1}$$

as indicated in the following picture.



As before the intermediate gray box Z indicates that an operadic composition occurs along it. The box Z is defined as

$$Z = X \sqcup \{c_{4+}, c_{4-}\} \sqcup \{c_1, c_5\} \sqcup \{c_7\} \in \text{Fin}_5$$

in which:

- $X = X_1 \sqcup X_2$.
- c_{4+} and c_{4-} are two copies of the wasted cable c_4 in φ , so $\{c_{4+}, c_{4-}\} = C_\varphi^{(0,0)} \sqcup C_\varphi^{(0,0)}$.
- $\{c_1, c_5\} = C_\varphi^{(0,\geq 1)}$.
- $\{c_7\} = C_\varphi^{(1,0)}$.

So we may also write Z as

$$Z = X \sqcup C_{\varphi,\pm}^{(0,0)} \sqcup C_\varphi^{(0,\geq 1)} \sqcup C_\varphi^{(1,0)} \tag{9.1.2.2}$$

in which $C_{\varphi,\pm}^{(0,0)} = C_\varphi^{(0,0)} \sqcup C_\varphi^{(0,0)}$ is the coproduct of two copies of the set of wasted cables $C_\varphi^{(0,0)}$ in φ .

In the decomposition (9.1.2.1) of φ , the inside undirected wiring diagram is the cospan

$$\varphi_2 = \left(X \xrightarrow{\text{inclusion}} Z \xleftarrow{=} Z \right) \in \text{UWD}_{(X_1, X_2)}^Z.$$

Note that in φ_2 :

- All the input wires—i.e., those in X —are $(1, 1)$ -cables.
- All other cables—i.e., those in $C_{\varphi,\pm}^{(0,0)} \sqcup C_\varphi^{(0,\geq 1)} \sqcup C_\varphi^{(1,0)}$ —are $(0, 1)$ -cables.
- There are no wasted cables.

As we will see later in (9.3.6.1), such an undirected wiring diagram can be decomposed into 2-cells (Def. 8.1.4) and 1-output wires (Def. 8.1.2). For example, this φ_2 needs:

- five 1-output wires, exactly as many as the number of $(0, 1)$ -cables;
- six 2-cells, where 6 is the number of input boxes plus the number of $(0, 1)$ -cables minus 1.


The outside undirected wiring diagram in the decomposition $\varphi = \varphi_1 \circ \varphi_2$ is the cospan

$$\varphi_1 = \left(Z \xrightarrow{(f_\varphi, \iota)} C_\varphi \xleftarrow{g_\varphi} Y \right) \in \text{UWD}\left(\frac{Y}{Z}\right).$$

Here:

- $f_\varphi : X \longrightarrow C_\varphi$ is the input soldering function of φ .
- $\iota : C_{\varphi, \pm}^{(0,0)} \amalg C_{\varphi}^{(0, \geq 1)} \amalg C_{\varphi}^{(1,0)} \longrightarrow C_\varphi$ is the inclusion map on each coproduct summand.
- $g_\varphi : Y \longrightarrow C_\varphi$ is the output soldering function of φ .
- Every cable is an (m, n) -cable with $m \geq 1$ and $n \geq 0$. In other words, every cable in φ_1 is soldered to some input wires, so in particular there are no wasted cables in φ_1 .
- There are also no $(1, 0)$ -cables, but there are $(\geq 2, 0)$ -cables.


As we will see later, such an undirected wiring diagram can be decomposed into loops (Def. 8.1.5) and splits (Def. 8.1.6). In the case of φ_1 , which is the undirected wiring diagram



this further decomposition

$$\varphi_1 = \phi_1 \circ \phi_2 \tag{9.1.2.3}$$

can be visualized as follows.



(9.1.2.4)

In this decomposition $\varphi_1 = \varphi_1 \circ \varphi_2$, the inner undirected wiring diagram is the cospan

$$\varphi_2 = \left(Z \xrightarrow{=} Z \xleftarrow{g_{\varphi_2}} W \right) \in \text{UWD} \left(\begin{smallmatrix} W \\ Z \end{smallmatrix} \right)$$

with g_{φ_2} surjective. So every cable in φ_2 is a $(1, n)$ -cable for some $n \geq 1$. As we will see later, such an undirected wiring diagram is generated by splits (Def. 8.1.6). For example, this φ_2 is the iterated operadic composition of 5 splits—one for the cable soldered to c_1 , one for the cable soldered to x_5 , and three for the cable soldered to x_2 .

The outer undirected wiring diagram in the decomposition (9.1.2.3) is the cospan

$$\varphi_1 = \left(W \longrightarrow C_{\varphi_1} \longleftarrow Y \right) \in \text{UWD} \left(\begin{smallmatrix} Y \\ W \end{smallmatrix} \right)$$

in which every cable is either a $(1, 1)$ -cable or a $(2, 0)$ -cable. We will show later that such an undirected wiring diagram is generated by loops (Def. 8.1.5). For example, this φ_1 is the iterated operadic composition of 6 loops, where 6 is the number of $(2, 0)$ -cables in φ_1 .

In summary, we decompose $\varphi \in \text{UWD} \left(\begin{smallmatrix} Y \\ X_1, X_2 \end{smallmatrix} \right)$ as the iterated operadic composition

$$\begin{aligned} \varphi &= \varphi_1 \circ \varphi_2 = \varphi_1 \circ \varphi_2 \circ \varphi_2 \\ &= \left(\underbrace{\lambda, \dots, \lambda}_6, \underbrace{\sigma, \dots, \sigma}_5, \underbrace{\theta, \dots, \theta}_6, \underbrace{\omega, \dots, \omega}_5 \right). \end{aligned} \tag{9.1.2.5}$$

Here λ, σ, θ , and ω denote a loop, a split, a 2-cell, and a 1-output wire, respectively. This decomposition in terms of the generators is called a stratified presentation (Def. 10.1.6). In the next few sections, we will establish all the steps needed to obtain a stratified presentation for a general undirected wiring diagram.

9.2. Factoring Undirected Wiring Diagrams

In this section, using Example 9.1.2 as a guide and motivation, we establish a decomposition of a general undirected wiring diagram into two simpler undirected wiring diagrams (Theorem 9.2.3). This is the general version of the decomposition (9.1.2.1) above. Each undirected wiring diagram in this decomposition will be decomposed further, eventually leading to the desired stratified presentation.

Assumption 9.2.1. Suppose

$$\psi = \left(X \xrightarrow{f_\psi} C_\psi \xleftarrow{g_\psi} Y \right) \in \text{UWD}(\underline{X}) \quad (9.2.1.1)$$

is a general undirected wiring diagram with:

- output box $Y \in \text{Fin}_S$ and input boxes $\underline{X} = (X_1, \dots, X_N)$ for some $N \geq 0$;
- $X = X_1 \sqcup \dots \sqcup X_N \in \text{Fin}_S$.

Recall Notation 9.1.1 for certain subsets of cables. The undirected wiring diagrams ψ_1 and ψ_2 in the next definition are the general versions of φ_1 and φ_2 in the decomposition (9.1.2.1) above.

Definition 9.2.2. Suppose $\psi = (C_\psi, f_\psi, g_\psi) \in \text{UWD}(\underline{X})$ is a general undirected wiring diagram as in (9.2.1.1) with $\underline{X} = (X_1, \dots, X_N)$.

(1) Define

$$Z = X \sqcup C_{\psi, \pm}^{(0,0)} \sqcup C_\psi^{(0, \geq 1)} \sqcup C_\psi^{(1,0)} \in \text{Fin}_S \quad (9.2.2.1)$$

in which

$$C_{\psi, \pm}^{(0,0)} = C_\psi^{(0,0)} \sqcup C_\psi^{(0,0)}$$

is the coproduct of two copies of the set of wasted cables $C_\psi^{(0,0)}$ in ψ .

(2) Define the undirected wiring diagram

$$\psi_1 = \left(Z \xrightarrow{(f_\psi, \iota)} C_\psi \xleftarrow{g_\psi} Y \right) \in \text{UWD}(\underline{Z}) \quad (9.2.2.2)$$

in which

$$C_{\psi, \pm}^{(0,0)} \sqcup C_\psi^{(0, \geq 1)} \sqcup C_\psi^{(1,0)} \xrightarrow{\iota} C_\psi$$

is the inclusion map on each coproduct summand.


(3) Define the undirected wiring diagram

$$\psi_2 = \left(X \xrightarrow{\text{inclusion}} Z \xleftarrow{=} Z \right) \in \text{UWD}(\underline{X}). \quad (9.2.2.3)$$

Theorem 9.2.3. *In the context of Def. 9.2.2, there is a decomposition*

$$\psi = \psi_1 \circ \psi_2 \in \text{UWD}(\underline{X}). \quad (9.2.3.1)$$

Proof. By the definition of $\circ = \circ_1$ (Def. 7.3.4), the operadic composition $\psi_1 \circ \psi_2$ is given by the cospan



in Fin_S . The square is a pushout by Example 7.2.3. This cospan is equal to ψ . \square

Example 9.2.4. If $\psi = \epsilon \in \text{UWD}^{(\emptyset)}$ is the empty cell (Def. 8.1.1), then:

- $\psi_1 = \mathbb{1}_{\emptyset}$, the \emptyset -colored unit (Def. 7.3.2) with $\emptyset \in \text{Fin}_S$ the empty box;
- $\psi_2 = \epsilon$.

So in this case the decomposition (9.2.3.1) simply says $\epsilon = \mathbb{1}_{\emptyset} \circ \epsilon$.

Remark 9.2.5. In the decomposition (9.2.3.1), both ψ_1 and ψ_2 are simpler than ψ for the following reasons.

- (1) ψ_1 has the same set of cables C_{ψ} and the same output soldering function g_{ψ} as ψ . Furthermore, its input soldering function (f_{ψ}, ι) includes the input soldering function f_{ψ} of ψ . However, every cable in ψ_1 is soldered to at least one input wire (i.e., $C_{\psi_1}^{(0, \geq 0)} = \emptyset$), whereas $C_{\psi}^{(0, \geq 0)}$ may be non-empty. In particular, ψ_1 has no wasted cables, even though ψ may have some. Furthermore, ψ_1 has only one input box Z , while ψ has $N \geq 0$ input boxes.
- (2) ψ_2 has the same input boxes \underline{X} as ψ . However, it is, in general, much simpler than ψ and ψ_1 because its cables are either $(1, 1)$ -cables or $(0, 1)$ -cables. In particular, ψ_2 also has no wasted cables.
- (3) Neither ψ_1 nor ψ_2 has any $(1, 0)$ -cables, even though ψ may have some.

9.3. The Inner Undirected Wiring Diagram

The purpose of this section is to analyze the undirected wiring diagram ψ_2 in the decomposition (9.2.3.1). The undirected wiring diagram ψ_1 will be studied in the next few sections. We begin with the following observation regarding iterated operadic compositions of 2-cells (Def. 8.1.4).

Proposition 9.3.1. Suppose $n \geq 2$, $X_i \in \text{Fin}_S$ for $1 \leq i \leq n$, and $X = \coprod_{i=1}^n X_i$. Then the undirected wiring diagram

$$\Theta = \left(X \xrightarrow{=} X \xleftarrow{=} X \right) \in \text{UWD}_{(X_1, \dots, X_n)}^X \quad (9.3.1.1)$$

is:

- a 2-cell if $n = 2$;
- an iterated operadic composition

$$\Theta = \left((\theta_1 \circ_2 \theta_2) \circ_3 \cdots \right) \circ_{n-1} \theta_{n-1}$$

with each θ_j a 2-cell if $n \geq 3$.

Proof. This is proved by induction on $n \geq 2$. The initial case simply says that Θ is the 2-cell $\theta_{(X_1, X_2)}$ by Def. 8.1.4.

Suppose $n \geq 3$. By the definition of \circ_{n-1} (Def. 7.3.4) and Example 7.2.3, we may decompose Θ as

$$\Theta = \Theta_1 \circ_{n-1} \theta_{(X_{n-1}, X_n)}$$

in which

$$\Theta_1 = \left(X \xrightarrow{=} X \xleftarrow{=} X \right) \in \text{UWD}_{(X_1, \dots, X_{n-2}, X_{n-1} \sqcup X_n)}^X$$

and

$$\theta_{(X_{n-1}, X_n)} \in \text{UWD}_{(X_{n-1}, X_n)}^{(X_{n-1} \sqcup X_n)}$$

is a 2-cell. Since the induction hypothesis applies to Θ_1 , the proof is finished. \square

Example 9.3.2. In the previous proposition:

- (1) If $n = 3$, then Θ decomposes as

$$\Theta = \theta_{(X_1, X_2 \sqcup X_3)} \circ_2 \theta_{(X_2, X_3)}$$

into two 2-cells.

- (2) If $n = 4$, then Θ decomposes as

$$\Theta = \left(\theta_{(X_1, X_2 \sqcup X_3 \sqcup X_4)} \circ_2 \theta_{(X_2, X_3 \sqcup X_4)} \right) \circ_3 \theta_{(X_3, X_4)}$$

into three 2-cells.

Notation 9.3.3. In the context of (9.2.2.1), write:

- $C'_\psi = C_{\psi, \pm}^{(0,0)} \sqcup C_\psi^{(0, \geq 1)} \sqcup C_\psi^{(1,0)} \in \text{Fin}_S$, so $Z = X \sqcup C'_\psi$.
- $p = |C'_\psi|$.

The following observation covers the marginal cases for ψ_2 .

Lemma 9.3.4. For $\psi_2 = \left(X \xrightarrow{\text{inclusion}} Z \xleftarrow{=} Z \right) \in \text{UWD}_{(Z)}^Z$ in (9.2.2.3):

- (1) If $N = p = 0$, then ψ_2 is the empty cell ϵ (Def. 8.1.1).
- (2) If $N = 0$ and $p = 1$, then ψ_2 is a 1-output wire (Def. 8.1.2).
- (3) If $N = 1$ and $p = 0$, then ψ_2 is the X_1 -colored unit (Def. 7.3.2).

Proof. Since $\underline{X} = (X_1, \dots, X_N)$ and $X = X_1 \sqcup \dots \sqcup X_N$, all three statements follow immediately from the definition of ψ_2 . \square

The next observation covers the other cases for ψ_2 . Recall C'_ψ in Notation 9.3.3.

Proposition 9.3.5. For $\psi_2 = \left(X \xrightarrow{\text{inclusion}} Z \xleftarrow{=} Z \right) \in \text{UWD}\left(\frac{Z}{\underline{X}}\right)$ in (9.2.2.3), suppose:

- $N, p \geq 1$, and $C'_\psi = \{c_1, \dots, c_p\}$;
- $\omega_j = \left(\emptyset \longrightarrow c_j \xleftarrow{=} c_j \right) \in \text{UWD}(c_j)$ is the 1-output wire for c_j (Def. 8.1.2) for $1 \leq j \leq p$.

Then there is a decomposition

$$\psi_2 = \left((\Theta \circ_{N+1} \omega_1) \cdots \right) \circ_{N+1} \omega_p \in \text{UWD}\left(\frac{Z}{\underline{X}}\right) \quad (9.3.5.1)$$

in which every pair of parentheses starts on the left and

$$\Theta = \left(Z \xrightarrow{=} Z \xleftarrow{=} Z \right) \in \text{UWD}\left(\frac{Z}{(X_1, \dots, X_N, c_1, \dots, c_p)}\right).$$

Proof. The right side of (9.3.5.1) is a well-defined element in $\left(\frac{Z}{\underline{X}}\right)$. By the correspondence between the \circ_i -compositions and γ (2.1.6.1) in the operad UWD, the right side of (9.3.5.1) can be rewritten as

$$\psi'_2 = \gamma\left(\Theta; \mathbb{1}_{X_1}, \dots, \mathbb{1}_{X_N}, \omega_1, \dots, \omega_p\right).$$

Since $Z = X \sqcup \{c_1, \dots, c_p\}$, by Prop. 7.3.13 the cospan for ψ'_2 is

$$\begin{array}{ccc} & & Z \\ & & \downarrow = \\ & Z & \xrightarrow{=} Z \\ & \downarrow = & \downarrow = \\ X & \xrightarrow{\text{inclusion}} & Z \xrightarrow{=} Z \end{array}$$

in Fin_S . This is equal to the cospan that defines ψ_2 . \square

The following observation says that, if $N, p \geq 1$, then ψ_2 is generated by 2-cells and 1-output wires.

Corollary 9.3.6. Suppose $\psi_2 \in \text{UWD}\left(\frac{Z}{\underline{X}}\right)$ in (9.2.2.3) has $N = |\underline{X}|, p = |C'_\psi| \geq 1$. Then there is a decomposition

$$\psi_2 = \left[\left[\left((\theta_1 \circ_2 \theta_2) \circ_3 \cdots \right) \circ_{N+p-1} \theta_{N+p-1} \right] \circ_{N+1} \omega_1 \right] \cdots \circ_{N+1} \omega_p \quad (9.3.6.1)$$

with:

- each θ_i a 2-cell;
- each ω_j a 1-output wire;
- each pair of parentheses starting on the left.

Proof. This is true by the decomposition (9.3.5.1) above and Prop. 9.3.1 with $n = N + p \geq 2$, applied to Θ . \square

9.4. The Outer Undirected Wiring Diagram

The purpose of this section is to establish a decomposition for the undirected wiring diagram ψ_1 (9.2.2.2) that appeared in (9.2.3.1). This is the general version of the decomposition (9.1.2.3), so the reader may wish to refer back there for specific examples of the constructions below. Each of the constituent undirected wiring diagrams in this decomposition will be studied further in later sections. The goal is to decompose ψ_1 into two undirected wiring diagrams in which the outer one, called ϕ_1 below, is generated by loops (Def. 8.1.5), while the inner one, called ϕ_2 below, is generated by splits (Def. 8.1.6).

Recall Notation 9.1.1 for certain subsets of cables. Also recall from Remark 9.2.5 that $\psi_1 \in \text{UWD}(\frac{Y}{Z})$ has neither $(0, \geq 0)$ -cables nor $(1, 0)$ -cables. So ψ_1 satisfies the hypotheses of the next definition.

Definition 9.4.1. Suppose $\varphi = (C_\varphi, f_\varphi, g_\varphi) \in \text{UWD}(\frac{B}{A})$ is an undirected wiring diagram with

- one input box A and
- $C_\varphi^{(0, \geq 0)} = \emptyset = C_\varphi^{(1, 0)}$.

We will write f_φ and g_φ as f and g , respectively.

- (1) For each cable $c \in C_\varphi^{(\geq 3, 0)} \sqcup C_\varphi^{\geq 3}$, choose a wire $a_c \in f^{-1}c \subseteq A$, where $f^{-1}c = f^{-1}(\{c\})$ is the set of f -preimages of c .
- (2) Define

$$W = B \sqcup f^{-1}C_\varphi^{(2, 0)} \sqcup \coprod_{c \in C_\varphi^{(\geq 3, 0)} \sqcup C_\varphi^{\geq 3}} [f^{-1}c \setminus a_c]_\pm \in \text{Fin}_S \quad (9.4.1.1)$$

in which

$$[f^{-1}c \setminus a_c]_\pm = [f^{-1}c \setminus a_c]_+ \sqcup [f^{-1}c \setminus a_c]_-$$

is the coproduct of two copies of $[f^{-1}c \setminus a_c]$. This W is the general version of the W in the example (9.1.2.4).

(3) Define

$$V = B \sqcup C_\varphi^{(2,0)} \sqcup \coprod_{c \in C_\varphi^{(\geq 3,0)} \sqcup C_\varphi^{\geq 3}} [f^{-1}c \setminus a_c] \in \text{Fin}_S. \quad (9.4.1.2)$$

This V is the general version of the set of cables between W and Y in the example (9.1.2.4).

(4) Define

$$\phi_1 = \left(W \xrightarrow{f_1} V \xleftarrow[\text{inclusion}]{g_1} B \right) \in \text{UWD}_W^B \quad (9.4.1.3)$$

in which the restrictions of f_1 to the coproduct summands of W are defined as follows.

- $f_1 : B \longrightarrow B$ is the identity map.
- $f_1 : f^{-1}C_\varphi^{(2,0)} \longrightarrow C_\varphi^{(2,0)}$ is the map f .
- $f_1 : [f^{-1}c \setminus a_c]_\pm \longrightarrow [f^{-1}c \setminus a_c]$ is the fold map for each $c \in C_\varphi^{(\geq 3,0)} \sqcup C_\varphi^{\geq 3}$. That is, the restriction of f_1 to each of $[f^{-1}c \setminus a_c]_+$ and $[f^{-1}c \setminus a_c]_-$ is the identity map.

This ϕ_1 is the general version of that in the example (9.1.2.4).

(5) Define

$$\phi_2 = \left(A \xrightarrow[=]{f_2} A \xleftarrow{g_2} W \right) \in \text{UWD}_A^W \quad (9.4.1.4)$$

as follows. We will use the equality

$$B = g^{-1}C_\varphi^{(1,\geq 1)} \sqcup g^{-1}C_\varphi^{(\geq 2,\geq 1)}$$

which is true because $C_\varphi^{(0,\geq 0)} = \emptyset = C_\varphi^{(1,0)}$. For

$$w \in W = g^{-1}C_\varphi^{(1,\geq 1)} \sqcup g^{-1}C_\varphi^{(\geq 2,\geq 1)} \sqcup f^{-1}C_\varphi^{(2,0)} \sqcup \coprod_{c \in C_\varphi^{(\geq 3,0)} \sqcup C_\varphi^{\geq 3}} [f^{-1}c \setminus a_c]_\pm \in \text{Fin}_S \quad (9.4.1.5)$$

define

$$g_2(w) = \begin{cases} f^{-1}g(w) \in A & \text{if } w \in g^{-1}C_\varphi^{(1,\geq 1)}; \\ a_{g(w)} \in f^{-1}g(w) \subseteq A & \text{if } w \in g^{-1}C_\varphi^{(\geq 2,\geq 1)}; \\ w & \text{if } w \in f^{-1}C_\varphi^{(2,0)} \text{ or } w \in [f^{-1}c \setminus a_c]_+; \\ a_c \in f^{-1}c \subseteq A & \text{if } w \in [f^{-1}c \setminus a_c]_-. \end{cases}$$

In the first line of this definition, we used the fact that each cable in $C_\varphi^{(1,\geq 1)}$ has a unique f -preimage in A . In the second line, a_g was defined earlier in the current definition, using the fact $C_\varphi^{(\geq 2,\geq 1)} \subseteq C_\varphi^{\geq 3}$. This ϕ_2 is the general version of that in the example (9.1.2.4).


Remark 9.4.2. Consider the previous definition.

- (1) The input soldering function f_1 of ϕ_1 is surjective. Furthermore, all the cables in ϕ_1 are either (1, 1)-cables (namely, those cables in $B \subseteq V$) or (2, 0)-cables (namely, those in $V \setminus B$).
- (2) The output soldering function g_2 of ϕ_2 is surjective because of the assumption $C_\varphi^{(0, \geq 0)} = \emptyset = C_\varphi^{(1, 0)}$.

Theorem 9.4.3. *In the context of Def. 9.4.1, there is a decomposition*


$$\varphi = \phi_1 \circ \phi_2. \tag{9.4.3.1}$$

Proof. It suffices to check that the operadic composition $\phi_1 \circ \phi_2 \in \text{UWD}(\begin{smallmatrix} B \\ A \end{smallmatrix})$ is given by the cospan



in Fin_S . Here the two coproducts \sqcup are both indexed by all $c \in C_\varphi^{(\geq 3, 0)} \sqcup C_\varphi^{\geq 3}$. By the definition of $\circ = \circ_1$ (7.3.4.1), we just need to check that the rectangle is a pushout (Def. 7.2.1) in Fin_S . It follows from direct inspection of each coproduct summand of W in (9.4.1.5) that the rectangle is commutative.

Next, suppose given a solid-arrow commutative diagram



in Fin_S . We must show that there exists a unique map h that makes the diagram commutative. Recall that

$$C_\varphi = C_\varphi^{(1,1)} \sqcup C_\varphi^{(2,0)} \sqcup C_\varphi^{(\geq 3,0)} \sqcup C_\varphi^{\geq 3}$$

because $C_\varphi^{(0,\geq 0)} = \emptyset = C_\varphi^{(1,0)}$. Define $h : C_\varphi \longrightarrow U$ as

$$h(c) = \begin{cases} \alpha f^{-1}(c) & \text{if } c \in C_\varphi^{(1,1)}; \\ \beta(c) & \text{if } c \in C_\varphi^{(2,0)} \subseteq V; \\ \alpha(a_c) & \text{if } c \in C_\varphi^{(\geq 3,0)} \sqcup C_\varphi^{\geq 3}. \end{cases}$$

One checks by direct inspection that (i) $hf = \alpha$ and $hg_3 = \beta$ and that (ii) h is the only such map. \square

As we mentioned just before Def. 9.4.1, the decomposition (9.4.3.1) applies to $\psi_1 \in \text{UWD}(\frac{Y}{Z})$ defined in (9.2.2.2). In the next two sections, we will show that, up to name changes, ϕ_1 is generated by loops (Prop. 9.6.1), and ϕ_2 is generated by splits (Prop. 9.5.2).

9.5. Iterated Splits

The purpose of this section is to show that ϕ_2 (9.4.1.4) is either a name change or is generated by splits. First let us adopt the following convention, which is the undirected version of Convention 4.2.4.

Convention 9.5.1. Using the three elementary relations (8.2.3.1), (8.2.4.1), and (8.2.5.1), name changes (Def. 8.1.3) can always be rewritten on the outside (i.e., left side) of an iterated operadic composition in UWD. Moreover, using the elementary relation (8.2.1.1), an iteration of name changes can be composed down into just one name change. To simplify the presentation, in what follows these elementary relations regarding name changes are automatically applied wherever necessary. With this in mind, in the sequel we will mostly not mention name changes.

Recall from Remark 9.4.2 that in ϕ_2 (9.4.1.4), the input soldering function is the identity function and the output soldering function is surjective. So the following Proposition applies to ϕ_2 .

Proposition 9.5.2. *Suppose $A, B \in \text{Fin}_S$, and*

$$\rho = \left(A \xrightarrow[=]{f_\rho} A \xleftarrow[\text{surjective}]{g_\rho} B \right) \in \text{UWD}(\frac{B}{A}) \quad (9.5.2.1)$$

with $f_\rho = \text{Id}_A$ and g_ρ surjective.

(1) *If $A = \emptyset$, then $\rho = \mathbb{1}_\emptyset \in \text{UWD}(\frac{\emptyset}{\emptyset})$ (Def. 7.3.2).*


(2) *Suppose $A \neq \emptyset$.*

(i) *If g_ρ is a bijection, then ρ is a name change $\tau_{A,B}$.*

(ii) *Otherwise, ρ is an iterated operadic composition of splits (Def. 8.1.6).*

Proof. We will write f_ρ and g_ρ as f and g , respectively. If $A = \emptyset$, then ρ is the cospan $(\emptyset \longrightarrow \emptyset \longleftarrow \emptyset)$, which is the \emptyset -colored unit in UWD. Suppose $A \neq \emptyset$. If g is a bijection, then by definition g is the name change $\tau_{g^{-1}}$.

So suppose g is surjective but is not a bijection. We must show that ρ is an iterated operadic composition of splits. For the following constructions, the reader may keep the picture



of ρ in mind. The first step is to decompose ρ in such a way that each constituent undirected wiring diagram creates one group of output wires $g^{-1}a_i$. Decompose A as $A = A_1 \sqcup A_2 \in \text{Fin}_S$ in which

- $A_1 = \{a \in A : |g^{-1}a| = 1\}$;
- $A_2 = \{a \in A : |g^{-1}a| \geq 2\} = \{a_1, \dots, a_n\}$.

By assumption $A_2 \neq \emptyset$. To decompose ρ we will use the following intermediate boxes. For each $1 \leq i \leq n+1$, define

$$D_i = A_1 \sqcup \underbrace{\coprod_{1 \leq k < i} g^{-1}a_k}_{\emptyset \text{ if } i=1} \sqcup \underbrace{\{a_i, \dots, a_n\}}_{\emptyset \text{ if } i=n+1} \in \text{Fin}_S.$$

Note that $D_1 = A$ and $D_{n+1} \cong B$.

For $1 \leq i \leq n$ define

$$\rho_i = \left(D_i \xrightleftharpoons[f_i]{g_i} D_{i+1} \right) \in \text{UWD}_{D_i}^{(D_{i+1})} \quad (9.5.2.2)$$


in which, for $d \in D_{i+1}$,

$$g_i(d) = \begin{cases} a_i & \text{if } d \in g^{-1}a_i, \\ d & \text{otherwise.} \end{cases}$$

A direct inspection using Example 7.2.3 and Prop. 7.3.5 shows that, up to a name change, there is a decomposition

$$\rho = \rho_n \circ \dots \circ \rho_1 \in \text{UWD}_{A}^{(B)}. \quad (9.5.2.3)$$

When $n = 2$, this decomposition is depicted in the following picture.



To finish the proof, it suffices to show that each ρ_i is an iterated operadic composition of splits. We will prove this assertion in the next result. \square

Proposition 9.5.3. *Suppose $D \in \text{Fin}_S$, $D \not\sharp b \in S$, and*


$$\pi = \left(D \sqcup b \xrightarrow{=} D \sqcup b \xleftarrow{g} D \sqcup g^{-1}b \right) \in \text{UWD} \left(\begin{smallmatrix} D \sqcup g^{-1}b \\ D \sqcup b \end{smallmatrix} \right) \quad (9.5.3.1)$$

such that

- $g|_D = \text{Id}_D$ and
- $p = |g^{-1}b| \geq 2$.

Then π is an iterated operadic composition of $p - 1$ splits.

Proof. Write $g^{-1}b = \{b_1, \dots, b_p\}$, so a picture for π is as follows.



If $p = 2$ then π is the split $\sigma^{(D \sqcup \{b_1, b_2\}, b_1, b_2)}$ by definition.

Suppose $p \geq 3$. Then there is a decomposition of π into $p - 1$ splits as

$$\pi = \sigma^{(D \sqcup \{b_1, \dots, b_p\}, b_{p-1}, b_p)} \circ \dots \circ \sigma^{(D \sqcup \{b_1, b_{[2,p]}\}, b_1, b_{[2,p]})}. \quad (9.5.3.2)$$

Here each $b_{[j,p]}$ means the wires b_l for $j \leq l \leq p$ are identified into one element. Starting from the right, the j th split in the above decomposition of π , namely

$$\sigma^{(D \sqcup \{b_1, \dots, b_j, b_{[j+1,p]}\}, b_j, b_{[j+1,p]})} \in \text{UWD} \left(\begin{smallmatrix} D \sqcup \{b_1, \dots, b_j, b_{[j+1,p]}\} \\ D \sqcup \{b_1, \dots, b_{j-1}, b_{[j,p]}\} \end{smallmatrix} \right),$$

is the cospan

$$\begin{array}{ccc} & D \sqcup \{b_1, \dots, b_j, b_{[j+1,p]}\} & \\ & \downarrow & \\ D \sqcup \{b_1, \dots, b_{j-1}, b_{[j,p]}\} & \xrightarrow{=} & D \sqcup \{b_1, \dots, b_{j-1}, b_{[j,p]}\} \end{array}$$

in Fin_S . Here the output soldering function sends b_j and $b_{[j+1,p]}$ to $b_{[j,p]}$ and is the identity function everywhere else. \square

Example 9.5.4. For each $1 \leq i \leq n$ the undirected wiring diagram $\rho_i \in \text{UWD}_{D_i}^{(D_{i+1})}$ in (9.5.2.2) is of the form π (9.5.3.1) with

$$D = A_1 \sqcup \coprod_{1 \leq k < i} g^{-1} a_k \sqcup \{a_{i+1}, \dots, a_n\} \quad \text{and} \quad b = a_i.$$

Therefore, ρ in (9.5.2.3) is an iterated operadic composition of splits.

Example 9.5.5. In (9.5.3.2) above:

(1) If $p = 3$, then π decomposes into two splits as

$$\pi = \sigma^{(D \sqcup \{b_1, b_2, b_3\}, b_2, b_3)} \circ \sigma^{(D \sqcup \{b_1, b_{[2,3]}\}, b_1, b_{[2,3]})}.$$

(2) If $p = 4$, then π decomposes into three splits as

$$\pi = \sigma^{(D \sqcup \{b_1, b_2, b_3, b_4\}, b_3, b_4)} \circ \sigma^{(D \sqcup \{b_1, b_2, b_{[3,4]}\}, b_2, b_{[3,4]})} \circ \sigma^{(D \sqcup \{b_1, b_{[2,4]}\}, b_1, b_{[2,4]})}.$$

9.6. Iterated Loops

The purpose of this section is to show that ϕ_1 (9.4.1.3) is either a name change or is generated by loops (Def. 8.1.5). Recall Convention 9.5.1 regarding name changes. Also recall from Remark 9.4.2 that in ϕ_1 (9.4.1.3) each cable is either a $(1, 1)$ -cable or a $(2, 0)$ -cable. Therefore, the following result applies to ϕ_1 .

Proposition 9.6.1. *Suppose $A, B, C \in \text{Fin}_S$ and*

$$\xi = \left(A \xrightarrow{f} C \xleftarrow[\text{inclusion}]{g} B \right) \in \text{UWD}_{A}^{(B)}$$

in which each cable is either a $(1, 1)$ -cable or a $(2, 0)$ -cable. Suppose ξ has q $(2, 0)$ -cables. Then:

- (1) ξ is a name change if $q = 0$.
- (2) ξ is the iterated operadic composition of q loops (Def. 8.1.5) if $q \geq 1$.

Proof. Since ξ only has $(1, 1)$ -cables and $(2, 0)$ -cables, up to a name change we may write it as the cospan

$$\xi = \left(B \sqcup T_{\pm} \xrightarrow[\text{(Id, fold)}]{f} B \sqcup T \xleftarrow[\text{inclusion}]{g} B \right)$$


with:

- T the set of $(2, 0)$ -cables in ξ ;
- $f^{-1}T = T_{\pm} = T_{+} \sqcup T_{-}$ the coproduct of two copies of T .

If $q = 0$ (i.e., $T = \emptyset$), then ξ is the B -colored unit (Def. 7.3.2).

If $q = 1$ with $T = \{t\}$ and $T_{\pm} = \{t_{\pm}\}$, then ξ is the loop $\lambda_{(B \sqcup \{t_{\pm}\}, t_{\pm})}$ by definition.

Suppose $q \geq 2$. We may write $T = \{t^1, \dots, t^q\}$ and $T_{\pm} = \{t_{\pm}^1, \dots, t_{\pm}^q\}$. The picture



depicts a decomposition of ζ into two loops when $q = 2$. A direct inspection shows that there is a decomposition of ζ into q loops as

$$\zeta = \lambda_{(B \sqcup t_{\pm}^q, t_{\pm}^q)} \circ \cdots \circ \lambda_{(B \sqcup \{t_{\pm}^1, \dots, t_{\pm}^q\}, t_{\pm}^1)}. \quad (9.6.1.1)$$

Starting from the right, the j th loop in the above decomposition of ζ , namely

$$\lambda_{(B \sqcup \{t_{\pm}^j, \dots, t_{\pm}^q\}, t_{\pm}^j)} \in \text{UWD}_{(B \sqcup \{t_{\pm}^j, \dots, t_{\pm}^q\})}^{(B \sqcup \{t_{\pm}^{j+1}, \dots, t_{\pm}^q\})},$$

is the cospan

$$B \sqcup \{t_{\pm}^j, \dots, t_{\pm}^q\} \xrightarrow{t_{\pm}^j \mapsto t_{\pm}^j} B \sqcup \{t_{\pm}^{j+1}, \dots, t_{\pm}^q\} \sqcup t_{\pm}^j$$

$B \sqcup \{t_{\pm}^{j+1}, \dots, t_{\pm}^q\}$
 \downarrow inclusion

in Fin_S . Here the input soldering function sends t_{\pm}^j to t_{\pm}^j and is the identity function everywhere else. \square

Example 9.6.2. In (9.6.1.1) above:

- (1) If $q = 2$, then ζ decomposes into two loops as

$$\zeta = \lambda_{(B \sqcup t_{\pm}^2, t_{\pm}^2)} \circ \lambda_{(B \sqcup \{t_{\pm}^1, t_{\pm}^2\}, t_{\pm}^1)}.$$

- (2) If $q = 3$, then ζ decomposes into three loops as

$$\zeta = \lambda_{(B \sqcup t_{\pm}^3, t_{\pm}^3)} \circ \lambda_{(B \sqcup \{t_{\pm}^2, t_{\pm}^3\}, t_{\pm}^2)} \circ \lambda_{(B \sqcup \{t_{\pm}^1, t_{\pm}^2, t_{\pm}^3\}, t_{\pm}^1)}.$$

Finite Presentation for Undirected Wiring Diagrams

Fix a class S , with respect to which the Fin_S -colored operad UWD of undirected wiring diagrams is defined (Theorem 7.3.11). The main purpose of this chapter is to establish a finite presentation for the operad UWD; see Theorem 10.2.7. This means the following two statements.

- (1) The 6 generating undirected wiring diagrams (Def. 8.1.7) generate the operad UWD. This means that every undirected wiring diagram can be expressed as a finite iterated operadic composition involving only the 6 generators. See Theorem 10.1.10.
- (2) If an undirected wiring diagram can be operadically generated by the generators in two different ways, then there exists a finite sequence of *elementary equivalences* (Def. 10.2.1) from the first iterated operadic composition to the other one. See Theorem 10.2.7. An elementary equivalence is induced by either an elementary relation in UWD (Def. 8.2.18) or an operad associativity/unity axiom for the generators.

This finite presentation theorem for UWD is the undirected analogue of the finite presentation theorem for WD (Theorem 5.2.10). As in the directed case, this result leads to a finite presentation theorem for UWD-algebras, which we will discuss in Chapter 11.

We will continue to use Notation 3.3.1 for (iterated) operadic compositions.

10.1. Stratified Presentation

In this section, we define a *stratified presentation* in UWD and show that every undirected wiring diagram has a stratified presentation (Theorem 10.1.10). The following definition is the undirected analogue of Def. 5.1.1.

Definition 10.1.1. Suppose $n \geq 1$. An n -simplex Ψ and its *composition* $|\Psi| \in \text{UWD}$ are defined inductively as follows.

- (1) A 1-simplex is a generator (Def. 8.1.7) ψ . Its *composition* $|\psi|$ is defined as ψ itself.
- (2) Suppose $n \geq 2$ and that k -simplices for $1 \leq k \leq n-1$ and their compositions in UWD are already defined. An n -simplex in UWD is a tuple $\Psi = (\underline{\psi}, i, \underline{\phi})$ consisting of
 - an integer $i \geq 1$,
 - a p -simplex $\underline{\psi}$ for some $p \geq 1$, and
 - a q -simplex $\underline{\phi}$ for some $q \geq 1$

such that:

- (i) $p + q = n$;
- (ii) the operadic composition

$$|\Psi| \stackrel{\text{def}}{=} |\underline{\psi}| \circ_i |\underline{\phi}| \quad (10.1.1.1)$$

is defined in UWD (Def. 7.3.4).

The undirected wiring diagram $|\Psi|$ in (10.1.1.1) is the *composition* of Ψ .

A *simplex* in UWD is an m -simplex in UWD for some $m \geq 1$. We say that a simplex Ψ is a *presentation* of the undirected wiring diagram $|\Psi|$.

Remark 10.1.2. To simplify the presentation, as in Notation 5.1.2, we will sometimes use either

- the right side of (10.1.1.1) or
- even just the list of generators (ψ_1, \dots, ψ_n) in a simplex in the order in which they appear in (10.1.1.1)

to denote a simplex in UWD.

Example 10.1.3. Elementary relations in UWD (Def. 8.2.18) provide a large source of simplices in UWD. In fact, each side, either left or right, of each elementary relation in UWD is a simplex. For example:

- (1) The elementary relation (8.2.6.1) says that the 3-simplex

$$\lambda_{(Y,x,y)} \circ (\theta_{(X,y)} \circ_2 \omega_y)$$

and the 2-simplex

$$\lambda_{(Y,x,y)} \circ \sigma^{(Y,x,y)}$$

have the same composition.

(2) The elementary relation (8.2.7.1) says that the 4-simplex

$$\lambda_{(W,w,y)} \circ \sigma^{(W,x,w)} \circ \left(\theta_{(X,y)} \circ_2 \omega_y \right)$$

and the 1-simplex $(\mathbb{1}_X)$ have the same composition. In other words, the former has composition $\mathbb{1}_X$.

Example 10.1.4. In (8.3.1.1) we considered the 5-simplex

$$\lambda_{(X,x_1,x_2)} \circ \left[\left(\left(\theta_{(\emptyset,X)} \circ_2 \theta_{(x_1,x_2)} \right) \circ_2 \omega_{x_1} \right) \circ_2 \omega_{x_2} \right],$$

whose composition has a wasted cable.

Example 10.1.5. In (8.3.2.1) we considered the 5-simplex

$$\lambda_{(Y \sqcup X, x_1, x_2)} \circ \left[\left(\left(\theta_{(Y,X)} \circ_2 \theta_{(x_1,x_2)} \right) \circ_2 \omega_{x_1} \right) \circ_2 \omega_{x_2} \right],$$

whose composition also has a wasted cable.

Definition 10.1.6. A *stratified simplex* in UWD is a simplex in UWD (Def. 10.1.1) of one of the following two forms:

- (1) (ϵ) , where $\epsilon \in \text{UWD}^{(\emptyset)}$ is the empty cell (Def. 8.1.1).
- (2) $(\tau, \underline{\lambda}, \underline{\sigma}, \underline{\theta}, \underline{\omega})$, where:
 - τ is a name change (Def. 8.1.3);
 - $\underline{\lambda}$ is a possibly empty string of loops (Def. 8.1.5);
 - $\underline{\sigma}$ is a possibly empty string of splits (Def. 8.1.6);
 - $\underline{\theta}$ is a possibly empty string of 2-cells (Def. 8.1.4);
 - $\underline{\omega}$ is a possibly empty string of 1-output wires (Def. 8.1.2).

We call these stratified simplices of type (1) and of type (2), respectively. If Ψ is a stratified simplex in UWD, then we call it a *stratified presentation* of the undirected wiring diagram $|\Psi|$.

Remark 10.1.7. The composition of a stratified simplex of type (2) cannot be the empty cell ϵ . Indeed, if the composition of a stratified simplex of type (2) is in $\text{UWD}^{(\emptyset)}$, then 1-output wires must be involved. So the composition must have at least one cable, and it cannot be the empty cell.

Example 10.1.8. In (8.3.2.1) and (8.3.3.1) we gave two stratified presentations of the undirected wiring diagram $\zeta_Y \in \text{UWD}^{\binom{Y}{Y}}$ in Example 8.3.2.

Example 10.1.9. In (9.1.2.5) we gave a stratified presentation of the undirected wiring diagram $\varphi \in \text{UWD}^{\binom{Y}{x_1, x_2}}$.

We now observe that the generators generate the operad UWD of undirected wiring diagrams in a highly structured way.

Theorem 10.1.10. *Every undirected wiring diagram admits a stratified presentation.*

Proof. Suppose ψ is an undirected wiring diagram. If ψ is the empty cell ϵ (Def. 8.1.1), then (ϵ) is a stratified presentation of ψ . So let us now assume that ψ is not the empty cell. We will show that it admits a stratified presentation of type (2). We remind the reader of Convention 9.5.1.

Combining (9.2.3.1) and (9.4.3.1), there is a decomposition

$$\psi = \phi_1 \circ \phi_2 \circ \psi_2.$$

In this decomposition:

- The undirected wiring diagram ψ_2 either is a colored unit or has a stratified presentation $(\underline{\theta}, \underline{\omega})$ by Lemma 9.3.4 and Corollary 9.3.6.
- The undirected wiring diagram ϕ_2 either is a name change or has a stratified presentation $(\underline{\sigma})$ by Prop. 9.5.2.
- The undirected wiring diagram ϕ_1 either is a name change or has a stratified presentation $(\underline{\lambda})$ by Prop. 9.6.1.

By the above three statements, ψ has a stratified presentation of type (2). □

10.2. Elementary Equivalences

The purpose of this section is to establish the second part of the finite presentation theorem for the operad UWD of undirected wiring diagrams. Recall the 17 elementary relations in UWD (Def. 8.2.18). In what follows, we will regard each operad associativity or unity axiom as an equality. The following definition is the undirected analogue of Def. 5.2.1.

Definition 10.2.1. Suppose Ψ is an n -simplex in UWD as in Def. 10.1.1.

- (1) A *subsimplex* of Ψ is a simplex in UWD defined inductively as follows.
 - If Ψ is a 1-simplex, then a *subsimplex* of Ψ is Ψ itself.
 - Suppose $n \geq 2$ and $\Psi = (\underline{\psi}, i, \underline{\phi})$ for some $i \geq 1$, p -simplex $\underline{\psi}$, and q -simplex $\underline{\phi}$ with $p + q = n$. Then a *subsimplex* of Ψ is
 - a subsimplex of $\underline{\psi}$,
 - a subsimplex of $\underline{\phi}$, or
 - Ψ itself.

If Ψ' is a subsimplex of Ψ , then we write $\Psi' \subseteq \Psi$.

- (2) An *elementary subsimplex* Ψ' of Ψ is a subsimplex of one of two forms:

- (i) Ψ' is one side (either left or right) of a specified elementary relation in UWD (Def. 8.2.18).
- (ii) Ψ' is one side (either left or right) of a specified operad associativity or unity axiom—(2.1.4.3), (2.1.4.4), (2.1.4.5), or (2.1.4.6)—involving only the generators in UWD (Def. 8.1.7).
- (3) Suppose Φ is another simplex in UWD. Then Ψ and Φ are said to be *equivalent* if their compositions are equal; i.e., $|\Psi| = |\Phi| \in \text{UWD}$.
- (4) Suppose:
- $\Psi' \subseteq \Psi$ is an elementary subsimplex corresponding to one side of R , which is either an elementary relation or an operad associativity/unity axiom for the generators in UWD.
 - Ψ'' is the simplex given by the other side of R .
 - Ψ^1 is the simplex obtained from Ψ by replacing the subsimplex Ψ' by Ψ'' .
- We say that Ψ and Ψ^1 are *elementarily equivalent*. Note that elementarily equivalent simplices are also equivalent.
- (5) If Ψ and Φ are elementarily equivalent, we write $\Psi \sim \Phi$ and call this an *elementary equivalence*.
- (6) Suppose Ψ_0, \dots, Ψ_r are simplices in UWD for some $r \geq 1$ and that there exist elementary equivalences

$$\Psi_0 \sim \Psi_1 \sim \dots \sim \Psi_r.$$

Then we say that Ψ_0 and Ψ_r are *connected by a finite sequence of elementary equivalences*. Note that in this case Ψ_0 and Ψ_r are equivalent.

Example 10.2.2. By definition, for each elementary relation in UWD (Def. 8.2.18), the simplices given by its two sides are elementarily equivalent. For example:

- (1) By the elementary relation (8.2.6.1), replacing an elementary subsimplex of the form

$$\lambda_{(Y,x,y)} \circ (\theta_{(X,y)} \circ_2 \omega_y)$$

by one of the form

$$\lambda_{(Y,x,y)} \circ \sigma^{(Y,x,y)}$$

yields an elementary equivalence.

- (2) By the elementary relation (8.2.7.1), replacing an elementary subsimplex of the form

$$\lambda_{(W,w,y)} \circ \sigma^{(W,x,w)} \circ (\theta_{(X,y)} \circ_2 \omega_y)$$

by the colored unit $\mathbb{1}_X$ yields an elementary equivalence.

Example 10.2.3. In Example 8.3.4, we observed that for the undirected wiring diagram $\zeta_Y \in \text{UWD}(Y)$ in Example 8.3.2, the stratified presentations (8.3.2.1) and (8.3.3.1) are connected by a finite sequence of elementary equivalences.

Convention 10.2.4. As in Convention 5.2.6, to simplify the presentation, elementary equivalences corresponding to an operad associativity/unity axiom—(2.1.4.3), (2.1.4.4), (2.1.4.5), or (2.1.4.6)—for the generators in UWD (Def. 8.1.7) will often be applied tacitly wherever necessary.

The goal of this section is to show that any two equivalent simplices in UWD are connected by a finite sequence of elementary equivalences. The first step is to show that every simplex in UWD is connected to a stratified simplex (Def. 10.1.6) in the following sense. The following observation is the undirected analogue of Lemma 5.2.7.

Lemma 10.2.5. *Every simplex in UWD is either a stratified simplex (Def. 10.1.6) or is connected to an equivalent stratified simplex by a finite sequence of elementary equivalences (Def. 10.2.1).*

Proof. Suppose Ψ is a simplex in UWD that is not a stratified simplex. Using the three elementary relations (8.2.3.1)–(8.2.5.1), first we move all the name changes (Def. 3.1.3) in Ψ , if there are any, to the left. Then we use the elementary relation (8.2.1.1) repeatedly to compose them down into one name change. Therefore, after a finite sequence of elementary equivalences, we may assume that there is at most one name change in Ψ , which is the left-most entry. If there are further elementary equivalences later that create name changes, we will perform the same procedure without explicitly mentioning it.

The empty cell $\epsilon \in \text{UWD}(\emptyset)$ (Def. 8.1.1) and a 1-output wire $\omega_* \in \text{UWD}(\ast)$ (Def. 8.1.2) have no input boxes, so no operadic composition of the forms $\epsilon \circ_i -$ or $\omega_* \circ_i -$ can be defined. Therefore, after a finite sequence of elementary equivalences corresponding to the operad horizontal associativity axiom (2.1.4.3), we may assume that Ψ has the form

$$\left(\tau, \Psi^1, \underline{\epsilon}, \underline{\omega} \right).$$

Here:

- τ is a name change;
- all the 1-output wires $\underline{\omega}$ are at the right-most entries;
- all the empty cells $\underline{\epsilon}$ are just to their left;
- Ψ^1 is either empty or is a subsimplex involving 2-cells (Def. 8.1.4), loops (Def. 8.1.5), and splits (Def. 8.1.6).

Next we use the elementary relations (8.2.9.1)–(8.2.12.1) to move all the 2-cells in Ψ to just the left of $\underline{\epsilon}$. Then we use the elementary relations (8.2.15.1) and

(8.2.17.1) to move all the remaining loops to just the right of the name change τ . So after a finite sequence of elementary equivalences, we may assume that the simplex Ψ has the form

$$(\tau, \underline{\lambda}, \underline{\sigma}, \underline{\theta}, \underline{\epsilon}, \underline{\omega}). \quad (10.2.5.1)$$

If the string $\underline{\epsilon}$ of empty cells is empty, then we are done because this is now a stratified simplex of type (2).

So suppose the string $\underline{\epsilon}$ of empty cells in (10.2.5.1) is non-empty. Using finitely many elementary equivalences corresponding to the elementary relations (8.2.8.1)–(8.2.10.1), we may cancel all the unnecessary empty cells in (10.2.5.1). If there are no empty cells left after the cancellation, then we have a stratified simplex of type (2).

Suppose that, after the cancellation in the previous paragraph, the resulting string $\underline{\epsilon}$ of empty cells is still non-empty. Then it must contain a single empty cell ϵ , and there are no 2-cells $\underline{\theta}$ and no 1-output wires $\underline{\omega}$ in the resulting simplex Ψ . Since the output box of ϵ is the empty box, the current simplex Ψ cannot have any loops $\underline{\lambda}$ or splits $\underline{\sigma}$. Therefore, in this case the simplex (10.2.5.1) has the form

$$(\tau, \epsilon).$$

Since the output box of ϵ is the empty box \emptyset , this name change τ must be the colored unit $\mathbb{1}_{\emptyset}$. So by the operad left unity axiom (2.1.4.5), the simplex $(\mathbb{1}_{\emptyset}, \epsilon)$ is elementarily equivalent to (ϵ) , which is a stratified simplex of type (1). \square

The next step is to show that equivalent stratified simplices are connected. The following observation is the undirected analogue of Lemmas 5.2.8 and 5.2.9.

Lemma 10.2.6. *Any two equivalent stratified simplices (Def. 10.1.6) in UWD are either equal or are connected by a finite sequence of elementary equivalences (Def. 10.2.1).*

Proof. Suppose Ψ^1 and Ψ^2 are equivalent stratified simplices in UWD. By Remark 10.1.7 Ψ^1 and Ψ^2 are both of type (1) or both of type (2). If they are both of type (1), then they are both equal to (ϵ) by definition. So let us now assume that Ψ^1 and Ψ^2 are distinct but equivalent stratified simplices of type (2) in UWD. The rest of the proof is similar to that of Lemma 5.2.9 and consists of a series of reductions.

Write $\psi \in \text{UWD}(\underline{X})$ for the common composition of Ψ^1 and Ψ^2 . Using elementary equivalences corresponding to

- the operad unity axioms (2.1.4.5) and (2.1.4.6),
- the elementary relations (8.2.7.1) and (8.2.8.1) regarding colored units, and
- other elementary relations in UWD that move the generators around the stratified simplices,

we may assume that there are no unnecessary generators in these stratified simplices. Here *unnecessary* refers to either a colored unit or generators whose (iterated) operadic composition is a colored unit. If ψ itself is a name change τ , then at this stage both Ψ^1 and Ψ^2 are equal to the 1-simplex (τ) . So let us now assume that ψ is not a name change.

The name change τ^1 in Ψ^1 has output box Y , and the same is true for the name change τ^2 in Ψ^2 . We may actually assume that the input boxes of τ^1 and of τ^2 are also equal, provided that we change the output boxes of other generators in Ψ^2 accordingly by a name change if necessary. Such changes correspond to elementary equivalences coming from the operad unity and associativity axioms and the elementary relation (8.2.1.1). Using finitely many elementary equivalences, we may therefore assume that τ^1 is equal to τ^2 . So we may as well assume that there are no name changes in the two stratified simplices Ψ^i . At this stage, each stratified simplex Ψ^i has the form

$$(\underline{\lambda}^i, \underline{\sigma}^i, \underline{\theta}^i, \underline{\omega}^i).$$

Using finitely many elementary equivalences corresponding to the elementary relation (8.2.6.1) and other elementary relations that move the generators around, we may assume that in the simplices Ψ^1 and Ψ^2 all the $(1,0)$ -cables in ψ are created as in the left side of (8.2.6.1), i.e., as $(\lambda, \theta, \omega)$ rather than as (λ, σ) . In plain language, this means that every $(1,0)$ -cable in ψ is created in both Ψ^i by applying a loop to a 1-output wire and some other wire, rather than by applying a loop to a split.

Similarly, using Example 8.3.4 and finitely many elementary equivalences, we may further assume that every wasted cable in ψ is created in both simplices Ψ^i as $(\lambda, \theta, \theta, \omega, \omega)$ as in (8.3.2.1), rather than as $(\lambda, \sigma, \theta, \omega)$ as in (8.3.3.1). In plain language, this means that every wasted cable in ψ is created in both Ψ^i by applying a loop to two 1-output wires, as in the first picture after (8.3.2.1).

Recall that each 1-output wire ω is a 0-ary element in UWD, while loops and splits are unary. Therefore, by the operad associativity axioms (2.1.4.3) and (2.1.4.4), we may assume that in each simplex Ψ^i , the right portion $(\underline{\theta}^i, \underline{\omega}^i)$ is a subsimplex. By the above reductions, at this stage the two simplices $(\underline{\theta}^1, \underline{\omega}^1)$ and $(\underline{\theta}^2, \underline{\omega}^2)$ are uniquely determined by ψ and have the same composition. In fact, each simplex $(\underline{\theta}^i, \underline{\omega}^i)$ has composition ψ_2 (9.2.2.3). Using finitely many elementary equivalences corresponding to the elementary relations (8.2.9.1) and (8.2.10.1) and the operad associativity axioms, we may now assume that the simplices $(\underline{\theta}^1, \underline{\omega}^1)$ and $(\underline{\theta}^2, \underline{\omega}^2)$ are equal.

Similarly, at this stage the simplices $(\underline{\lambda}^1, \underline{\sigma}^1)$ and $(\underline{\lambda}^2, \underline{\sigma}^2)$ both have composition ψ_1 (9.2.2.2). Using finitely many elementary equivalences corresponding to the elementary relations (8.2.13.1)–(8.2.17.1) and the operad vertical associativity axiom (2.1.4.4), we may now assume that the simplices $(\underline{\lambda}^1, \underline{\sigma}^1)$ and $(\underline{\lambda}^2, \underline{\sigma}^2)$ are equal. \square

We are now ready for the finite presentation theorem for undirected wiring diagrams. It describes the operad UWD of undirected wiring diagrams (Theorem 7.3.11) in terms of finitely many generators and finitely many relations.

Theorem 10.2.7. *Consider the operad UWD of undirected wiring diagrams.*

- (1) *Every undirected wiring diagram can be obtained from finitely many generators (Def. 8.1.7) via iterated operadic compositions (Def. 2.1.4).*
- (2) *Any two equivalent simplices in UWD are either equal or are connected by a finite sequence of elementary equivalences (Def. 10.2.1).*

Proof. The first statement is a special case of Theorem 10.1.10. The second statement is a combination of Lemma 10.2.5 twice and Lemma 10.2.6. \square

Algebras of Undirected Wiring Diagrams

The main purpose of this chapter is to provide a finite presentation theorem for algebras over the operad UWD of undirected wiring diagrams (Theorem 7.3.11). As in the case of wiring diagrams (Theorem 6.2.2), this finite presentation for UWD-algebras is a consequence of the finite presentation for the operad UWD (Theorem 10.2.7). This finite presentation allows us to reduce the understanding of a UWD-algebra to just a few basic structure maps and a small number of easy-to-check axioms. We will illustrate this point further with the relational algebra of a set and the typed relational algebra.

In Section 11.1 we first define a UWD-algebra in terms of 6 generating structure maps and 17 generating axioms corresponding to the generators (Def. 8.1.7) and the elementary relations (Def. 8.2.18) in UWD. Then we observe that this finite presentation for a UWD-algebra is in fact equivalent to the general definition (Def. 6.1.2) of a UWD-algebra (Theorem 11.1.2). This is an application of the finite presentation theorem for the operad UWD (Theorem 10.2.7).

In Section 11.2 we provide, for each set A , a finite presentation for the UWD-algebra called the relational algebra of A (Theorem 11.2.5). In its original form, the relational algebra was the main algebra example in [Spi13]. In [Spi13] Spivak pointed out that the relational algebra of a set and its variant called the typed relational algebra, to be discussed in Section 11.4, have applications in digital circuits, machine learning, and database theory.

In Section 11.3 we prove a rigidity property of the relational algebra of a set (Theorem 11.3.3). It says that a given map of sets is a bijection precisely when it

induces a map between the two relational algebras. The motivation for this rigidity property comes from [Spi13] Section 3, where several examples suggest that there are very few interesting maps out of the relational algebra of a set. In fact, in [Spi13] Conjecture 3.1.6, Spivak conjectured that the relational algebra of any set is quotient-free. Although our rigidity result does not prove Spivak's conjecture in its full generality, it adds further evidence that the conjecture should be true.

In Section 11.4 we consider a generalization of the relational algebra of a set, called the typed relational algebra. We observe that, similar to the relational algebra of a set, the typed relational algebra has a finite presentation (Theorem 11.4.7). In its original form, the typed relational algebra was first defined in [Spi13] Section 4.

11.1. Finite Presentation for Algebras

The main purpose of this section is to prove a finite presentation theorem for UWD-algebras. We first define a UWD-algebra in terms of a finite number of generators and relations. Immediately afterwards we will show that this definition agrees with the general definition of an operad algebra (Def. 6.1.2) when the operad is UWD.

Fix a class S , with respect to which the Fin_S -colored operad UWD of undirected wiring diagrams is defined (Theorem 7.3.11).

Definition 11.1.1. A UWD-algebra A consists of the following data.

- (1) For each $X \in \text{Fin}_S$, A is equipped with a set A_X called the X -colored entry of A .
- (2) It is equipped with the following 6 *generating structure maps* corresponding to the generators in UWD (Def. 8.1.7).
 - (i) Corresponding to the empty cell $\epsilon \in \text{UWD}(\emptyset)$ (Def. 8.1.1), it has a structure map

$$* \xrightarrow{\epsilon} A_\emptyset, \quad (11.1.1.1)$$

i.e., a chosen element in A_\emptyset .

- (ii) Corresponding to each 1-output wire $\omega_* \in \text{UWD}(*)$ (Def. 8.1.2), it has a structure map

$$* \xrightarrow{\omega_*} A_*, \quad (11.1.1.2)$$

i.e., a chosen element in A_* .

- (iii) Corresponding to each name change $\tau_f \in \text{UWD}(X^Y)$ (Def. 8.1.3), it has a structure map

$$A_X \xrightarrow{\tau_f} A_Y \quad (11.1.1.3)$$

that is, furthermore, the identity map if f is the identity map on X .

- (iv) Corresponding to each 2-cell $\theta_{(X,Y)} \in \text{UWD}(\frac{X \sqcup Y}{X,Y})$ (Def. 8.1.4), it has a structure map

$$A_X \times A_Y \xrightarrow{\theta_{(X,Y)}} A_{X \sqcup Y} . \quad (11.1.1.4)$$

- (v) Corresponding to each loop $\lambda_{(X,x_{\pm})} \in \text{UWD}(\frac{X \setminus x_{\pm}}{X})$ (Def. 8.1.5), it has a structure map

$$A_X \xrightarrow{\lambda_{(X,x_{\pm})}} A_{X \setminus x_{\pm}} . \quad (11.1.1.5)$$

- (vi) Corresponding to each split $\sigma^{(X,x_1,x_2)} \in \text{UWD}(\frac{X}{X'})$ (Def. 8.1.6), it has a structure map

$$A_{X'} \xrightarrow{\sigma^{(X,x_1,x_2)}} A_X . \quad (11.1.1.6)$$

The following 17 diagrams, called the *generating axioms*, which correspond to the elementary relations in UWD (Def. 8.2.18), are required to be commutative.

- (1) In the setting of (8.2.1.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\tau_f} & A_Y \\ & \searrow \tau_{gf} & \downarrow \tau_g \\ & & A_Z \end{array}$$

is commutative.

- (2) In the setting of (8.2.2.1), the diagram

$$\begin{array}{ccc} * & \xrightarrow{\omega_x} & A_x \\ & \searrow \omega_y & \downarrow \tau_{x,y} \\ & & A_y \end{array}$$

is commutative.

- (3) In the setting of (8.2.3.1), the diagram

$$\begin{array}{ccc} A_{X_1} \times A_{X_2} & \xrightarrow{\theta_{(X_1,X_2)}} & A_{X_1 \sqcup X_2} \\ (\tau_{f_1}, \tau_{f_2}) \downarrow & & \downarrow \tau_{f_1 \sqcup f_2} \\ A_{Y_1} \times A_{Y_2} & \xrightarrow{\theta_{(Y_1,Y_2)}} & A_{Y_1 \sqcup Y_2} \end{array}$$

is commutative.

(4) In the setting of (8.2.4.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\lambda_{(X,x_{\pm})}} & A_{X \setminus x_{\pm}} \\ \tau_f \downarrow & & \downarrow \tau_{f'} \\ A_Y & \xrightarrow{\lambda_{(Y,y_{\pm})}} & A_{Y \setminus y_{\pm}} \end{array}$$

is commutative.

(5) In the setting of (8.2.5.1), the diagram

$$\begin{array}{ccc} A_{X'} & \xrightarrow{\sigma^{(X,x_1,x_2)}} & A_X \\ \tau_{f'} \downarrow & & \downarrow \tau_f \\ A_{Y'} & \xrightarrow{\sigma^{(Y,y_1,y_2)}} & A_Y \end{array}$$

is commutative.

(6) In the setting of (8.2.6.1), the diagram

$$\begin{array}{ccc} A_X \times * \cong A_X & \xrightarrow{\sigma^{(Y,x,y)}} & A_Y \\ (\text{Id}, \omega_y) \downarrow & & \downarrow \lambda_{(Y,x,y)} \\ A_X \times A_y & \xrightarrow{\theta_{(X,y)}} & A_Y \xrightarrow{\lambda_{(Y,x,y)}} & A_W \end{array} \quad (11.1.1.7)$$

is commutative.

(7) In the setting of (8.2.7.1), the diagram

$$\begin{array}{ccccc} A_X \cong A_X \times * & \xrightarrow{(\text{Id}, \omega_y)} & A_X \times A_y & \xrightarrow{\theta_{(X,y)}} & A_Y \\ \text{Id} \downarrow & & & & \downarrow \sigma^{(W,x,w)} \\ A_X & \xleftarrow{\lambda_{(W,w,y)}} & & & A_W \end{array}$$

is commutative.

(8) In the setting of (8.2.8.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\cong} & A_X \times * \\ \text{Id} \downarrow & & \downarrow (\text{Id}, \epsilon) \\ A_X & \xleftarrow{\theta_{(X,\emptyset)}} & A_X \times A_{\emptyset} \end{array}$$

is commutative.

(9) In the setting of (8.2.9.1), the diagram

$$\begin{array}{ccc}
 A_X \times A_Y \times A_Z & \xrightarrow{(\text{Id}, \theta_{(Y,Z)})} & A_X \times A_{Y \sqcup Z} \\
 (\theta_{(X,Y)}, \text{Id}) \downarrow & & \downarrow \theta_{(X,Y \sqcup Z)} \\
 A_{X \sqcup Y} \times A_Z & \xrightarrow{\theta_{(X \sqcup Y, Z)}} & A_{X \sqcup Y \sqcup Z}
 \end{array} \tag{11.1.1.8}$$

is commutative.

(10) In the setting of (8.2.10.1), the diagram

$$\begin{array}{ccc}
 A_Y \times A_X & \xrightarrow{\text{permute}} & A_X \times A_Y \\
 \theta_{(Y,X)} \downarrow & & \downarrow \theta_{(X,Y)} \\
 A_{Y \sqcup X} & \xrightarrow{=} & A_{X \sqcup Y}
 \end{array} \tag{11.1.1.9}$$

is commutative.

(11) In the setting of (8.2.11.1), the diagram

$$\begin{array}{ccc}
 A_X \times A_Y & \xrightarrow{\theta_{(X,Y)}} & A_{X \sqcup Y} \\
 (\text{Id}, \lambda_{(Y, Y_\pm)}) \downarrow & & \downarrow \lambda_{(X \sqcup Y, Y_\pm)} \\
 A_X \times A_{Y'} & \xrightarrow{\theta_{(X, Y')}} & A_{X \sqcup Y'}
 \end{array}$$

is commutative.

(12) In the setting of (8.2.12.1), the diagram

$$\begin{array}{ccc}
 A_X \times A_{Y'} & \xrightarrow{\theta_{(X, Y')}} & A_{X \sqcup Y'} \\
 (\text{Id}, \sigma^{(Y, Y_1, Y_2)}) \downarrow & & \downarrow \sigma^{(X \sqcup Y, Y_1, Y_2)} \\
 A_X \times A_Y & \xrightarrow{\theta_{(X, Y)}} & A_{X \sqcup Y}
 \end{array}$$

is commutative.

(13) In the setting of (8.2.13.1), the diagram

$$\begin{array}{ccc}
 A_{X'} & \xrightarrow{\sigma^{(Y, Y_1, Y_2)}} & A_Y \\
 \sigma^{(Z, z_1, z_2)} \downarrow & & \downarrow \sigma^{(X, z_1, z_2)} \\
 A_Z & \xrightarrow{\sigma^{(X, Y_1, Y_2)}} & A_X
 \end{array}$$

is commutative.

(14) In the setting of (8.2.14.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\sigma^{(Y_2, y_1, y_2, 3)}} & A_{Y_2} \\ \sigma^{(Y_1, y_1, 2, y_3)} \downarrow & & \downarrow \sigma^{(Y, y_2, y_3)} \\ A_{Y_1} & \xrightarrow{\sigma^{(Y, y_1, y_2)}} & A_Y \end{array}$$

is commutative.

(15) In the setting of (8.2.15.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\lambda_{(X, x_{\pm})}} & A_{X'} \\ \sigma^{(Y', y_1, y_2)} \downarrow & & \downarrow \sigma^{(Y, y_1, y_2)} \\ A_{Y'} & \xrightarrow{\lambda_{(Y', x_{\pm})}} & A_Y \end{array}$$

is commutative.

(16) In the setting of (8.2.16.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\sigma^{(W, y, x_-)}} & A_W \\ \sigma^{(W, y, x_+)} \downarrow & & \downarrow \lambda_{(W, x_{\pm})} \\ A_W & \xrightarrow{\lambda_{(W, x_{\pm})}} & A_Y \end{array}$$

is commutative.

(17) In the setting of (8.2.17.1), the diagram

$$\begin{array}{ccc} A_X & \xrightarrow{\lambda_{(X, x_3, x_4)}} & A_Z \\ \lambda_{(X, x_1, x_2)} \downarrow & & \downarrow \lambda_{(Z, x_1, x_2)} \\ A_W & \xrightarrow{\lambda_{(W, x_3, x_4)}} & A_Y \end{array}$$

is commutative.

This finishes the definition of a UWD-algebra.

At this moment we have two definitions of a UWD-algebra.

- On the one hand, in Def. 6.1.2 with $O = \text{UWD}$, a UWD-algebra has a structure map μ_{ζ} (6.1.1.1) for each undirected wiring diagram $\zeta \in \text{UWD}$. This structure map satisfies the associativity axiom (6.1.2.1) for a general operadic composition in UWD, together with the unity and the equivariance axioms in Def. 6.1.1.
- On the other hand, in Def. 11.1.1 a UWD-algebra has 6 generating structure maps and satisfies 17 generating axioms.

We now observe that these two definitions are equivalent, so UWD-algebras indeed have a finite presentation as in Def. 11.1.1.

Theorem 11.1.2. *For the operad UWD of undirected wiring diagrams (Theorem 7.3.11), Def. 6.1.2 with $\mathcal{O} = \text{UWD}$ and Def. 11.1.1 of a UWD-algebra are equivalent.*

Proof. This proof proceeds as in the proof of Theorem 6.2.2. First suppose (A, μ) is a UWD-algebra in the sense of Def. 6.1.2. To see that it is also a UWD-algebra in the sense of Def. 11.1.1, first note that the structure map μ_γ (6.1.1.1) gives the 6 generating structure maps (11.1.1.1)–(11.1.1.6). Moreover, the generating structure map μ_{1_x} (11.1.1.3) is the identity map by the unity axiom (6.1.1.3).

The generating axiom (11.1.1.9) is a special case of the equivariance diagram (6.1.1.4), so it is commutative. Each of the other 16 generating axioms corresponds to an elementary relation in UWD that describes two different ways to construct the same undirected wiring diagram as an iterated operadic composition of generators in UWD. Each such generating axiom asserts that the two corresponding compositions of generating structure maps—defined using the composition in the diagram (6.1.2.1)—are equal. The associativity axiom (6.1.2.1) of (A, μ) applied twice guarantees that two such compositions are indeed equal.

Conversely, suppose A is a UWD-algebra in the sense of Def. 11.1.1, so it has 6 generating structure maps that satisfy 17 generating axioms. We must show that it is a UWD-algebra in the sense of Def. 6.1.2 For an undirected wiring diagram $\psi \in \text{UWD}$ with a presentation Ψ (Def. 10.1.1), we define its structure map μ_ψ (6.1.1.1) inductively as follows.

- (1) If Ψ is a 1-simplex, then $\Psi = (\psi)$, and ψ is a generator in UWD by definition. In this case, we define μ_ψ as the corresponding generating structure map (11.1.1.1)–(11.1.1.6) of A .
- (2) Inductively, suppose Ψ is an n -simplex for some $n \geq 2$, so $\Psi = (\Phi, i, \Theta)$ for some $i \geq 1$, p -simplex Φ , and q -simplex Θ with $p + q = n$. Since $1 \leq p, q < n$, by the induction hypothesis, the structure maps $\mu_{|\Phi|}$ and $\mu_{|\Theta|}$ are already defined. Then we define the structure map

$$\mu_\psi = \mu_{|\Phi|} \circ_i \mu_{|\Theta|} \tag{11.1.2.1}$$

as in Notation 6.1.3.

By Theorem 10.1.10 every undirected wiring diagram has a stratified presentation, hence a presentation. To see that the structure map μ_ψ as above is well-defined, we need to show that the map μ_ψ is independent of the choice of a presentation Ψ . Any two presentations of an undirected wiring diagram are by definition equivalent simplices. By Theorem 10.2.7(2) (= the relations part of the finite presentation theorem for UWD), any two equivalent simplices in UWD are either equal or are connected by a finite sequence of elementary equivalences. Therefore, it

suffices to show that every elementary equivalence in UWD yields a commutative diagram involving the generating structure maps of A , where \circ_i is interpreted as in Notation 6.1.3. Recall from Def. 10.2.1 that an elementary equivalence comes from either an elementary relation in UWD or an operad associativity/unity axiom for the generators in UWD.

It follows from a direct inspection that the operad associativity and unity axioms—(2.1.4.3), (2.1.4.4), (2.1.4.5), and (2.1.4.6)—for the generators yield commutative diagrams involving the generating structure maps of A . In fact, the diagrams involving the horizontal and the vertical associativity axioms (2.1.4.3) and (2.1.4.4) are commutative because composition of functions is associative. The diagrams for the two unity axioms (2.1.4.5) and (2.1.4.6) are commutative because the generating structure map for a colored unit (11.1.1.3) is required to be the identity map.

By definition each of the 17 generating axioms of A corresponds to an elementary relation (Def. 8.2.18) and is a commutative diagram. Therefore, the structure map μ_ψ for each wiring diagram ψ is well-defined.

It remains to check that the structure map μ satisfies the required unity, equivariance, and associativity axioms. The unity axiom (6.1.1.3) holds because it is part of the assumption on the generating structure map corresponding to a name change (11.1.1.3).

The associativity axiom (6.1.2.1) holds because the structure map μ_ψ is defined above (11.1.2.1) by requiring that the diagram (6.1.2.1) be commutative.

For the equivariance axiom (6.1.1.4), first note that it is enough to check it when the undirected wiring diagram in question is an iterated operadic composition of 2-cells. This is because 2-cells are the only binary generators in UWD (Remark 8.1.8). All other generators are either 0-ary or unary, for which equivariance is trivial.

So now suppose ζ in the equivariance axiom (6.1.1.4) is an iterated operadic composition of 2-cells. If ζ is a 2-cell and the permutation σ is the transposition $(1\ 2) \in \Sigma_2$, then the equivariance axiom (6.1.1.4) is true by the generating axiom (11.1.1.9). The general case now follows from this special case using:

- the generating axiom (11.1.1.8) corresponding to the associativity property of 2-cells (8.2.9.1);
- the operad associativity axioms (2.1.4.3) and (2.1.4.4) when applied to 2-cells;
- the fact that the transpositions $(i, i + 1)$ for $1 \leq i \leq n - 1$ generate the symmetric group Σ_n .

So (A, μ) is a UWD-algebra in the sense of Def. 6.1.2. □

Remark 11.1.3. The proofs of the finite presentation theorems 11.1.2 and 6.2.2 for UWD-algebras and WD-algebras are almost identical. In fact, it is not difficult to formulate and prove a more general result that has both of these finite presentation theorems as special cases. Such a result would say that, if an operad O has a finite presentation (i.e., specific finite sets of generators and generating relations expressed in terms of simplices and elementary equivalences similar to Def. 10.1.1 and 10.2.1), then O -algebras have a corresponding finite presentation. We purposely chose not to present the material this way in order to avoid the higher level of abstraction that is unnecessary for actual applications of (undirected) wiring diagrams. Although the context is slightly different, the formulation and proof of such a finite presentation theorem for O -algebras can be extracted from the Strong Biased Definition Theorem in [YJ15] page 193.

11.2. Finite Presentation for the Relational Algebra

The purpose of this section is to provide an illustration of Theorem 11.1.2, the finite presentation theorem of UWD-algebras, using the relational algebra. This algebra was originally introduced as the main algebra example in [Spi13] using Def. 6.1.1. We will describe the relational algebra in terms of 6 generating structure maps and 17 generating axioms. First we need some notations.

Definition 11.2.1. Suppose A and X are sets.

- (1) $A^X = \text{Set}(X, A)$ is the set of functions $X \longrightarrow A$.
- (2) An element $u \in A^X$ is called an X -vector in A , and $u(x) \in A$ is called the x -entry of u for $x \in X$.
- (3) $\wp(X) = \{T \subseteq X\}$ is the set of subsets of X , called the *power set* of X .
- (4) $\text{Rel}_A(X) = \wp(A^X)$ is the power set of the set A^X of X -vectors in A .

Example 11.2.2. Suppose A, B, X, Y are sets and $*$ is a one-element set.

- (1) Since $A^\emptyset = *$, it follows that

$$\text{Rel}_A(\emptyset) = \wp(*) = \{\emptyset, *\}. \quad (11.2.2.1)$$

- (2) Since $A^* = A$, it follows that

$$\text{Rel}_A(*) = \wp(A), \quad (11.2.2.2)$$

the power set of A .

- (3) There is a canonical bijection

$$A^X \times A^Y \cong A^{X \sqcup Y}. \quad (11.2.2.3)$$

- (4) Suppose $h : X \longrightarrow Y$ is a function.

- (i) There is an induced map $h^* : A^Y \longrightarrow A^X$ sending each map $Y \longrightarrow A$ to the composition of $X \longrightarrow Y \longrightarrow A$; i.e., h^* is pre-composition with h .
- (ii) Likewise, there is an induced map

$$\text{Rel}_A(Y) \xrightarrow{h^*} \text{Rel}_A(X) \quad (11.2.2.4)$$

given by pre-composition with h .

- (5) Suppose $p : A \longrightarrow B$ is a function.
 - (i) There is an induced map $p_* : A^X \longrightarrow B^X$ sending each map $X \longrightarrow A$ to the composition $X \longrightarrow A \longrightarrow B$; i.e., p_* is post-composition with p .
 - (ii) Likewise, there is an induced map

$$\text{Rel}_A(X) \xrightarrow{p_*} \text{Rel}_B(X) \quad (11.2.2.5)$$

given by post-composition with p .

Assumption 11.2.3. Throughout this section, S is the one-element set. So $\text{Fin}_S = \text{Fin}$ is the collection of finite sets, and UWD is a Fin -colored operad (Theorem 7.3.11).

We now define the relational algebra in terms of finitely many generating structure maps and generating axioms.

Definition 11.2.4. Suppose A is a set. The *relational algebra of A* , denoted Rel_A , is the UWD-algebra in the sense of Def. 11.1.1 defined as follows.

- (1) For each finite set X , the X -colored entry is

$$\text{Rel}_A(X) = \wp(A^X)$$

as in Def. 11.2.1.

- (2) Its 6 generating structure maps are defined as follows.
 - (i) For the empty cell $\epsilon \in \text{UWD}(\emptyset)$ (Def. 8.1.1), the chosen element in $\text{Rel}_A(\emptyset) = \{\emptyset, *\}$ (11.2.2.1) is $*$.
 - (ii) For a 1-output wire $\omega_* \in \text{UWD}(\ast)$ (Def. 8.1.2), the chosen element in $\text{Rel}_A(\ast) = \wp(A)$ (11.2.2.2) is A .
 - (iii) For a bijection $f : X \longrightarrow Y \in \text{Fin}$ and the name change $\tau_f \in \text{UWD}(\overset{Y}{X})$ (Def. 8.1.3), the generating structure map is the pre-composition map (11.2.2.4)

$$\text{Rel}_A(X) \xrightarrow{\tau_f = (f^{-1})^*} \text{Rel}_A(Y) .$$

In other words, each X -vector in A is reindexed as a Y -vector in A using the bijection f .

- (iv) For a 2-cell $\theta_{(X,Y)} \in \text{UWD}_{(X,Y)}^{(X \amalg Y)}$ (Def. 8.1.4), the generating structure map is defined using the bijection (11.2.2.3) as follows.

$$\begin{array}{ccc} \text{Rel}_A(X) \times \text{Rel}_A(Y) & & (U \subseteq A^X, V \subseteq A^Y) \\ \downarrow \theta_{(X,Y)} & & \downarrow \\ \text{Rel}_A(X \amalg Y) & & (U \times V \subseteq A^X \times A^Y \cong A^{X \amalg Y}) \end{array}$$

In other words, concatenate every given X -vector with every given Y -vector to form an $(X \amalg Y)$ -vector.

- (v) For a loop $\lambda_{(X,x_{\pm})} \in \text{UWD}_{(X,x_{\pm})}^{(X \setminus x_{\pm})}$ (Def. 8.1.5), the generating structure map is defined as

$$\begin{array}{ccc} \text{Rel}_A(X) & & (U \subseteq A^X) \\ \downarrow \lambda_{(X,x_{\pm})} & & \downarrow \\ \text{Rel}_A(X \setminus x_{\pm}) & & \{u_{\setminus x_{\pm}} : u \in U, u(x_+) = u(x_-)\} \subseteq A^{X \setminus x_{\pm}} \end{array} \quad (11.2.4.1)$$

in which $u_{\setminus x_{\pm}}$ is the composition

$$X \setminus x_{\pm} \xrightarrow{\text{inclusion}} X \xrightarrow{u} A.$$

In other words, for a given subset of X -vectors in A , look for those whose x_+ -entry and x_- -entry are equal, and then delete these two entries to form a subset of $(X \setminus x_{\pm})$ -vectors.

- (vi) For a split $\sigma^{(X,x_1,x_2)} \in \text{UWD}_{(X')}^{(X)}$ (Def. 8.1.6), denote by $p : X \rightarrow X'$ the projection map that sends both $x_1, x_2 \in X$ to $x \in X'$ and is the identity function everywhere else. The generating structure map is defined as the pre-composition map (11.2.2.4)

$$\text{Rel}_A(X') \xrightarrow{\sigma^{(X,x_1,x_2)} = p^*} \text{Rel}_A(X).$$

In other words, for a given subset of X' -vectors in A , use the x -entry for both the x_1 -entry and the x_2 -entry to form a subset of X -vectors.

The following observation is the finite presentation theorem for the relational algebra of a set.

Theorem 11.2.5. *For each set A , the relational algebra Rel_A in Def. 11.2.4 is actually a UWD-algebra in the sense of Def. 11.1.1, hence also in the sense of Def. 6.1.2 by Theorem 11.1.2.*

Proof. We need to check that Rel_A satisfies the 17 generating axioms in Def. 11.1.1. Due to the simplicity of the 6 generating structure maps, all the generating axioms can be checked by a direct inspection. For example, the generating axiom (11.1.1.7),

which corresponds to the elementary relation (8.2.6.1), is the assertion that the diagram

$$\begin{array}{ccc} \text{Rel}_A(X) \times * \cong \text{Rel}_A(X) & \xrightarrow{\sigma^{(Y,x,y)}} & \text{Rel}_A(Y) \\ (\text{Id}, \omega_y) \downarrow & & \downarrow \lambda^{(Y,x,y)} \\ \text{Rel}_A(X) \times \text{Rel}_A(y) & \xrightarrow{\theta^{(X,y)}} \text{Rel}_A(Y) \xrightarrow{\lambda^{(Y,x,y)}} & \text{Rel}_A(W) \end{array}$$

is commutative, where $X = Y \setminus y$ and $W = Y \setminus \{x, y\} = X \setminus x$. For each element

$$(U \subseteq A^X) \in \text{Rel}_A(X),$$

one can check that both compositions in the above diagram send U to the element

$$\left\{ W \xrightarrow{\text{inclusion}} X \xrightarrow{u} A : u \in U \right\} \subseteq A^W$$

in $\text{Rel}_A(W)$. The other 16 generating axioms are checked similarly. \square

Remark 11.2.6. To see that our relational algebra Rel_A in Def. 11.2.4 agrees with the one in [Spi13] Example 2.2.10, note that the latter is based on Def. 6.1.1, which is equivalent to Def. 6.1.2. A direct inspection of [Spi13] Eq. (11) reveals that Spivak's structure map of Rel_A , when applied to the 6 generators in UWD (Def. 8.1.7), reduces to our generating structure maps in Def. 11.2.4. Theorem 11.2.5 then guarantees that the two definitions of the relational algebra Rel_A —i.e., our Def. 11.2.4 and [Spi13] Example 2.2.10—are equivalent.

11.3. Spivak's Conjecture: Rigidity of the Relational Algebra

The purpose of this section is to partially verify a conjecture in [Spi13] (Conjecture 3.1.6) that states that the relational algebra Rel_A in Def. 11.2.4 is quotient-free. To state this conjecture, we first need the definition of a map between operad algebras. Recall from Section 6.1 the definition of an operad algebra.

Definition 11.3.1. Suppose O is an S -colored operad, and (A, μ^A) and (B, μ^B) are O -algebras. A map of O -algebras $f : A \longrightarrow B$ consists of a collection of maps

$$\left\{ A_c \xrightarrow{f_c} B_c : c \in S \right\}$$

that is compatible with the structure maps in the following sense.

Compatibility with Structure Maps: For each $d \in S$, $\underline{c} = (c_1, \dots, c_n) \in \text{Prof}(S)$, and $\zeta \in O(\underline{c})$, the diagram

$$\begin{array}{ccc} \prod_{i=1}^n A_{c_i} & \xrightarrow{\prod f_{c_i}} & \prod_{i=1}^n B_{c_i} \\ \mu_{\zeta}^A \downarrow & & \downarrow \mu_{\zeta}^B \\ A_d & \xrightarrow{f_d} & B_d \end{array} \quad (11.3.1.1)$$

is commutative.

Furthermore, we call f an *isomorphism* if there exists a map of O-algebras $g : B \longrightarrow A$ such that $gf = \text{Id}_A$ and $fg = \text{Id}_B$. If such a map g exists, then it is necessarily unique.

The following conjecture regarding the relational algebra is [Spi13] (Conjecture 3.1.6). Since we are talking about the relational algebra, here S is a one-element set, and UWD is a Fin-colored operad.

Conjecture 11.3.2. Suppose:

- A is a set, and Rel_A is the relational algebra of A in Def. 11.2.4.
- $f : \text{Rel}_A \longrightarrow B$ is a map of UWD-algebras.

Then at least one of the following two statements holds.

- (1) f is an isomorphism.
- (2) B_X is a one-element set for each finite set X .

Roughly speaking this conjecture states that there are no interesting maps out of any relational algebra. In the following observation, we will verify Conjecture 11.3.2 in the special case when the map $\text{Rel}_A \longrightarrow B$ is induced by a map of sets out of A .

Theorem 11.3.3. Suppose $f : A \longrightarrow B$ is a map of sets. Then the following statements are equivalent.

- (1) f is a bijection of sets.
- (2) The post-composition maps $f_* : \text{Rel}_A(X) \longrightarrow \text{Rel}_B(X)$ (11.2.2.5), with X running through all the finite sets, form an isomorphism of UWD-algebras.
- (3) The post-composition maps $f_* : \text{Rel}_A(X) \longrightarrow \text{Rel}_B(X)$, with X running through all the finite sets, form a map of UWD-algebras.

Proof. The implications (1) \implies (2) \implies (3) are both immediate from the definitions. It remains to check the implication (3) \implies (1). So let us now assume that $f_* : \text{Rel}_A \longrightarrow \text{Rel}_B$ is a map of UWD-algebras. This means that the diagram

$$\begin{array}{ccc}
 \prod_{i=1}^n \text{Rel}_A(X_i) & \xrightarrow{\prod f_{X_i}} & \prod_{i=1}^n \text{Rel}_B(X_i) \\
 \mu_\zeta^A \downarrow & & \downarrow \mu_\zeta^B \\
 \text{Rel}_A(Y) & \xrightarrow{f_Y} & \text{Rel}_B(Y)
 \end{array} \tag{11.3.3.1}$$

is commutative for each $\zeta \in \text{UWD}(\underline{Y})$ with $\underline{X} = (X_1, \dots, X_n)$. We will consider two special cases, which will show that f is surjective and injective.

- (1) To show that f is surjective, consider a 1-output wire $\omega_* \in \text{UWD}(\ast)$ (Def. 8.1.2). In this case, the commutative diagram (11.3.3.1) becomes the diagram

$$\begin{array}{ccc} \ast & \xrightarrow{=} & \ast \\ \omega_*^A \downarrow & & \downarrow \omega_*^B \\ \text{Rel}_A(\ast) = \wp(A) & \xrightarrow{f_*} & \wp(B) = \text{Rel}_B(\ast) \end{array}$$

in which

$$\omega_*^A(\ast) = A \in \wp(A) \quad \text{and} \quad \omega_*^B(\ast) = B \in \wp(B)$$

by Def. 11.2.4. The bottom horizontal map f_* is post-composition with f , so it sends each subset $U \subseteq A$ to its image $f(U) \subseteq B$. Therefore, the commutativity of the above diagram forces

$$f(A) = f_*(A) = B,$$

so f is surjective.

- (2) To show that f is injective, we argue by contradiction. So suppose there exist distinct elements $a_+, a_- \in A$ such that $f(a_+) = f(a_-) \in B$. We will show that this assumption leads to a contradiction. Consider the loop $\lambda_{(A, a_\pm)} \in \text{UWD}(\overset{A \setminus a_\pm}{A})$ (Def. 8.1.5). In this case, the commutative diagram (11.3.3.1) becomes the diagram

$$\begin{array}{ccc} \text{Rel}_A(A) & \xrightarrow{f_*} & \text{Rel}_B(A) \\ \lambda_{(A, a_\pm)} \downarrow & & \downarrow \lambda_{(A, a_\pm)} \\ \text{Rel}_A(A \setminus a_\pm) & \xrightarrow{f_*} & \text{Rel}_B(A \setminus a_\pm) \end{array} \quad (11.3.3.2)$$

in which both horizontal maps f_* are post-composition with f . Consider the element

$$U = \left\{ A \xrightarrow{=} A \right\} \in \text{Rel}_A(A) = \wp(A^A),$$

which is the single-element set consisting of the identity map of A . We will show that the two compositions in (11.3.3.2) do not agree at U .

On the one hand, since $a_+ \neq a_-$, applying the left vertical map to U yields

$$\lambda_{(A, a_\pm)}(U) = \emptyset \subseteq A^{A \setminus a_\pm}$$

by the definition of the generating structure map for a loop (11.2.4.1). Applying the bottom horizontal map f_* in (11.3.3.2) yields

$$f_* \lambda_{(A, a_\pm)}(U) = \emptyset \subseteq B^{A \setminus a_\pm}.$$

On the other hand, applying the top horizontal map f_* to U yields

$$f_*(U) = \left\{ A \xrightarrow{f} B \right\} \in \text{Rel}_B(A) = \wp(B^A),$$

which is the single-element set consisting of the map f . Since $f(a_+) = f(a_-)$, applying the right vertical map now yields the single-element set

$$\lambda_{(A, a_{\pm})} f_*(U) = \left\{ A \setminus a_{\pm} \xrightarrow{\text{inclusion}} A \xrightarrow{f} B \right\} \subseteq B^{A \setminus a_{\pm}}$$

by (11.2.4.1). Since this is not empty, the two compositions in the commutative diagram (11.3.3.2) do not agree at the element U . This is a contradiction, so the map f is injective. □

11.4. Finite Presentation for the Typed Relational Algebra

The relational algebra Rel_A in Def. 11.2.4 has a fixed set A as the set of potential values in each coordinate in an X -vector (Def. 11.2.1). There is a more general version of the relational algebra, called the typed relational algebra, in which each coordinate in an X -vector has its own set of potential values. The typed relational algebra was first introduced in [Spi13] (Section 4) using Def. 6.1.1. In this section, we observe that the typed relational algebra also has a finite presentation, similar to the one for the relational algebra in Theorem 11.2.5.

Assumption 11.4.1. Throughout this section, S is the collection of sets, so UWD is the Fin_{Set} -colored operad of undirected wiring diagrams (Theorem 7.3.11).

Definition 11.4.2. Suppose $(X, v) \in \text{Fin}_{\text{Set}}$ (Def. 2.2.3), so X is a finite set and $v : X \rightarrow \text{Set}$ assigns to each $x \in X$ a set $v(x)$.

- (1) Define the set

$$X_v = \prod_{x \in X} v(x) \tag{11.4.2.1}$$

in which an empty product, for the case $X = \emptyset$, means the one-point set.

- (2) An element in X_v is also called an X -vector.
 (3) For $x \in X$, the x -entry of an X -vector u is denoted by u_x .

As before, we will omit writing v in (X, v) if there is no danger of confusion.

Example 11.4.3. Suppose A is a set and $(X, v) \in \text{Fin}_{\text{Set}}$ such that $v(x) = A$ for all $x \in X$. Then

$$X_v = \prod_{x \in X} A = A^X$$

as in Def. 11.2.1

Example 11.4.4. Each map $f : (X, v) \longrightarrow (Y, v) \in \text{Fin}_{\text{Set}}$ induces a map

$$Y_v = \prod_{y \in Y} v(y) \xrightarrow{f_v} \prod_{x \in X} v(x) = X_v . \quad (11.4.4.1)$$

For $(a_y)_{y \in Y} \in Y_v$ with each $a_y \in v(y)$, its image is defined as

$$f_v \left((a_y)_{y \in Y} \right) = (a_{f(x)})_{x \in X}$$

using the fact that $a_{f(x)} \in v(f(x)) = v(x)$. If A is a set and $v(y) = v(x) = A$ for all $y \in Y$ and $x \in X$, then f_v is the pre-composition map in Example 11.2.2. In what follows, a map induced by the map f_v will often be denoted by f_v as well.

We now define the typed relational algebra in terms of finitely many generating structure maps and generating axioms.

Definition 11.4.5. The *typed relational algebra* Rel is the UWD-algebra in the sense of Def. 11.1.1 defined as follows.

- (1) For each $(X, v) \in \text{Fin}_{\text{Set}}$, the X -colored entry is

$$\text{Rel}(X) = \wp(X_v)$$

with X_v as in (11.4.2.1) and $\wp(-)$ the power set (Def. 11.2.1).

- (2) Its 6 generating structure maps are defined as follows.

- (i) For the empty cell $\epsilon \in \text{UWD}(\emptyset)$ (Def. 8.1.1), the chosen element in

$$\text{Rel}(\emptyset) = \wp(\emptyset_v) = \wp(*) = \{\emptyset, *\}$$

is $*$.

- (ii) For a 1-output wire $\omega_x \in \text{UWD}(x)$ (Def. 8.1.2), the chosen element in $\text{Rel}(x) = \wp(v(x))$ is $v(x)$.

- (iii) For a bijection $f : X \longrightarrow Y \in \text{Fin}_{\text{Set}}$ and the name change $\tau_f \in \text{UWD}(X)$ (Def. 8.1.3), the generating structure map is the bijection

$$\text{Rel}(X) = \wp(X_v) \xrightarrow{\tau_f = f_v^{-1}} \wp(Y_v) = \text{Rel}(Y)$$

induced by f_v^{-1} as in (11.4.4.1).

- (iv) For a 2-cell $\theta_{(X,Y)} \in \text{UWD}(X \amalg Y)$ (Def. 8.1.4), the generating structure map is defined as follows.

$$\begin{array}{ccc} \text{Rel}(X) \times \text{Rel}(Y) & & (U \subseteq X_v, V \subseteq Y_v) \\ \downarrow \theta_{(X,Y)} & & \downarrow \\ \text{Rel}(X \amalg Y) & & (U \times V \subseteq X_v \times Y_v \cong (X \amalg Y)_v) \end{array}$$

- (v) For a loop $\lambda_{(X, x_{\pm})} \in \text{UWD}(\frac{X \setminus x_{\pm}}{X})$ (Def. 8.1.5), the generating structure map is defined as

$$\begin{array}{ccc} \text{Rel}(X) & & (U \subseteq X_v) \\ \downarrow \lambda_{(X, x_{\pm})} & & \downarrow \\ \text{Rel}(X \setminus x_{\pm}) & & \{u_{\setminus x_{\pm}} : u \in U, u_{x_+} = u_{x_-}\} \subseteq (X \setminus x_{\pm})_v \end{array} \quad (11.4.5.1)$$

in which $u_{\setminus x_{\pm}}$ is obtained from u by deleting the x_{\pm} -entries. In other words, if $\iota : (X \setminus x_{\pm}) \longrightarrow X$ is the inclusion map, then

$$u_{\setminus x_{\pm}} = \iota_v(u),$$

provided $u_{x_+} = u_{x_-}$, where ι_v is as in (11.4.4.1).

- (vi) For a split $\sigma^{(X, x_1, x_2)} \in \text{UWD}(\frac{X}{X'})$ (Def. 8.1.6), denote by $p : X \longrightarrow X'$ the projection map that sends both $x_1, x_2 \in X$ to $x \in X'$ and is the identity function everywhere else. The generating structure map is the map

$$\text{Rel}(X') \xrightarrow{\sigma^{(X, x_1, x_2)} = p_v} \text{Rel}(X)$$

induced by p_v in (11.4.4.1). In other words, $\sigma^{(X, x_1, x_2)}$ takes each X' -vector u in any given subset of X' -vectors to the X -vector whose x_1 -entry and x_2 -entry are both equal to the x -entry of u , and all other entries remain the same.

Example 11.4.6. Suppose A is a set and $(X, v) \in \text{Fin}_{\text{Set}}$ such that $v(x) = A$ for all $x \in X$. Then

$$\text{Rel}(X) = \wp(X_v) = \wp(A^X) = \text{Rel}_A(X),$$

the X -colored entry of the relational algebra of A (Def. 11.2.4). Furthermore, if in Def. 11.4.5 all the value assignments v take the constant value A , then the 6 generating structure maps of Rel reduce to those of Rel_A in Def. 11.2.4.

The following observation is the finite presentation theorem for the typed relational algebra.

Theorem 11.4.7. *The typed relational algebra Rel in Def. 11.4.5 is actually a UWD-algebra in the sense of Def. 11.1.1, hence also in the sense of Def. 6.1.2 by Theorem 11.1.2.*

Proof. As in the proof of Theorem 11.2.5 for the relational algebra of A , we just need to check that Rel satisfies the 17 generating axioms in Def. 11.1.1. Due to the simplicity of the 6 generating structure maps, all the generating axioms can be checked by a direct inspection. For example, the generating axiom (11.1.1.7), which

corresponds to the elementary relation (8.2.6.1), is the assertion that the diagram

$$\begin{array}{ccc}
 \text{Rel}(X) \times * \cong \text{Rel}(X) & \xrightarrow{\sigma^{(Y,x,y)}} & \text{Rel}(Y) \\
 (\text{Id}, \omega_y) \downarrow & & \downarrow \lambda^{(Y,x,y)} \\
 \text{Rel}(X) \times \text{Rel}(y) & \xrightarrow{\theta_{(X,y)}} \text{Rel}(Y) \xrightarrow{\lambda_{(Y,x,y)}} & \text{Rel}(W)
 \end{array}$$

is commutative, where $X = Y \setminus y$ and $W = Y \setminus \{x, y\} = X \setminus x$. For each element

$$\left(U \subseteq X_v = \prod v(x) \right) \in \text{Rel}(X),$$

one can check that both compositions in the above diagram send U to the element

$$\left\{ \iota_v(u) : u \in U \right\} \subseteq W_v$$

in $\text{Rel}(W)$, where $\iota : W \rightarrow X$ is the inclusion map and ι_v is as in (11.4.4.1). The other 16 generating axioms are checked similarly. \square

Remark 11.4.8. To see that our relational algebra Rel in Def. 11.4.5 agrees with the one in [Spi13] Section 4, note that the latter is based on Def. 6.1.1, which is equivalent to Def. 6.1.2. A direct inspection of [Spi13] Lemma 4.1.2 reveals that Spivak's structure map of Rel , when applied to the 6 generators in UWD (Def. 8.1.7), reduces to our generating structure maps in Def. 11.4.5. Theorem 11.4.7 then guarantees that the two definitions of the relational algebra Rel —i.e., our Def. 11.4.5 and [Spi13] Section 4—are equivalent.

Part 3

Maps Between Operads of Wiring Diagrams

So far we have considered four operads constructed from wiring diagrams and undirected wiring diagrams:

- (1) the Box_S -colored operad of wiring diagrams WD (Theorem 2.3.8);
- (2) the Box_S -colored operad of normal wiring diagrams WD_\bullet (Prop. 5.3.5);
- (3) the Box_S -colored operad of strict wiring diagrams WD_0 (Prop. 5.4.6);
- (4) the Fin_S -colored operad of undirected wiring diagrams UWD (Theorem 7.3.11).

The purpose of this part is to study maps between these operads. We will show that there is a commutative diagram

$$\begin{array}{ccccc}
 \text{WD}_0 & \longrightarrow & \text{WD}_\bullet & \longrightarrow & \text{WD} \\
 & \searrow \chi^0 & \downarrow \chi & \swarrow \rho & \\
 & & \text{UWD} & &
 \end{array}$$

of operad maps, in which the horizontal maps are operad inclusions. All the operad maps in this diagram except ρ are discussed in Chapter 12. The operad map ρ is discussed in Chapter 13. The existence of such operad maps implies that:

- Every UWD -algebra induces a WD -algebra along ρ .
- Every WD -algebra restricts to a WD_\bullet -algebra.
- Every WD_\bullet -algebra restricts to a WD_0 -algebra.

For each of the three operad maps that end at UWD , we will compute precisely the image. An undirected wiring diagram is in the image of

- χ^0 if and only if its cables are either $(1, 1)$ -cables or $(2, 0)$ -cables;
- χ if and only if it has no $(0, 0)$ -cables and no $(0, \geq 2)$ -cables.

Furthermore, the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ is surjective, so every undirected wiring diagram is the ρ -image of some wiring diagram. Delay nodes play a crucial role in the surjectivity of the operad map ρ .

Map from Normal to Undirected Wiring Diagrams

This chapter has three main purposes.

- (1) We show that there exists an operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ from the operad WD_\bullet of normal wiring diagrams to the operad UWD of undirected wiring diagrams. See Theorem 12.2.4. Recall that a normal wiring diagram is a wiring diagram with no delay nodes. Intuitively, the map χ is given by forgetting directions.
- (2) We compute precisely the image of the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ in Theorem 12.4.1. An undirected wiring diagram is in the image of χ if and only if it has no wasted cables and no $(0, \geq 2)$ -cables.
- (3) We consider the restriction $\chi^0 : \text{WD}_0 \longrightarrow \text{UWD}$ of the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ to the operad WD_0 of strict wiring diagrams and compute precisely its image in Theorem 12.5.1. An undirected wiring diagram is in the image of χ^0 if and only if its cables are either $(1, 1)$ -cables or $(2, 0)$ -cables.

In Theorem 13.1.4 we will extend the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ to an operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ defined for all wiring diagrams. Furthermore, we will show in Theorem 13.3.3 that the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ is surjective.

In Section 12.1 we define a map of operads and observe that there are inclusions of operads $\text{WD}_0 \longrightarrow \text{WD}_\bullet \longrightarrow \text{WD}$. Furthermore, if the underlying class S

changes, then there are corresponding maps of operads for each of the four operads of (undirected) wiring diagrams.

Section 12.2 contains the first main result Theorem 12.2.4 of this chapter. It says that there is a map of operads $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ defined by forgetting directions.

In Section 12.3 we provide a series of examples to illustrate the operad map χ .

Section 12.4 contains the second main result Theorem 12.4.1 of this chapter. This result identifies precisely the image of the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ as consisting of the undirected wiring diagrams with no wasted cables and no $(0, \geq 2)$ -cables.

In Section 12.5 we consider the restriction of the operad map χ to the operad WD_0 of strict wiring diagrams. Recall that a strict wiring diagram is a wiring diagram with no delay nodes and whose supplier assignment is a bijection. In Theorem 12.5.1 we will show that the image of the operad map $\text{WD}_0 \longrightarrow \text{UWD}$ consists of precisely the undirected wiring diagrams with only $(1, 1)$ -cables and $(2, 0)$ -cables.

12.1. Operad Maps

In this section, we define an operad map and record some obvious maps among the various operads of (undirected) wiring diagrams (Prop. 12.1.7 and 12.1.9). Recall from Def. 2.1.4 the definition of an S -colored operad.

Definition 12.1.1. Suppose O is an S -colored operad and P is a T -colored operad. A map of operads, also called an *operad map*, $f : O \longrightarrow P$ consists of a pair of maps (f_0, f_1) as follows.

- (1) $f_0 : S \longrightarrow T$, called the *color map*.
- (2) For each $d \in S$ and $\underline{c} = (c_1, \dots, c_n) \in \text{Prof}(S)$ with $n \geq 0$, it has a map, called an *entry map*,

$$O_{\underline{c}}^{(d)} \xrightarrow{f_1} P_{f\underline{c}}^{(fd)}$$

in which $fd = f_0d \in T$ and $f\underline{c} = (f_0c_1, \dots, f_0c_n) \in \text{Prof}(T)$.

We will usually write both f_0 and f_1 as f . These maps are required to preserve the operad structure in the sense that the following three conditions hold.

Preservation of Equivariance: For each $(\underline{c}) \in \text{Prof}(S) \times S$ as above and permutation $\sigma \in \Sigma_n$, the diagram

$$\begin{array}{ccc} \mathcal{O}(\underline{c}) & \xrightarrow{f} & \mathcal{P}(f_{\underline{c}}^d) \\ \sigma \downarrow \cong & & \cong \downarrow \sigma \\ \mathcal{O}(\underline{c\sigma}) & \xrightarrow{f} & \mathcal{P}(f_{\underline{c\sigma}}^d) \end{array} \quad (12.1.1.1)$$

is commutative, in which $f_{\underline{c}\sigma} = (f_{c_{\sigma(1)}}, \dots, f_{c_{\sigma(n)}})$.

Preservation of Colored Units: For each $c \in S$,

$$f\mathbb{1}_c = \mathbb{1}_{f_c} \quad (12.1.1.2)$$

in which $\mathbb{1}_c \in \mathcal{O}(\underline{c})$ is the c -colored unit in \mathcal{O} and $\mathbb{1}_{f_c} \in \mathcal{P}(f_c)$ is the (f_c) -colored unit in \mathcal{P} .

Preservation of Operadic Composition: For each $(\underline{c}) \in \text{Prof}(S) \times S$ with $|\underline{c}| \geq 1$, $\underline{b} \in \text{Prof}(S)$, and $1 \leq i \leq |\underline{c}|$, the diagram

$$\begin{array}{ccc} \mathcal{O}(\underline{c}) \times \mathcal{O}(\underline{c}_i) & \xrightarrow{(f,f)} & \mathcal{P}(f_{\underline{c}}^d) \times \mathcal{P}(f_{\underline{c}_i}^{c_i}) \\ \circ_i \downarrow & & \downarrow \circ_i \\ \mathcal{O}(\underline{c\circ_i}) & \xrightarrow{f} & \mathcal{P}(f_{\underline{c\circ_i}}^d) \end{array} \quad (12.1.1.3)$$

is commutative.

Definition 12.1.2. Suppose \mathcal{O} is an S -colored operad and \mathcal{P} is a T -colored operad.

- (1) A map of operads $f : \mathcal{O} \longrightarrow \mathcal{P}$ is called an *operad inclusion* if the color map $f_0 : S \longrightarrow T$ and all the entry maps f_1 are inclusions.
- (2) If there exists an operad inclusion $\mathcal{O} \longrightarrow \mathcal{P}$, then we call \mathcal{O} a *sub-operad* of \mathcal{P} .

Example 12.1.3. With the one-point set $*$ as the set of color, there is an operad \mathcal{T} in which every entry $\mathcal{T}(\underline{*, \dots, *}) = *$. Then for each colored operad \mathcal{O} , there exists a unique map of operads $\mathcal{O} \longrightarrow \mathcal{T}$. In category theoretical terms, \mathcal{T} is a *terminal object* in the category of all colored operads.

Example 12.1.4. There is an operad \mathcal{I} with the empty set as its set of color, and \mathcal{I} has no entries because it has no colors. Then for each colored operad \mathcal{O} , there exists a unique operad inclusion $\mathcal{I} \longrightarrow \mathcal{O}$. In category theoretical terms, \mathcal{I} is an *initial object* in the category of all colored operads.

Example 12.1.5. Suppose $f : \mathcal{O} \longrightarrow \mathcal{P}$ and $g : \mathcal{P} \longrightarrow \mathcal{Q}$ are maps of operads. Composing the color maps and the entry maps, there is a composition map of operads $gf : \mathcal{O} \longrightarrow \mathcal{Q}$.

Example 12.1.6. Suppose $f : \mathcal{O} \longrightarrow \mathcal{P}$ is an operad map as in Def. 12.1.1 and $A = \{A_t\}_{t \in T}$ is a \mathcal{P} -algebra as in Def. 6.1.1 or Def. 6.1.2. Then there is an induced \mathcal{O} -algebra A^f defined by the following data.

- (1) For each $c \in S$, A^f is equipped with the c -colored entry $A_c^f = A_{fc}$.
- (2) For each $(c_1, \dots, c_n) \in \text{Prof}(S) \times S$ and $\zeta \in \mathcal{O}(c_1, \dots, c_n)$, A^f is equipped with the structure map

$$A_{c_1}^f \times \dots \times A_{c_n}^f = A_{fc_1} \times \dots \times A_{fc_n} \xrightarrow{\mu_\zeta^f = \mu_{f\zeta}} A_{fd} = A_d^f.$$

Here μ_ζ is the \mathcal{P} -algebra structure map of A , and $f\zeta \in \mathcal{P}(f c_1, \dots, f c_n)$. Since an operad map is assumed to preserve all the operad structure, a direct inspection reveals that A^f is indeed an \mathcal{O} -algebra.

We say that the \mathcal{O} -algebra A^f is *induced along f* .

In the next two observations, we record some obvious operad maps among the various operads of (undirected) wiring diagrams.

Recall the Box_S -colored operad WD of wiring diagrams (Theorem 2.3.8), the Box_S -colored operad WD_\bullet of normal wiring diagrams (Prop. 5.3.5), and the Box_S -colored operad WD_0 of strict wiring diagrams (Prop. 5.4.6). Remember that a normal wiring diagram is a wiring diagram without delay nodes, and a strict wiring diagram is a normal wiring diagram whose supplier assignment is a bijection. Also recall that WD^S means the operad of S -wiring diagrams, and the symbol S is suppressed from the notation WD^S unless we need to emphasize it. Similar remarks apply to WD_0^S and WD_\bullet^S .

Proposition 12.1.7. *Given a map $f : S \longrightarrow T$ of classes, there exists an induced commutative diagram*

$$\begin{array}{ccccc} \text{WD}_0^S & \longrightarrow & \text{WD}_\bullet^S & \longrightarrow & \text{WD}^S \\ f_* \downarrow & & f_* \downarrow & & f_* \downarrow \\ \text{WD}_0^T & \longrightarrow & \text{WD}_\bullet^T & \longrightarrow & \text{WD}^T \end{array} \quad (12.1.7.1)$$

of maps of operads in which:

- the horizontal maps are operad inclusions;
- the vertical maps are induced by f on value assignments.

Proof. In each row of the diagram (12.1.7.1), the maps on colors (i.e., either Box_S or Box_T) are the identity map. For a fixed class, a strict wiring diagram is by definition also a normal wiring diagram, which by definition is also a wiring diagram. In each of WD_0 and WD_\bullet , the operad structure—i.e., the equivariant structure, the colored

units, and the operad composition—is defined as that in WD (Def. 2.3.1–2.3.3). So the horizontal entrywise inclusions actually define operad inclusions.

For the vertical maps in the diagram (12.1.7.1), first note that f induces maps $\text{Fin}_S \longrightarrow \text{Fin}_T$ and $\text{Box}_S \longrightarrow \text{Box}_T$ that are the identity map on the underlying finite sets. On value assignments, these maps are post-composition with f . A direct inspection reveals that, using these two maps, every (strict/normal) S -wiring diagram is sent to a (strict/normal) T -wiring diagram. Moreover, all the operad structure (Def. 2.3.1–2.3.3) is preserved by these maps. So the vertical entrywise defined maps in the diagram (12.1.7.1) are maps of operads. The commutativity of the diagram is immediate from the definitions of the operad maps. \square

Example 12.1.8. By Example 12.1.6 and Prop. 12.1.7, every WD-algebra (Def. 6.2.1) restricts to a WD_\bullet -algebra (Def. 6.4.1), and every WD_\bullet -algebra restricts to a WD_0 -algebra (Def. 6.6.1). For example, the propagator algebra (Def. 6.3.6), which is a WD-algebra, restricts to a WD_\bullet -algebra and also to a WD_0 -algebra.

Recall that UWD^S is the Fin_S -colored operad of undirected S -wiring diagrams (Theorem 7.3.11), and the symbol S in UWD^S is dropped unless we need to emphasize S . Essentially the same as in Prop. 12.1.7, we have the following operad maps for undirected wiring diagrams.

Proposition 12.1.9. *Given a map $f : S \longrightarrow T$ of classes, there exists an induced map of operads*


$$\text{UWD}^S \longrightarrow \text{UWD}^T .$$

Example 12.1.10. Suppose $S = *$, a one-point set, and $T = \text{Set}$, the collection of sets. Then the inclusion $* \longrightarrow \text{Set}$ induces an operad inclusion $\text{UWD}^* \longrightarrow \text{UWD}^{\text{Set}}$. In [Spi13] Example 2.1.7, UWD^* is denoted by \mathcal{S} and is called the operad of singly-typed wiring diagrams. In [Spi13] Example 4.1.1, UWD^{Set} is denoted by \mathcal{T} and is called the operad of typed wiring diagrams.

12.2. Normal to Undirected Wiring Diagrams

Fix a class S for the rest of this chapter, with respect to which the operad WD_\bullet of normal wiring diagrams (Prop. 5.3.5) and the operad UWD of undirected wiring diagrams (Theorem 7.3.11) are defined. Recall that a normal wiring diagram is a wiring diagram without delay nodes. The purpose of this section is to construct a map of operads $\text{WD}_\bullet \longrightarrow \text{UWD}$ given by forgetting directions (Theorem 12.2.4). The existence of such a map of operads was hinted at in the discussion in [RS13] Section 4.1.

Example 12.2.1. To motivate the definition of the map of operads $\text{WD}_\bullet \longrightarrow \text{UWD}$ to be defined below, consider the following normal wiring diagram.



Here

$$X_1^{\text{in}} = \{x_{11}^{\text{in}}, x_{12}^{\text{in}}, x_{13}^{\text{in}}\}, \quad X_1^{\text{out}} = \{x_{11}^{\text{out}}, x_{12}^{\text{out}}\}, \quad X_2^{\text{in}} = \{x_2^{\text{in}}\}, \quad \text{and} \quad X_2^{\text{out}} = \{x_2^{\text{out}}\}.$$

The supplier assignment of φ (Def. 2.2.9), $s : \text{Dm}_\varphi \longrightarrow \text{Sp}_\varphi$, is given by

- $y_1 = s(x_{12}^{\text{in}}) = s(x_2^{\text{in}})$;
- $x_{11}^{\text{out}} = s(x_{11}^{\text{in}}) = s(y^1)$;
- $x_2^{\text{out}} = s(y^2) = s(y^3) = s(x_{13}^{\text{in}})$.

Note that $y_2 \in Y^{\text{in}}$ is an external wasted wire, and $x_{12}^{\text{out}} \in X_1^{\text{out}}$ is an internal wasted wire.

A natural way to make φ into an undirected wiring diagram is to forget the directions of all the arrows. For instance, we send

$$Y = (Y^{\text{in}}, Y^{\text{out}}) = (\{y_1, y_2\}, \{y^1, y^2, y^3\}) \in \text{Box}_S$$


to

$$\bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} = \{y_1, y_2, y^1, y^2, y^3\} \in \text{Fin}_S,$$

and similarly we send $X_i \in \text{Box}_S$ to $\bar{X}_i = X_i^{\text{in}} \sqcup X_i^{\text{out}} \in \text{Fin}_S$ for $i = 1, 2$. So we have

$$\bar{X}_1 = \{x_{11}^{\text{in}}, x_{12}^{\text{in}}, x_{13}^{\text{in}}, x_{11}^{\text{out}}, x_{12}^{\text{out}}\} \quad \text{and} \quad \bar{X}_2 = \{x_2^{\text{in}}, x_2^{\text{out}}\}.$$

Inserting cables at appropriate places, we obtain the following undirected wiring diagram.



Call the two cables on the left, from top to bottom, c_1 and c_2 and the three cables on the right, also from top to bottom, c_3 , c_4 , and c_5 . Then on the left side c_1 is a $(2, 1)$ -cable, and c_2 is a $(0, 1)$ -cable. On the right side, c_3 , c_4 , and c_5 are a $(2, 1)$ -cable, a $(1, 0)$ -cable, and a $(2, 2)$ -cable (Def. 7.1.1), respectively.

Note that the set of cables $\{c_1, \dots, c_5\}$ in $\bar{\varphi}$ is in canonical bijection with the set of supply wires in φ (Def. 2.2.9), namely

$$\text{Sp}_\varphi = Y^{\text{in}} \sqcup X_1^{\text{out}} \sqcup X_2^{\text{out}} \in \text{Fin}_S.$$

With this identification, the input and output soldering functions of $\bar{\varphi}$ are completely determined by the identity map on Sp_φ and the supplier assignment of φ . We will make this precise in (12.2.2.3) below.

With the previous example as motivation, we now define the map of operads $\text{WD}_\bullet \longrightarrow \text{UWD}$. Recall the definitions of normal wiring diagrams (Def. 2.2.9 and 5.3.1) and of undirected wiring diagrams (Def. 7.1.1 and 7.1.3).

Definition 12.2.2. Fix a class S .

- (1) Define the map $\chi_0 : \text{Box}_S \longrightarrow \text{Fin}_S$ by

$$\chi_0 Y = \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} \in \text{Fin}_S \quad (12.2.2.1)$$

for each $Y = (Y^{\text{in}}, Y^{\text{out}}) \in \text{Box}_S$.

- (2) For each $(x_1, \dots, x_n) \in \text{Prof}(\text{Box}_S) \times \text{Box}_S$ with $n \geq 0$, define the map

$$\text{WD}_\bullet(x_1, \dots, x_n) \xrightarrow{\chi_1} \text{UWD}(\bar{x}_1, \dots, \bar{x}_n) \quad (12.2.2.2)$$

as follows. For $\psi \in \text{WD}_\bullet(x_1, \dots, x_n)$ (so $\text{DN}_\psi = \emptyset$), its image

$$\chi_1 \psi = \bar{\psi} \in \text{UWD}(\bar{x}_1, \dots, \bar{x}_n)$$

is the cospan

$$\begin{array}{ccc} & \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} & (12.2.2.3) \\ & \downarrow \text{Id}_{Y^{\text{in}}} \sqcup s_\psi|_{Y^{\text{out}}} & \\ \coprod_{i=1}^n \bar{X}_i = X^{\text{in}} \sqcup X^{\text{out}} & \xrightarrow{(s_\psi|_{X^{\text{in}}}, \text{Id}_{X^{\text{out}}})} & \text{Sp}_\psi = Y^{\text{in}} \sqcup X^{\text{out}} \end{array}$$

in Fin_S . Here:

- $X^{\text{out}} = \coprod_{i=1}^n X_i^{\text{out}}$ and $X^{\text{in}} = \coprod_{i=1}^n X_i^{\text{in}}$.
- Sp_ψ is the set of supply wires of ψ .
- The map

$$\text{Dm}_\psi = Y^{\text{out}} \sqcup X^{\text{in}} \xrightarrow{s_\psi} Y^{\text{in}} \sqcup X^{\text{out}} = \text{Sp}_\psi$$

is the supplier assignment for ψ (Def. 2.2.9).

Remark 12.2.3. Consider the output soldering function of $\bar{\psi}$ in (12.2.2.3). Due to the non-instantaneity requirement (2.2.9.2), the restriction of the supplier assignment s_ψ to Y^{out} is a map $Y^{\text{out}} \longrightarrow X^{\text{out}}$.

Theorem 12.2.4. The maps χ_0 (12.2.2.1) and χ_1 (12.2.2.2) define a map of operads

$$\text{WD}_\bullet \xrightarrow{\chi} \text{UWD} . \quad (12.2.4.1)$$

Proof. As before we will write both χ_0 and χ_1 as χ . We must check that χ preserves the operad structure in the sense of Def. 12.1.1. In both WD_\bullet (2.3.1.1) and UWD (7.3.1.1), the equivariant structure is given by permuting the labels of the input boxes. So χ preserves equivariance in the sense of (12.1.1.1). Likewise, it follows immediately from the definitions of the colored units in WD_\bullet (2.3.2.1) and UWD (7.3.2.1) that they are preserved by χ in the sense of (12.1.1.2).

To check that χ preserves operadic composition in the sense of (12.1.1.3), suppose $\varphi \in \text{WD}_\bullet(X_1, \dots, X_n)$ with $n \geq 1$, $1 \leq i \leq n$, and $\psi \in \text{WD}_\bullet(W_1, \dots, W_m)$ with $m \geq 0$. We must show that

$$\chi(\varphi \circ_i \psi) = (\chi\varphi) \circ_i (\chi\psi) \in \text{UWD}(\bar{Z}) \quad (12.2.4.2)$$

in which

$$\bar{Z} = \overline{(\underline{X} \circ_i \underline{W})} = (\bar{X}_1, \dots, \bar{X}_{i-1}, \bar{W}_1, \dots, \bar{W}_m, \bar{X}_{i+1}, \dots, \bar{X}_n) \in \text{Prof}(\text{Fin}_S)$$

as in (2.1.4.2), $\underline{X} = (X_1, \dots, X_n)$, and $\underline{W} = (W_1, \dots, W_m)$.

To prove (12.2.4.2), on the one hand, by Def. 2.3.3 $\varphi \circ_i \psi \in \text{WD}_\bullet(\underline{X} \circ_i \underline{W})$ has supplier assignment

$$\text{Dm}_{\varphi \circ_i \psi} = Y^{\text{out}} \sqcup \coprod_{j \neq i} X_j^{\text{in}} \sqcup W^{\text{in}} \xrightarrow{s_{\varphi \circ_i \psi}} Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} = \text{Sp}_{\varphi \circ_i \psi}$$

that is given by $s_\varphi, s_\psi s_\varphi, s_\psi, s_\varphi s_\psi$, or $s_\psi s_\varphi s_\psi$ according to (2.3.3.2) and (2.3.3.3). Here

$$W^{\text{in}} = \coprod_{k=1}^m W_k^{\text{in}} \quad \text{and} \quad W^{\text{out}} = \coprod_{k=1}^m W_k^{\text{out}} \in \text{Fin}_S.$$

So by (12.2.2.3) $\chi(\varphi \circ_i \psi) \in \text{UWD}(\bar{Z})$ is the cospan

$$\begin{array}{ccc} & \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} & (12.2.4.3) \\ & \downarrow \text{Id} \sqcup s_{\varphi \circ_i \psi} & \\ \coprod_{j \neq i} \bar{X}_j \sqcup \coprod_k \bar{W}_k & \xrightarrow{(s_{\varphi \circ_i \psi}, \text{Id})} & \text{Sp}_{\varphi \circ_i \psi} = Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} \end{array}$$

in Fin_S . Here:

- The input soldering function is made up of
 - the identity map on $\coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}}$;

- the supplier assignment $s_{\varphi \circ_i \psi} : \coprod_{j \neq i} X_j^{\text{in}} \sqcup W^{\text{in}} \longrightarrow \text{Sp}_{\varphi \circ_i \psi}$.
- The output soldering function is the coproduct of
 - the identity map on Y^{in} ;
 - the supplier assignment $s_{\varphi \circ_i \psi} : Y^{\text{out}} \longrightarrow \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}}$.

On the other hand, by (12.2.2.3) and Def. 7.3.4, the \circ_i -composition

$$(\chi\varphi) \circ_i (\chi\psi) \in \text{UWD}(\bar{Z})$$

is the cospan

$$\begin{array}{ccc}
 & & \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} \\
 & & \downarrow \text{Id}_{Y^{\text{in}}} \sqcup s_{\varphi}|_{Y^{\text{out}}} \\
 & X^{\text{in}} \sqcup X^{\text{out}} & \xrightarrow{(s_{\varphi}|_{X^{\text{in}}}, \text{Id}_{X^{\text{out}}})} \text{Sp}_{\varphi} = Y^{\text{in}} \sqcup X^{\text{out}} \\
 & \downarrow \text{Id} \sqcup s_{\psi}|_{X_i^{\text{out}}} & \downarrow \\
 \coprod_{j \neq i} \bar{X}_j \sqcup \coprod_k \bar{W}_k & \xrightarrow{(s_{\psi}|_{W^{\text{in}}}, \text{Id})} \coprod_{j \neq i} \bar{X}_j \sqcup \underbrace{(X_i^{\text{in}} \sqcup W^{\text{out}})}_{\text{Sp}_{\psi}} & \longrightarrow C \\
 & \downarrow & \uparrow \\
 & & \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}}
 \end{array} \tag{12.2.4.4}$$

in Fin_S , in which the square is defined as a pushout. In this diagram:

- In the middle vertical map, the restriction to
 - X_i^{out} is the supplier assignment $s_{\psi} : X_i^{\text{out}} \longrightarrow W^{\text{out}}$;
 - all other coproduct summands is the identity map.
- In the bottom left horizontal map, the restriction to
 - W^{in} is the supplier assignment $s_{\psi} : W^{\text{in}} \longrightarrow \text{Sp}_{\psi}$;
 - all other coproduct summands is the identity map.

Therefore, to check the condition (12.2.4.2), it suffices to show that the cospans (12.2.4.3) and (12.2.4.4) are the same. So it is enough to show that the square

$$\begin{array}{ccc}
 X^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup X_i^{\text{out}} = X^{\text{in}} \sqcup X^{\text{out}} & \xrightarrow{(s_\varphi|_{X^{\text{in}}}, \text{Id}_{X^{\text{out}}})} & \text{Sp}_\varphi = Y^{\text{in}} \sqcup X^{\text{out}} \\
 \downarrow \left(\text{Id}_{X^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}}} \right) \sqcup (s_\psi|_{X_i^{\text{out}}}) & & \downarrow \left(\text{Id}_{Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}}} \right) \sqcup (s_\psi|_{X_i^{\text{out}}}) \\
 X^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} = \coprod_{j \neq i} \bar{X}_j \sqcup (X_i^{\text{in}} \sqcup W^{\text{out}}) & \xrightarrow{h} & \text{Sp}_{\varphi \circ \psi} = Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}}
 \end{array} \tag{12.2.4.5}$$

in Fin_S is a pushout (Def. 7.2.1). Here the restriction of the map h to

- $\coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}}$ is the identity map;
- X^{in} is the composition

$$X^{\text{in}} \xrightarrow{s_\varphi} Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup X_i^{\text{out}} \xrightarrow{\text{Id} \sqcup s_\psi|_{X_i^{\text{out}}}} Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} .$$

To see that the square (12.2.4.5) is commutative, observe that both compositions when restricted to

- X^{in} is $(\text{Id} \sqcup s_\psi|_{X_i^{\text{out}}}) \circ s_\varphi$;
- $\coprod_{j \neq i} X_j^{\text{out}}$ is the identity map;
- X_i^{out} is s_ψ .

It remains to check the condition (7.2.1.2) of a pushout. So suppose given a solid-arrow commutative diagram

$$\begin{array}{ccc}
 X^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup X_i^{\text{out}} & \xrightarrow{(s_\varphi|_{X^{\text{in}}}, \text{Id})} & Y^{\text{in}} \sqcup X^{\text{out}} \\
 \downarrow \text{Id} \sqcup s_\psi|_{X_i^{\text{out}}} & & \downarrow \text{Id} \sqcup s_\psi|_{X_i^{\text{out}}} \\
 X^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} & \xrightarrow{h} & Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}}
 \end{array}$$

β (curved arrow from top-right to bottom-right)
 α (curved arrow from bottom-left to bottom-right)
 η (dotted arrow from bottom-right to V)

in Fin_S . We must show that there exists a unique dotted map η that makes the diagram commutative. By a direct inspection the only possible candidate for η is given by the restrictions

$$Y^{\text{in}} \amalg \coprod_{j \neq i} X_j^{\text{out}} \xrightarrow{\eta = \beta} V \quad \text{and} \quad W^{\text{out}} \xrightarrow{\eta = \alpha} V.$$

With this definition of η , it remains to check the equalities

$$\eta \left(\text{Id} \amalg_{S\psi} \chi_i^{\text{out}} \right) = \beta \quad \text{and} \quad \eta h = \alpha. \quad (12.2.4.6)$$

Both of these equalities can be checked by a direct inspection. This finishes the proof that the square (12.2.4.5) is a pushout and, therefore, that χ preserves operadic composition (12.2.4.2). \square

Example 12.2.5. By Example 12.1.6 and Theorem 12.2.4, every UWD-algebra (Def. 11.1.1) induces a WD_\bullet -algebra (Def. 6.4.1) along the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$. For example:

- The relational algebra of a set A (Def. 11.2.4 with $S = *$) induces a WD_\bullet -algebra along the operad map χ .
- The typed relational algebra (Def. 11.4.5 with $S = \text{Set}$) also induces a WD_\bullet -algebra along the operad map χ .

12.3. Examples of the Operad Map

The purpose of this section is to provide concrete examples of the map of operads $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ in Theorem 12.2.4. Recall that the map χ was defined in Def. 12.2.2. Similar to Section 8.2, all the assertions in this section are checked by a direct inspection of the normal and undirected wiring diagrams involved. So we will omit the proofs.

First we consider the normal generating wiring diagrams (Def. 5.3.6) that are sent by χ to generators in UWD (Def. 8.1.7).

Example 12.3.1. For the empty wiring diagram $\epsilon \in \text{WD}_\bullet^{(\emptyset)}$ (Def. 3.1.1), the image

$$\chi \epsilon \in \text{UWD}^{(\emptyset)}$$

is the empty cell (Def. 8.1.1).

Example 12.3.2. For a name change $\tau_f \in \text{WD}_\bullet \left(\begin{smallmatrix} Y \\ X \end{smallmatrix} \right)$ (Def. 3.1.3), the image

$$\chi \tau_f \in \text{UWD} \left(\begin{smallmatrix} \bar{Y} \\ \bar{X} \end{smallmatrix} \right)$$

is the name change $\tau_{\bar{f}}$ (Def. 8.1.3) corresponding to the bijection

$$\bar{X} = X^{\text{in}} \amalg X^{\text{out}} \xrightarrow{f^{\text{in}} \amalg (f^{\text{out}})^{-1}} Y^{\text{in}} \amalg Y^{\text{out}} = \bar{Y} \in \text{Fin}_S$$

induced by f .

Example 12.3.3. For a 2-cell $\theta_{X,Y} \in \text{WD}_\bullet(\frac{X \cup Y}{X,Y})$ (Def. 3.1.4), the image

$$\chi\theta_{X,Y} \in \text{UWD}(\frac{\overline{X \cup Y}}{\overline{X,Y}})$$

is the 2-cell $\theta_{(\overline{X},\overline{Y})}$ (Def. 8.1.4).

Example 12.3.4. For a 1-loop $\lambda_{X,x} \in \text{WD}_\bullet(\frac{X \setminus x}{X})$ (Def. 3.1.5), the image

$$\chi\lambda_{X,x} \in \text{UWD}(\frac{\overline{X \setminus x_\pm}}{\overline{X}})$$

is the loop $\lambda_{(\overline{X},x_\pm)}$ (Def. 8.1.5).

Example 12.3.5. For an out-split $\sigma^{Y,y_1,y_2} \in \text{WD}_\bullet(\frac{Y}{X})$ (Def. 3.1.7), the image

$$\chi\sigma^{Y,y_1,y_2} \in \text{UWD}(\frac{\overline{Y}}{\overline{X}})$$

is the split $\sigma^{(\overline{Y},y_1,y_2)}$ (Def. 8.1.6).

Next we consider an in-split and a 1-wasted wire. They are *not* sent by the map of operads χ to generators in UWD. So we will express their χ -images as operadic compositions of the generators in UWD. By Theorem 10.1.10 this is always possible.

Example 12.3.6. For an in-split $\sigma_{X,x_1,x_2} \in \text{WD}_\bullet(\frac{Y}{X})$ (Def. 3.1.6) with $Y = \frac{X}{(x_1=x_2)}$, suppose

$$Z = \overline{Y} \sqcup \{x_1^+, x_1^-\} \in \text{Fin}_S$$

in which $v(x_1^+) = v(x_1^-) = v(x_1) \in S$. Identify

$$\frac{Z}{(x_{12} = x_1^+)} = \frac{\overline{X} \sqcup \{x_1^+, x_1^-\}}{(x_1 = x_2 = x_1^+)} = \overline{X}$$


via $x_1^+ \mapsto x_1$ and $x_1^- \mapsto x_2$. Then we have

$$\chi\sigma_{X,x_1,x_2} = \lambda_{(Z,x_1^\pm)} \circ \sigma^{(Z,x_{12},x_1^+)} \in \text{UWD}(\frac{\overline{Y}}{\overline{X}}) \quad (12.3.6.1)$$

in which:

- $\lambda_{(Z,x_1^\pm)} \in \text{UWD}(\frac{\overline{Y}}{Z})$ is a loop (Def. 8.1.5);
- $\sigma^{(Z,x_{12},x_1^+)} \in \text{UWD}(\frac{Z}{\overline{X}})$ is a split (Def. 8.1.6).

Observe that the right side of (12.3.6.1) also appeared in the elementary relation (8.2.16.1) in UWD. The equality (12.3.6.1) may be visualized as the following picture.



On the right side, the intermediate gray box is Z . In $\chi\sigma_{X,x_1,x_2}$ we drew all of $\overline{X} \setminus \{x_1, x_2\}$ on the right side of the box to make the picture easier to read. It has a $(2,1)$ -cable, and all other cables are $(1,1)$ -cables.

Next we consider the χ -image of a 1-wasted wire.

Example 12.3.7. For a 1-wasted wire $\omega_{Y,y} \in \text{WD}_\bullet(\overset{Y}{X})$ (Def. 3.1.8) with $X = Y \setminus y$, we have

$$\chi\omega_{Y,y} = \theta_{(\overline{X},y)} \circ_2 \omega_y \in \text{UWD}(\overset{Y}{\overline{X}}) \quad (12.3.7.1)$$

in which:

- $\theta_{(\overline{X},y)} \in \text{UWD}(\overset{\overline{X} \cup y}{\overline{X},y})$ is a 2-cell (Def. 8.1.4);
- $\omega_y \in \text{UWD}(\overset{y}{y})$ is a 1-output wire (Def. 8.1.2).

Observe that the right side of (12.3.7.1) also appeared in the elementary relations (8.2.6.1) and (8.2.7.1) and the example (8.3.3.1). The equality (12.3.7.1) may be visualized as the following picture.

$$(12.3.7.2)$$

In $\chi\omega_{Y,y}$ we drew all of \overline{X} on the right side to make the picture easier to read. It has a $(0,1)$ -cable, and all other cables are $(1,1)$ -cables.

Example 12.3.8. Each 1-output wire is in the image of χ . Indeed, for a 1-output wire $\omega_y \in \text{UWD}(\overset{y}{y})$ (Def. 8.1.2), we have

$$\begin{aligned} \omega_y &= [\theta_{(\emptyset,y)} \circ_2 \omega_y] \circ \epsilon \\ &= (\chi\omega_{y,y}) \circ (\chi\epsilon) \quad \text{by Examples 12.3.7 and 12.3.1} \\ &= \chi(\omega_{y,y} \circ \epsilon). \end{aligned} \quad (12.3.8.1)$$

Here:

- $\theta_{(\emptyset,y)} \in \text{UWD}(\overset{y}{\emptyset,y})$ is a 2-cell (Def. 8.1.4).
- $\epsilon \in \text{UWD}(\emptyset)$ is the empty cell (Def. 8.1.1).
- $\omega_{y,y} \in \text{WD}_\bullet(\overset{y}{\emptyset})$ is the 1-wasted wire $\omega_{Y,y}$ (Def. 3.1.8) with $Y^{\text{out}} = \emptyset$ and $Y^{\text{in}} = y$.
- $\epsilon \in \text{WD}_\bullet(\emptyset)$ is the empty wiring diagram (Def. 3.1.1).

Note that in the first two lines of (12.3.8.1), the operadic compositions are in the operad UWD. On the other hand, in the last line of (12.3.8.1) the operadic composition is in the operad WD_\bullet .

Example 12.3.9. By Examples 12.3.1–12.3.5 and 12.3.8, all 6 types of generators in UWD (Def. 8.1.7) are in the image of the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$. However, one must be careful that this does *not* imply that every undirected wiring diagram is in the image of χ . We will make precise the image of the operad map χ in Theorem 12.4.1 below.

Next we consider a 1-internal wasted wire, which by Prop. 3.2.2 can be generated by a 1-loop and a 1-wasted wire.


Example 12.3.10. For a 1-internal wasted wire $\omega^{X,x} \in \text{WD}_\bullet(\overline{Y})$ (Def. 3.2.1) with $Y = X \setminus x$, we have

$$\chi\omega^{X,x} = \lambda_{(Z,x_\pm)} \circ \sigma^{(Z,x_\pm)} \in \text{UWD}(\overline{Y}) \tag{12.3.10.1}$$

in which:


- $Z = \overline{Y} \sqcup x_\pm \in \text{Fin}_S$ with $v(x_+) = v(x_-) = v(x) \in S$;
- $\lambda_{(Z,x_\pm)} \in \text{UWD}(\overline{Z})$ is a loop (Def. 8.1.5);
- $\sigma^{(Z,x_\pm)} \in \text{UWD}(\overline{Z})$ is a split (Def. 8.1.6).

Observe that the right side of (12.3.10.1) also appeared in the elementary relation (8.2.6.1). The equality (12.3.10.1) may be visualized as the following picture.




On the right side, the gray box is Z . In $\chi\omega^{X,x}$, all of $\overline{X} \setminus x = \overline{Y}$ is drawn on the left side. It has a $(1,0)$ -cable, and all other cables are $(1,1)$ -cables.

Example 12.3.11. Consider the wiring diagram $\pi \in \text{WD}_\bullet(\overline{Y})$ in Example 4.2.3. Then $\chi\pi \in \text{UWD}(\overline{Y})$ is the right side of the following picture.



So $\chi\pi$ has a $(0,1)$ -cable, a $(2,1)$ -cable, a $(3,1)$ -cable, a $(1,1)$ -cable, and a $(1,0)$ -cable.

Example 12.3.12. Consider the wiring diagram $\pi_2 \in \text{WD}_\bullet(\binom{Z}{X})$ in Example 4.3.2. Then $\chi\pi_2 \in \text{UWD}(\binom{\bar{Z}}{\bar{X}})$ is the right side of the following picture.



So $\chi\pi_2$ has two $(2,1)$ -cables, two $(0,1)$ -cables, a $(1,2)$ -cable, and two $(1,1)$ -cables.

12.4. Image of the Operad Map

The purpose of this section is to give an explicit description of the image of the map of operads $\chi : \text{WD}_\bullet \rightarrow \text{UWD}$ in Theorem 12.2.4. Recall that the map χ was defined in Def. 12.2.2. Also recall the notations and terminology in Notation 9.1.1 regarding subsets of cables.

Theorem 12.4.1. Consider the operad map $\chi : \text{WD}_\bullet \rightarrow \text{UWD}$ in Theorem 12.2.4. Then:

- (1) The color map $\chi_0 : \text{Box}_S \rightarrow \text{Fin}_S$ (12.2.2.1) is surjective.
- (2) The image of the entry map $\chi_1 : \text{WD}_\bullet \rightarrow \text{UWD}$ (12.2.2.2) consists of precisely the undirected wiring diagrams with no wasted cables and no $(0, \geq 2)$ -cables.

Proof. The color map χ_0 is surjective because, for each $X \in \text{Fin}_S$, we have $(\emptyset, X) \in \text{Box}_S$ and $\chi(\emptyset, X) = X$.

For the second assertion, we will prove the required inclusions in both directions. First suppose $\psi \in \text{WD}_\bullet(\binom{Y}{X_1, \dots, X_n})$ for some $n \geq 0$. Recall that $\chi\psi = \bar{\psi} \in \text{UWD}(\binom{\bar{Y}}{\bar{X}_1, \dots, \bar{X}_n})$ is the cospan (12.2.2.3)

$$\begin{array}{ccc} & & \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} \\ & & \downarrow \text{Id}_{Y^{\text{in}}} \sqcup s_\psi|_{Y^{\text{out}}} \\ \coprod_{i=1}^n \bar{X}_i = X^{\text{in}} \sqcup X^{\text{out}} & \xrightarrow{(s_\psi|_{X^{\text{in}}}, \text{Id}_{X^{\text{out}}})} & \text{Sp}_\psi = Y^{\text{in}} \sqcup X^{\text{out}} \end{array}$$

in Fin_S . To see that $\bar{\psi}$ has no wasted cables (i.e., $(0,0)$ -cables) and no $(0, \geq 2)$ -cables, suppose $c \in \text{Sp}_\psi$ is *not* in the image of the input soldering function $(s_\psi|_{X^{\text{in}}}, \text{Id}_{X^{\text{out}}})$. We must show that c is a $(0,1)$ -cable in $\bar{\psi}$. Since c is not in the image of $\text{Id}_{X^{\text{out}}}$, we have $c \in Y^{\text{in}}$. By the non-instantaneity requirement (2.2.9.2), we also have $c \notin s_\psi(Y^{\text{out}})$. Therefore, c is in the image of the output soldering function $\text{Id}_{Y^{\text{in}}} \sqcup s_\psi|_{Y^{\text{out}}}$ exactly once, so c is a $(0,1)$ -cable in $\bar{\psi}$.

To improve readability, the other half of the second assertion—i.e., that every undirected wiring diagram with no wasted cables and no $(0, \geq 2)$ -cables is in the image of the operad map χ —will be proved in Proposition 12.4.10 below. \square

First we consider the special case when there are no $(0, \geq 0)$ -cables.

Definition 12.4.2. Suppose

$$\varphi = \left(\coprod_{j=1}^N U_j \xrightarrow{f_\varphi} C_\varphi \xleftarrow{g_\varphi} V \right) \in \text{UWD}_{(U_1, \dots, U_N)}^V \quad (12.4.2.1)$$

with $N \geq 0$ and $C_\varphi^{(0, \geq 0)} = \emptyset$.

(1) For each cable $c \in C_\varphi$, pick a wire

$$u_c \in f_\varphi^{-1}(c) \subseteq \coprod_{j=1}^N U_j \quad (12.4.2.2)$$

in the f_φ -preimage of c . This is possible because the assumption $C_\varphi^{(0, \geq 0)} = \emptyset$ means exactly that f_φ is surjective. We will use the canonical bijection

$$\{u_c : c \in C_\varphi\} \xrightarrow[\cong]{f_\varphi} C_\varphi \in \text{Fins} \quad (12.4.2.3)$$

below.

(2) For each $1 \leq j \leq N$ define a box $X_j \in \text{Box}_S$ as

$$X_j^{\text{out}} = \{u_c \in U_j : c \in C_\varphi\} \subseteq U_j \quad \text{and} \quad X_j^{\text{in}} = U_j \setminus X_j^{\text{out}}.$$

Note that we have $\overline{X_j} = U_j$,

$$X^{\text{out}} = \coprod_{j=1}^N X_j^{\text{out}} = \{u_c : c \in C_\varphi\} \cong C_\varphi, \quad \text{and} \quad X^{\text{in}} = \coprod_{j=1}^N U_j \setminus \{u_c : c \in C_\varphi\}.$$

(3) Define $Y = (\emptyset, V) \in \text{Box}_S$, so $\overline{Y} = V$.

(4) Using the bijection (12.4.2.3), define $\psi \in \text{WD}_\bullet(X_1, \dots, X_N)^Y$ whose supplier assignment

$$\begin{aligned} \text{Dm}_\psi &= Y^{\text{out}} \sqcup X^{\text{in}} = V \sqcup \left[\coprod_{j=1}^N U_j \setminus \{u_c : c \in C_\varphi\} \right] \\ &\quad \downarrow s_\psi = (g_\varphi, f_\varphi) \\ \text{Sp}_\psi &= Y^{\text{in}} \sqcup X^{\text{out}} \cong C_\varphi \end{aligned} \quad (12.4.2.4)$$

is

- g_φ when restricted to V ;

- f_φ when restricted to $\coprod_j U_j \setminus \{u_c\}$.

Lemma 12.4.3. *In the context of Def. 12.4.2, we have*

$$\chi\psi = \varphi \in \text{UWD}(\overline{X}_1, \overline{Y}, \overline{X}_N) = \text{UWD}(U_1, \dots, U_N).$$


Proof. By definition $\chi\psi$ is the cospan (12.2.2.3)

$$\begin{array}{ccc} & & V = Y^{\text{in}} \sqcup Y^{\text{out}} \\ & & \downarrow \text{Id}_\emptyset \sqcup s_\psi \\ \coprod_{j=1}^N U_j = X^{\text{in}} \sqcup X^{\text{out}} & \xrightarrow{(s_\psi, \text{Id})} & \text{Sp}_\psi = Y^{\text{in}} \sqcup X^{\text{out}} \cong C_\varphi \end{array}$$


in Fin_S . Using the bijection (12.4.2.3) and the definition of s_ψ (12.4.2.4), it follows that this cospan is equivalent to the given cospan (12.4.2.1) in the sense of Def. 7.1.3. So they define the same undirected wiring diagram, i.e., $\chi\psi = \varphi$. \square

Example 12.4.4. Consider φ in (12.4.2.1) with $N = 0$. Then $\coprod_j U_j = \emptyset$. Since f_φ is surjective, it follows that $C_\varphi = V = \emptyset$. So φ is the empty cell $\epsilon \in \text{UWD}^{(\emptyset)}$ (Def. 8.1.1). The construction (12.4.2.4) above yields $\psi = \epsilon \in \text{WD}_\bullet^{(\emptyset)}$, the empty wiring diagram. So the conclusion $\chi\epsilon = \epsilon$ agrees with Example 12.3.1.

Example 12.4.5. Suppose φ with $C_\varphi^{(0, \geq 0)} = \emptyset$ is the following undirected wiring diagram.



Then one choice of a χ -preimage $\psi \in \text{WD}_\bullet$, as constructed in (12.4.2.4), is the following normal wiring diagram.



So X_1 has 2 inputs and 4 outputs, and X_2 has 2 inputs and no outputs. Note that according to Convention 2.2.7 we should draw inputs on the left and outputs on the right. However, we drew ψ to resemble φ to make the construction easier to understand.

Next we consider the general case where there may be $(0, 1)$ -cables in φ . The idea is to decompose φ as $\varphi_1 \circ_1 \varphi_0$ such that the following statements hold.

- φ_0 satisfies the hypotheses of Lemma 12.4.3, so it has no $(0, \geq 0)$ -cables.
- φ_1 contains all the $(0, 1)$ -cables in φ ; its other cables are all $(1, 1)$ -cables.
- Each of φ_0 and φ_1 can be lifted back to WD_\bullet in such a way that the lifted wiring diagrams are operadically composable in WD_\bullet .

The fact that $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ is an operad map will then show that φ has a χ -preimage.

Definition 12.4.6. Suppose

$$\varphi = \left(\coprod_{j=1}^N U_j \xrightarrow{f_\varphi} C_\varphi \xleftarrow{g_\varphi} V \right) \in \text{UWD}_{(U_1, \dots, U_N)}^V \quad (12.4.6.1)$$

with $N \geq 0$ and $C_\varphi^{(0,0)} = C_\varphi^{(0,\geq 2)} = \emptyset$. By assumption there is a decomposition

$$C_\varphi = \text{Im}(f_\varphi) \sqcup C_\varphi^{(0,1)}$$

in which $\text{Im}(f_\varphi)$ is the image of f_φ .

- Define

$$V_0 = g_\varphi^{-1}(\text{Im}(f_\varphi)) \quad \text{and} \quad V_1 = g_\varphi^{-1}(C_\varphi^{(0,1)}). \quad (12.4.6.2)$$

So $V = V_0 \sqcup V_1$, and there is a bijection $g_\varphi : V_1 \cong C_\varphi^{(0,1)}$.

- Define

$$\varphi_0 = \left(\coprod_{j=1}^N U_j \xrightarrow{f_\varphi} \text{Im}(f_\varphi) \xleftarrow{g_\varphi} V_0 \right) \in \text{UWD}_{(U_1, \dots, U_N)}^{V_0}, \quad (12.4.6.3)$$

in which the input soldering function is surjective, i.e., $C_{\varphi_0}^{(0,\geq 0)} = \emptyset$.

- Define

$$\varphi_1 = \left(V_0 \xrightarrow{\text{inclusion}} V_0 \sqcup V_1 = V \xleftarrow{=} V \right) \in \text{UWD}_{(V_0)}^V, \quad (12.4.6.4)$$

which has only 1 input box V_0 .

- Define $Y_0 = (\emptyset, V_0) \in \text{Box}_S$, so $\bar{Y}_0 = V_0 \in \text{Fin}_S$.
- Define $Y = (V_1, V_0) \in \text{Box}_S$, so $\bar{Y} = V \in \text{Fin}_S$.

First we observe that the two undirected wiring diagrams in the previous definition give a decomposition of φ .

Lemma 12.4.7. *In the context of Def. 12.4.6, there is a decomposition*

$$\varphi = \varphi_1 \circ \varphi_0.$$

Proof. Since φ is the cospan

$$\begin{array}{ccccc}
 & & & & V \\
 & & & & \downarrow = \\
 & & & & \downarrow \text{inclusion} \\
 & & V_0 & \xrightarrow{\text{inclusion}} & V_0 \sqcup V_1 \\
 & & \downarrow g_\varphi & & \downarrow g_\varphi \\
 \coprod_{j=1}^N U_j & \xrightarrow{f_\varphi} & \text{Im}(f_\varphi) & \xrightarrow{\text{inclusion}} & C_\varphi = \text{Im}(f_\varphi) \sqcup C_\varphi^{(0,1)} \\
 & \searrow f_\varphi & & & \uparrow g_\varphi \\
 & & & & V
 \end{array}$$

in Fin_S , by the definition of $\circ = \circ_1$ in UWD (Def. 7.3.4) it is enough to check that the square is a pushout. Since $g_\varphi : V_1 \cong C_\varphi^{(0,1)}$ is a bijection, a direct inspection reveals that the square is a pushout. \square

Lemma 12.4.8. *For $\varphi_1 \in \text{UWD}(V_0)$ in (12.4.6.4), there exists $\psi_1 \in \text{WD}_\bullet(Y_0)$ such that*

$$\chi\psi_1 = \varphi_1.$$

Proof. Define $\psi_1 \in \text{WD}_\bullet(Y_0)$ whose supplier assignment

$$\begin{aligned}
 \text{Dm}_{\psi_1} &= Y^{\text{out}} \sqcup Y_0^{\text{in}} = V_0 & (12.4.8.1) \\
 & \downarrow s_{\psi_1} = \text{inclusion} \\
 \text{Sp}_{\psi_1} &= Y^{\text{in}} \sqcup Y_0^{\text{out}} = V_1 \sqcup V_0 = V
 \end{aligned}$$

is the inclusion map. Then it follows from the definition of χ (12.2.2.3) that $\chi\psi_1 = \varphi_1$. \square

Remark 12.4.9. By Lemma 4.3.6 ψ_1 in (12.4.8.1) is an iterated operadic composition of $|V_1|$ 1-wasted wires (Def. 3.1.8). Since $V_1 \cong g_\varphi^{-1}(C_\varphi^{(0,1)})$ (12.4.6.2), this means that the $(0,1)$ -cables in φ are lifted to external wasted wires in ψ_1 .

Proposition 12.4.10. *Every undirected wiring diagram φ with $C_\varphi^{(0,0)} = C_\varphi^{(0,\geq 2)} = \emptyset$ is in the image of the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$.*

Proof. Suppose $\varphi \in \text{UWD}(U_1, \dots, U_N)$ with $C_\varphi^{(0,0)} = C_\varphi^{(0,\geq 2)} = \emptyset$. By Lemma 12.4.7 there is a decomposition

$$\varphi = \varphi_1 \circ \varphi_0 \tag{12.4.10.1}$$

with $\varphi_0 \in \text{UWD}_{(U_1, \dots, U_N)}^{(V_0)}$ and $\varphi_1 \in \text{UWD}_{(V_0)}$ as in Def. 12.4.6. Moreover, φ_0 satisfies the hypotheses of Lemma 12.4.3 (i.e., that its input soldering function is surjective). So there exists $\psi_0 \in \text{WD}_{(X_1, \dots, X_N)}^{\bullet(Y_0)}$ such that

$$\chi\psi_0 = \varphi_0. \tag{12.4.10.2}$$


With $\psi_1 \in \text{WD}_{(Y_0)}^{\bullet(Y)}$ as in Lemma 12.4.8, we have

$$\begin{aligned} \chi(\psi_1 \circ \psi_0) &= (\chi\psi_1) \circ (\chi\psi_0) \quad \text{by Theorem 12.2.4} \\ &= \varphi_1 \circ \varphi_0 \quad \text{by Lemma 12.4.8 and (12.4.10.2)} \\ &= \varphi \quad \text{by (12.4.10.1)}. \end{aligned}$$


This proves that φ is in the image of χ . □

Proposition 12.4.10 finishes the proof of Theorem 12.4.1.

Example 12.4.11. This is an extension of Example 12.4.5. Suppose φ with $C_\varphi^{(0,0)} = C_\varphi^{(0, \geq 2)} = \emptyset$ is the following undirected wiring diagram.



Then one choice of a χ -preimage $\psi \in \text{WD}_{\bullet}$, as constructed in Prop. 12.4.10, is the following normal wiring diagram.



Note that the two $(0,1)$ -cables in φ are lifted to external wasted wires in ψ .

12.5. Map from Strict to Undirected Wiring Diagrams

For a fixed class S , recall the Box_S -colored operad of strict wiring diagrams WD_0 (Prop. 5.4.6). As pointed out in Example 12.1.4, we can compose the operad map $\chi : \text{WD}_{\bullet} \longrightarrow \text{UWD}$ in Theorem 12.2.4 with the operad inclusion $\text{WD}_0 \longrightarrow \text{WD}_{\bullet}$ in

Prop. 12.1.7 to obtain an operad map

$$\begin{array}{ccc} & \xrightarrow{\chi^0} & \\ \text{WD}_0 & \xrightarrow{\quad} & \text{WD}_\bullet \xrightarrow{\chi} \text{UWD} . \end{array} \quad (12.5.0.1)$$

The purpose of this section is to identify precisely the image of this operad map.

Theorem 12.5.1. *The image of the operad map $\chi^0 : \text{WD}_0 \longrightarrow \text{UWD}$ consists of precisely the undirected wiring diagrams whose cables are either (1,1)-cables or (2,0)-cables.*

Proof. To make the argument easier to read, we will prove the two required inclusions in Lemmas 12.5.2 and 12.5.3 below. \square

Lemma 12.5.2. *The image of each strict wiring diagram under the operad map $\chi^0 : \text{WD}_0 \longrightarrow \text{UWD}$ has only (1,1)-cables and (2,0)-cables.*

Proof. Suppose $\psi \in \text{WD}_0(\overline{X}_1, \dots, \overline{X}_n)$, so it has no delay nodes and its supplier assignment

$$\text{Dm}_\psi = Y^{\text{out}} \sqcup X^{\text{in}} \xrightarrow[\cong]{s_\psi} Y^{\text{in}} \sqcup X^{\text{out}} = \text{Sp}_\psi$$

is a bijection, where $X^{\text{in}} = \coprod_{i=1}^n X_i^{\text{in}}$ and $X^{\text{out}} = \coprod_{i=1}^n X_i^{\text{out}}$. Since $s_\psi(Y^{\text{out}}) \subseteq X^{\text{out}}$ by the non-instantaneity requirement (2.2.9.2), there is a decomposition

$$X^{\text{out}} = X_+^{\text{out}} \sqcup X_-^{\text{out}}$$

such that there are bijections

$$Y^{\text{out}} \xrightarrow[\cong]{s_\psi} X_-^{\text{out}} = \text{Im}(s_\psi|_{Y^{\text{out}}}) \quad \text{and} \quad X^{\text{in}} \xrightarrow[\cong]{s_\psi} Y^{\text{in}} \sqcup X_+^{\text{out}}$$

in Fin_S . By definition (12.2.2.3), $\chi^0\psi \in \text{UWD}(\overline{X}_1, \dots, \overline{X}_n)$ is the following cospan.

$$\begin{array}{ccc} & \overline{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} & \\ & \downarrow \text{Id}_{Y^{\text{in}}} \sqcup s_\psi|_{Y^{\text{out}}} & \\ \coprod_{i=1}^n \overline{X}_i = X^{\text{in}} \sqcup X_+^{\text{out}} \sqcup X_-^{\text{out}} & \xrightarrow{(s_\psi|_{X^{\text{in}}}, \text{Id}_{X_+^{\text{out}}})} & \text{Sp}_\psi = Y^{\text{in}} \sqcup X_+^{\text{out}} \sqcup X_-^{\text{out}} \end{array}$$

Observe that:

- $X_+^{\text{out}} \subseteq \text{Sp}_\psi$ consists of only (2,0)-cables in $\chi^0\psi$;
- $Y^{\text{in}} \sqcup X_-^{\text{out}} \subseteq \text{Sp}_\psi$ consists of only (1,1)-cables in $\chi^0\psi$.

Since there are no other cables, this finishes the proof. \square

Lemma 12.5.3. *If $\varphi \in \text{UWD}$ has only (1,1)-cables and (2,0)-cables, then it is in the image of the operad map $\chi^0 : \text{WD}_0 \longrightarrow \text{UWD}$.*

Proof. Suppose

$$\varphi = \left(U = \coprod_{j=1}^N U_j \xrightarrow{f_\varphi} C_\varphi \xleftarrow{g_\varphi} V \right) \in \text{UWD}_{(U_1, \dots, U_N)}^V$$

has only (1,1)-cables and (2,0)-cables, i.e., $C_\varphi = C_\varphi^{(1,1)} \sqcup C_\varphi^{(2,0)}$. To construct a χ^0 -preimage of φ , first note that there is a decomposition

$$U = U^1 \sqcup U_+^2 \sqcup U_-^2$$

such that the following statements hold.

- $U^1 = \{u \in U : f_\varphi u \in C_\varphi^{(1,1)}\}$, so there are bijections

$$U^1 \xrightarrow[\cong]{f_\varphi} C_\varphi^{(1,1)} \xleftarrow[\cong]{g_\varphi} V. \quad (12.5.3.1)$$

- $U_+^2 = \{u_c \in f_\varphi^{-1}(c) : c \in C_\varphi^{(2,0)}\}$ with u_c as in (12.4.2.2).
- For each $c \in C_\varphi^{(2,0)}$, there exist unique $u_+ = u_c \in U_+^2$ and $u_- \in U_-^2$ such that $f_\varphi(u_\pm) = c$. The correspondence $u_+ \leftrightarrow u_-$ defines a bijection $U_+^2 \cong U_-^2$.

In (12.4.2.4) we already defined $\psi \in \text{WD}_\bullet(X_1, \dots, X_N)$ with supplier assignment

$$\begin{aligned} \text{Dm}_\psi &= Y^{\text{out}} \sqcup X^{\text{in}} = V \sqcup U \setminus \{u_c : c \in C_\varphi\} \\ &\quad \downarrow s_\psi = (g_\varphi, f_\varphi) \\ \text{Sp}_\psi &= Y^{\text{in}} \sqcup X^{\text{out}} \cong C_\varphi = C_\varphi^{(1,1)} \sqcup C_\varphi^{(2,0)} \end{aligned}$$

such that $\chi\psi = \varphi$ by Lemma 12.4.3. So it is enough to show that ψ is a strict wiring diagram. Since $\psi \in \text{WD}_\bullet$ has no delay nodes, it suffices to show that its supplier assignment s_ψ is a bijection. First note that the map $g_\varphi : V \longrightarrow C_\varphi^{(1,1)}$ (12.5.3.1) is a bijection.

It remains to show that the map

$$U \setminus \{u_c : c \in C_\varphi\} \xrightarrow{f_\varphi} C_\varphi^{(2,0)}$$

is also a bijection. We have

$$\begin{aligned} U \setminus \{u_c : c \in C_\varphi\} &= U^1 \sqcup U_+^2 \sqcup U_-^2 \setminus \{u_c : c \in C_\varphi^{(1,1)} \sqcup C_\varphi^{(2,0)}\} \\ &= U_+^2 \sqcup U_-^2 \setminus \{u_c : c \in C_\varphi^{(2,0)}\} \\ &= U_-^2. \end{aligned}$$

Since $f_\varphi : U_-^2 \longrightarrow C_\varphi^{(2,0)}$ is a bijection, the proof is complete. \square

The proof of Theorem 12.5.1 is complete.

Example 12.5.4. The following generators in UWD (Def. 8.1.7) are in the image of the operad map $\chi^0 : \text{WD}_0 \longrightarrow \text{UWD}$.


- the empty cell $\epsilon \in \text{UWD}(\emptyset)$ (Def. 8.1.1);
- a name change $\tau_f \in \text{UWD}(\overset{Y}{X})$ (Def. 8.1.3);
- a 2-cell $\theta_{X,Y} \in \text{UWD}(\overset{X \cup Y}{X,Y})$ (Def. 8.1.4);
- a 1-loop $\lambda_{X,x} \in \text{UWD}(\overset{X \setminus x}{X})$ (Def. 8.1.5).

In fact, by Examples 12.3.1–12.3.4, these generators are χ^0 -images of strict generating wiring diagrams (Def. 5.4.7). On the other hand,

- a 1-output wire $\omega_* \in \text{UWD}(\ast)$ (Def. 8.1.2) and
- a split $\sigma^{(X,x_1,x_2)} \in \text{UWD}(\overset{X}{X'})$ (Def. 8.1.6)


are not in the image of χ^0 .

Example 12.5.5. In the following picture, the strict wiring diagram on the left is sent by $\chi^0 : \text{WD}_0 \longrightarrow \text{UWD}$ to the undirected wiring diagram on the right.



On the right, there are two (2,0)-cables, and the other cables are (1,1)-cables.

Example 12.5.6. In the following picture, the strict wiring diagram on the left is sent by $\chi^0 : \text{WD}_0 \longrightarrow \text{UWD}$ to the undirected wiring diagram on the right.



On the right, there are two (2,0)-cables and three (1,1)-cables.

Map from Wiring Diagrams to Undirected Wiring Diagrams

This chapter has two main purposes.

- (1) We extend the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ in Theorem 12.2.4, defined for normal wiring diagrams (i.e., those without delay nodes), to an operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ that is defined for all wiring diagrams. See Theorem 13.1.4.
- (2) Furthermore, we will show that the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ is surjective; see Theorem 13.3.3. In other words, every undirected wiring diagram is the ρ -image of some wiring diagram.

We remind the reader that the image of the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ was identified in Theorem 12.4.1. It consists of precisely those undirected wiring diagrams with no wasted cables and no $(0, \geq 2)$ -cables.

At first glance, the existence of the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ is not obvious because a general wiring diagram has delay nodes, but undirected wiring diagrams have no obvious analogues of delay nodes. In fact, for this reason Rupel and Spivak ([RS13] 4.1) expressed doubt that there exists an operad map from WD to UWD . Our main results in this chapter, Theorems 13.1.4 and 13.3.3, show that not only is there an operad map $\rho : \text{WD} \longrightarrow \text{UWD}$, but also it is surjective. As we will see in (13.3.1.6), delay nodes play a critical role in realizing wasted cables and $(0, \geq 2)$ -cables in undirected wiring diagrams.

In Section 13.1 we prove that an operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ exists and that it extends the existing operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$. The construction of the operad map ρ is motivated in Example 13.1.1, where we discuss how delay nodes should be sent to undirected wiring diagrams.


In Section 13.2 we provide a series of examples, all containing delay nodes, to further illustrate the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$.

In Section 13.3 we prove that the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ is surjective. This section ends with Example 13.3.4, which provides a detailed illustration of how to lift an undirected wiring diagram back to a wiring diagram.

13.1. Wiring Diagrams to Undirected Wiring Diagrams

The purpose of this section is to construct an operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ that extends the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$ in Theorem 12.2.4. Since normal wiring diagrams are wiring diagrams with no delay nodes, to construct the operad map ρ , we need to decide how to map the delay nodes to undirected wiring diagrams.

Example 13.1.1. Before we define the desired operad map $\rho : \text{WD} \longrightarrow \text{UWD}$, let us consider a motivating example that explains what happens to delay nodes. In the following picture, the wiring diagram $\varphi \in \text{WD}^{(Y)}$ on the left is sent to the undirected wiring diagram $\bar{\varphi} \in \text{UWD}^{(\bar{Y})}$ on the right.



In φ there are 3 delay nodes and no input boxes. In $\bar{\varphi}$ there are 3 cables and no input boxes. As in the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$, every supply wire $\{y, d_1, d_2, d_3\}$ in φ yields a cable in $\bar{\varphi}$. However, since a delay node is both a demand wire and a supply wire, we need to identify the cables corresponding to a delay node d and its supply wire $s(d)$.

- In φ the top delay node d_1 supplies only itself, so the identification is trivial. It yields a wasted cable in $\bar{\varphi}$.
- The middle delay node d_2 is supplied by the global input y , so their cables are identified, yielding a $(0, 2)$ -cable in $\bar{\varphi}$.

- The bottom delay node d_3 supplies itself and three global outputs, so the identification is trivial. Its cable is a $(0, 3)$ -cable in $\bar{\varphi}$.

For a general wiring diagram, this identification is defined in (13.1.2.2) below.

Observe that in $\bar{\varphi}$, there are a wasted cable, a $(0, 2)$ -cable, and a $(0, 3)$ -cable, none of which is possible in the image of $\chi : \text{WD}_\bullet \rightarrow \text{UWD}$ by Theorem 12.4.1. In fact, this example suggests that the desired operad map $\rho : \text{WD} \rightarrow \text{UWD}$ is surjective because wasted cables and $(0, \geq 2)$ -cables are now realizable by carefully chosen delay nodes. We will prove in Theorem 13.3.3 that this is indeed the case.

We now define the operad map $\rho : \text{WD} \rightarrow \text{UWD}$ that extends the operad map $\chi : \text{WD}_\bullet \rightarrow \text{UWD}$ in Theorem 12.2.4. Recall the color map $\chi_0 : \text{Box}_S \rightarrow \text{Fin}_S$ in (12.2.2.1) with

$$\chi_0 Y = \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} \in \text{Fin}_S$$

for each $Y = (Y^{\text{in}}, Y^{\text{out}}) \in \text{Box}_S$.

Definition 13.1.2. Fix a class S . For each $(x_1, \dots, x_n) \in \text{Prof}(\text{Box}_S) \times \text{Box}_S$ with $n \geq 0$, define the map

$$\text{WD}_{(x_1, \dots, x_n)} \xrightarrow{\rho_1} \text{UWD}_{(\bar{x}_1, \dots, \bar{x}_n)} \quad (13.1.2.1)$$

as follows. For $\psi \in \text{WD}_{(x_1, \dots, x_n)}$, its image

$$\rho_1 \psi = \bar{\psi} \in \text{UWD}_{(\bar{x}_1, \dots, \bar{x}_n)}$$

is the cospan

$$\begin{array}{ccc}
 & & \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} \\
 & & \downarrow \text{Id}_{Y^{\text{in}}} \sqcup s_\psi|_{Y^{\text{out}}} \\
 & & \text{Sp}_\psi = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\psi \\
 & & \downarrow \text{quotient} \\
 & & \text{Sp}_\psi \\
 X^{\text{in}} \sqcup X^{\text{out}} & \xrightarrow{(s_\psi|_{X^{\text{in}}}, \text{Id}_{X^{\text{out}}})} & \text{Sp}_\psi \xrightarrow{\text{quotient}} C_{\rho\psi} = \frac{\text{Sp}_\psi}{(d = s_\psi d : d \in \text{DN}_\psi)} \\
 & \searrow & \uparrow \\
 & & \bar{\psi}
 \end{array} \quad (13.1.2.2)$$

in Fin_S . Here:

- $X^{\text{out}} = \coprod_{i=1}^n X_i^{\text{out}}$ and $X^{\text{in}} = \coprod_{i=1}^n X_i^{\text{in}}$.
- The map

$$\text{Dm}_\psi = Y^{\text{out}} \sqcup X^{\text{in}} \sqcup \text{DN}_\psi \xrightarrow{s_\psi} Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\psi = \text{Sp}_\psi$$

is the supplier assignment for ψ (Def. 2.2.9).

- $s_\psi|_{Y^{\text{out}}} : Y^{\text{out}} \rightarrow X^{\text{out}} \sqcup \text{DN}_\psi$ by the non-instantaneity requirement (2.2.9.2).

- $C_{\rho\psi}$ in the lower right corner is the quotient set obtained from Sp_ψ by identifying d and $s_\psi d$ for each delay node $d \in \text{DN}_\psi$.

Remark 13.1.3. In Def. 13.1.2 suppose $\psi \in \text{WD}_\bullet(\overset{Y}{X_1, \dots, X_n})$, i.e., $\text{DN}_\psi = \emptyset$. Then

$$C_{\rho\psi} = \text{Sp}_\psi = Y^{\text{in}} \sqcup X^{\text{out}},$$

so $\rho_1\psi$ in (13.1.2.2) is equal to $\chi_1\psi$ in (12.2.2.3). In other words, when applied to normal wiring diagrams, the entry maps ρ_1 and χ_1 are the same. So Def. 13.1.2 is indeed an extension of Def. 12.2.2 to all wiring diagrams.

Theorem 13.1.4. The maps $\rho_0 = \chi_0$ (12.2.2.1) and ρ_1 (13.1.2.1) define a map of operads

$$\text{WD} \xrightarrow{\rho} \text{UWD}. \quad (13.1.4.1)$$

Proof. This proof is similar to that of Theorem 12.2.4. The difference here is that we now need to take into account the delay nodes.

We will write both ρ_0 and ρ_1 as ρ . We must check that ρ preserves the operad structure in the sense of Def. 12.1.1. In both WD (2.3.1.1) and UWD (7.3.1.1), the equivariant structure is given by permuting the labels of the input boxes. So ρ preserves equivariance in the sense of (12.1.1.1). Likewise, it follows immediately from the definitions of the colored units in WD (2.3.2.1) and UWD (7.3.2.1) that they are preserved by ρ in the sense of (12.1.1.2).

To check that ρ preserves operadic composition in the sense of (12.1.1.3), suppose $\varphi \in \text{WD}(\overset{Y}{X_1, \dots, X_n})$ with $n \geq 1$, $1 \leq i \leq n$, and $\psi \in \text{WD}(\overset{X_i}{W_1, \dots, W_m})$ with $m \geq 0$. We must show that

$$\rho(\varphi \circ_i \psi) = (\rho\varphi) \circ_i (\rho\psi) \in \text{UWD}(\overline{\underline{Z}}) \quad (13.1.4.2)$$

in which

$$\overline{\underline{Z}} = \overline{(\underline{X} \circ_i \underline{W})} = (\overline{X}_1, \dots, \overline{X}_{i-1}, \overline{W}_1, \dots, \overline{W}_m, \overline{X}_{i+1}, \dots, \overline{X}_n) \in \text{Prof}(\text{Fin}_S)$$

as in (2.1.4.2), $\underline{X} = (X_1, \dots, X_n)$, and $\underline{W} = (W_1, \dots, W_m)$.

To prove (13.1.4.2), on the one hand, by Def. 2.3.3 $\varphi \circ_i \psi \in \text{WD}(\overset{Y}{\underline{X} \circ_i \underline{W}})$ has supplier assignment

$$\begin{array}{c} \text{Dm}_{\varphi \circ_i \psi} = Y^{\text{out}} \sqcup \coprod_{j \neq i} X_j^{\text{in}} \sqcup W^{\text{in}} \sqcup \text{DN}_\varphi \sqcup \text{DN}_\psi \\ \downarrow s_{\varphi \circ_i \psi} \\ \text{Sp}_{\varphi \circ_i \psi} = Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} \sqcup \text{DN}_\varphi \sqcup \text{DN}_\psi \end{array}$$

that is given by s_φ , $s_\psi s_\varphi$, s_ψ , $s_\varphi s_\psi$, or $s_\psi s_\varphi s_\psi$ according to (2.3.3.2) and (2.3.3.3). Here

$$W^{\text{in}} = \prod_{k=1}^m W_k^{\text{in}} \quad \text{and} \quad W^{\text{out}} = \prod_{k=1}^m W_k^{\text{out}} \in \text{Fin}_S.$$

So by (13.1.2.2) $\rho(\varphi \circ_i \psi) \in \text{UWD}(\bar{Z})$ is the cospan

$$\begin{array}{c} \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} \\ \downarrow (\text{Id}_{Y^{\text{in}}, s_{\varphi \circ_i \psi} |_{Y^{\text{out}}}) \\ Z^{\text{in}} \sqcup Z^{\text{out}} \xrightarrow{(s_{\varphi \circ_i \psi} |_{Z^{\text{in}}, \text{Id}_{Z^{\text{out}}})} C_{\rho(\varphi \circ_i \psi)} = \frac{\text{Sp}_{\varphi \circ_i \psi} = Y^{\text{in}} \sqcup Z^{\text{out}} \sqcup \text{DN}_{\varphi} \sqcup \text{DN}_{\psi}}{(d = s_{\varphi \circ_i \psi} d : d \in \text{DN}_{\varphi} \sqcup \text{DN}_{\psi})} \end{array} \quad (13.1.4.3)$$

in Fin_S . In (13.1.4.3):

- $\underline{Z} = \underline{X} \circ_i \underline{W} \in \text{Box}_S$, so

$$Z^{\text{in}} = \coprod_{j \neq i} X_j^{\text{in}} \sqcup W^{\text{in}} \quad \text{and} \quad Z^{\text{out}} = \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} \in \text{Fin}_S. \quad (13.1.4.4)$$
- The input soldering function is induced by
 - the identity map on Z^{out} ;
 - the supplier assignment $s_{\varphi \circ_i \psi} : Z^{\text{in}} \longrightarrow \text{Sp}_{\varphi \circ_i \psi}$.
- The output soldering function is induced by
 - the identity map on Y^{in} ;
 - the supplier assignment $s_{\varphi \circ_i \psi} : Y^{\text{out}} \longrightarrow Z^{\text{out}} \sqcup \text{DN}_{\varphi} \sqcup \text{DN}_{\psi}$.

In (13.1.4.3) and in what follows, to simplify the notation, we use the same symbol to denote a map and a map induced by it.

On the other hand, by (13.1.2.2) and Def. 7.3.4, the \circ_i -composition

$$(\rho\varphi) \circ_i (\rho\psi) \in \text{UWD}(\bar{Z})$$

is the cospan

$$\begin{array}{c} \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} \\ \downarrow (\text{Id}_{Y^{\text{in}}, s_{\varphi} |_{Y^{\text{out}}}) \\ X^{\text{in}} \sqcup X^{\text{out}} \xrightarrow{(s_{\varphi} |_{X^{\text{in}}, \text{Id}_{X^{\text{out}}})} C_{\rho\varphi} \\ \downarrow (\text{Id}, s_{\psi} |_{X^{\text{out}}}) \\ \coprod_{j \neq i} \bar{X}_j \sqcup W^{\text{in}} \sqcup W^{\text{out}} \xrightarrow{(s_{\psi} |_{W^{\text{in}}, \text{Id}})} \coprod_{j \neq i} \bar{X}_j \sqcup C_{\rho\psi} \longrightarrow C \end{array} \quad (13.1.4.5)$$

in Fin_S , in which the square is defined as a pushout. In (13.1.4.5):

- $C_{\rho\varphi}$ and $C_{\rho\psi}$ are the sets of cables in $\rho\varphi$ and $\rho\psi$, i.e.,

$$C_{\rho\varphi} = \frac{\text{Sp}_\varphi = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\varphi}{(d = s_\varphi d : d \in \text{DN}_\varphi)} \quad \text{and} \quad C_{\rho\psi} = \frac{\text{Sp}_\psi = X_i^{\text{in}} \sqcup W^{\text{out}} \sqcup \text{DN}_\psi}{(d = s_\psi d : d \in \text{DN}_\psi)}.$$
- In the middle vertical map, the restriction to
 - X_i^{out} is the composition $X_i^{\text{out}} \xrightarrow{s_\psi} W^{\text{out}} \sqcup \text{DN}_\psi \subseteq \text{Sp}_\psi \longrightarrow C_{\rho\psi}$;
 - all other coproduct summands is induced by the identity map.
- In the bottom left horizontal map, the restriction to
 - W^{in} is the composition $W^{\text{in}} \xrightarrow{s_\psi} \text{Sp}_\psi \longrightarrow C_{\rho\psi}$;
 - all other coproduct summands is induced by the identity map.
- In the middle right horizontal map, the restriction to
 - X^{in} is the composition $X^{\text{in}} \xrightarrow{s_\varphi} \text{Sp}_\varphi \longrightarrow C_{\rho\varphi}$;
 - X^{out} is induced by the identity map.

Therefore, to check the condition (13.1.4.2), it suffices to show that the cospans (13.1.4.3) and (13.1.4.5) are the same. So it is enough to show that the square

$$\begin{array}{ccc}
 X^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup X_i^{\text{out}} = X^{\text{in}} \sqcup X^{\text{out}} & \xrightarrow{(s_\varphi|_{X^{\text{in}}}, \text{Id}_{X^{\text{out}}})} & C_{\rho\varphi} \\
 \left(\text{Id}, s_\psi|_{X_i^{\text{out}}} \right) \downarrow & & \left(\text{Id}, s_\psi|_{X_i^{\text{out}}} \right) \downarrow \\
 \coprod_{j \neq i} X_j^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup C_{\rho\psi} = \coprod_{j \neq i} \bar{X}_j \sqcup C_{\rho\psi} & \xrightarrow{h} & C_{\rho(\varphi \circ_i \psi)}
 \end{array} \tag{13.1.4.6}$$

in Fin_S is a pushout (Def. 7.2.1). In (13.1.4.6) the map h is induced by

- the composition $X^{\text{in}} \xrightarrow{s_\varphi} \text{Sp}_\varphi \longrightarrow C_{\rho\varphi} \xrightarrow{(\text{Id}, s_\psi|_{X_i^{\text{out}}})} C_{\rho(\varphi \circ_i \psi)}$;
- the identity map of $\coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} \sqcup \text{DN}_\psi$.

A direct inspection reveals that the right vertical map and the map h in (13.1.4.6) are both well-defined.

To see that the square (13.1.4.6) is commutative, observe that both compositions when restricted to

- X^{in} is induced by $(\text{Id}, s_\psi|_{X_i^{\text{out}}}) \circ (s_\varphi|_{X^{\text{in}}})$;
- $\coprod_{j \neq i} X_j^{\text{out}}$ is induced by the identity map;

- X_i^{out} is induced by $s_\psi|_{X_i^{\text{out}}}$.

It remains to check the condition (7.2.1.2) of a pushout. So suppose given a solid-arrow commutative diagram

$$\begin{array}{ccc}
 X^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup X_i^{\text{out}} & \xrightarrow{(s_\varphi|_{X^{\text{in}}}, \text{Id})} & C_{\rho\varphi} \\
 \downarrow (\text{Id}, s_\psi|_{X_i^{\text{out}}}) & & \downarrow (\text{Id}, s_\psi|_{X_i^{\text{out}}}) \\
 \coprod_{j \neq i} X_j^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup C_{\rho\psi} & \xrightarrow{h} & C_{\rho(\varphi \circ_i \psi)} \\
 & \searrow \alpha & \downarrow \eta \\
 & & V
 \end{array}$$

β (curved arrow from $C_{\rho\varphi}$ to V)

in Fin_S . We must show that there exists a unique dotted map η that makes the diagram commutative. Recall that

$$C_{\rho\varphi} = \frac{\text{Sp}_\varphi = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\varphi}{(d = s_\varphi d : d \in \text{DN}_\varphi)}, \quad C_{\rho\psi} = \frac{\text{Sp}_\psi = X_i^{\text{in}} \sqcup W^{\text{out}} \sqcup \text{DN}_\psi}{(d = s_\psi d : d \in \text{DN}_\psi)},$$

and

$$C_{\rho(\varphi \circ_i \psi)} = \frac{\text{Sp}_{\varphi \circ_i \psi} = Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup W^{\text{out}} \sqcup \text{DN}_\varphi \sqcup \text{DN}_\psi}{(d = s_{\varphi \circ_i \psi} d : d \in \text{DN}_\varphi \sqcup \text{DN}_\psi)}.$$

A direct inspection reveals that the only possible candidate for η is the map induced by the compositions

$$Y^{\text{in}} \sqcup \coprod_{j \neq i} X_j^{\text{out}} \sqcup \text{DN}_\varphi \subseteq \text{Sp}_\varphi \longrightarrow C_{\rho\varphi} \xrightarrow{\beta} V ; \tag{13.1.4.7}$$

$$W^{\text{out}} \sqcup \text{DN}_\psi \subseteq \text{Sp}_\psi \longrightarrow C_{\rho\psi} \xrightarrow{\alpha} V .$$

One can check that these definitions indeed yield a well-defined map η . So with η defined as in (13.1.4.7), it remains to check the equalities

$$\eta \left(\text{Id}, s_\psi|_{X_i^{\text{out}}} \right) = \beta \quad \text{and} \quad \eta h = \alpha. \tag{13.1.4.8}$$

Both of these equalities can be checked by a direct inspection. This finishes the proof that the square (13.1.4.6) is a pushout and, therefore, that ρ preserves operadic composition (12.2.4.2). \square

Example 13.1.5. By Example 12.1.6 and Theorem 13.1.4, every UWD-algebra (Def. 11.1.1) induces a WD-algebra (Def. 6.2.1) along the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$. For example:


- The relational algebra of a set A (Def. 11.2.4 with $S = *$) induces a WD-algebra along the operad map ρ .
- The typed relational algebra (Def. 11.4.5 with $S = \text{Set}$) also induces a WD-algebra along the operad map ρ .

13.2. Examples of the Operad Map

In this section we provide examples of the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ in Theorem 13.1.4.


Recall from Remark 13.1.3 that the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ extends the operad map $\chi : \text{WD}_\bullet \longrightarrow \text{UWD}$. Therefore, the next example and Examples 12.3.1–12.3.7 give a complete description of the ρ -images of all the generating wiring diagrams (Def. 3.1.9).

Example 13.2.1. For an element $d \in S$, the 1-delay node $\delta_d \in \text{WD}^{(d)}$ (Def. 3.1.2) is sent by ρ to the undirected wiring diagram on the right.



In δ_d the delay node is supplied by the unique global input, so in $\rho\delta_d$ there is only one cable. In $\rho\delta_d$ the output box $\{d, d\} \in \text{Fin}_S$ is the S -finite set with two copies of the element $d \in S$. There are no input boxes in $\rho\delta_d$, and the only cable in it is a $(0,2)$ -cable.

Example 13.2.2. In the following picture, the wiring diagram $\varphi \in \text{WD}^{(Y/X)}$ with one delay node d is sent by ρ to the undirected wiring diagram on the right.



Indeed, the set of supply wires in φ is


$$\text{Sp}_\varphi = Y^{\text{in}} \sqcup \text{DN}_\varphi \sqcup X^{\text{out}} = \{y_1, y_2, d\} \sqcup X^{\text{out}}.$$

Since the delay node d is supplied by the global input y_1 , by definition (13.1.2.2) the set of cables of $\rho\varphi$ is

$$C_{\rho\varphi} = \frac{\{y_1, y_2, d\} \sqcup X^{\text{out}}}{(d = s_\varphi d = y_1)} = \{y_1, y_2\} \sqcup X^{\text{out}}.$$

Therefore, in $\rho\varphi$ the cable represented by y_1 is a (2,3)-cable. It is soldered to: y_1 , the input of X supplied by y_1 in φ , and the two global output wires and the input wire of X supplied by d in φ . The cable represented by y_2 is a (0,1)-cable. The other two cables are a (1,0)-cable and a (2,1)-cable.

Example 13.2.3. In the following picture, the wiring diagram $\varphi \in \text{WD}(\overset{Y}{\underset{X}{\square}})$ with one delay node d is sent by ρ to the undirected wiring diagram on the right.




In φ the delay node is supplied by itself, so the set of cables in $\rho\varphi$ is

$$C_{\rho\varphi} = \text{Sp}_\varphi = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \{d\}.$$

In $\rho\varphi$ the cable corresponding to d is a (1,2)-cable. The other two cables are both (1,1)-cables.

Example 13.2.4. In the following picture, the wiring diagram $\varphi \in \text{WD}(\overset{Y}{\underset{X}{\square}})$ with one delay node d is sent by ρ to the undirected wiring diagram on the right.



In φ the delay node d is supplied by the unique output wire x of X , so their corresponding cables are identified in $\rho\varphi$. This cable is a (2,2)-cable. The other cable is a (1,1)-cable.

13.3. Surjectivity of the Operad Map

The reader is reminded of Notation 9.1.1 regarding subsets of cables. The purpose of this section is to show that the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ in Theorem 13.1.4 is surjective. Our strategy is similar to the proof of Lemma 12.4.3, except that here the input soldering function may not be surjective. Cables not in the image of the input soldering function are $(0, \geq 0)$ -cables. Wasted cables (i.e., $(0, 0)$ -cables) and $(0, \geq 2)$ -cables are realized using delay nodes, similar to the delay nodes d_1 and d_3 in Example 13.1.1. Moreover, $(0, 1)$ -cables are realized using external wasted wires, similar to y in the picture (12.3.7.2).

Given an undirected wiring diagram, we now define a wiring diagram that will be shown to be a ρ -preimage. Below we will use the map $\chi_0 = \rho_0 : \text{Box}_S \longrightarrow \text{Fin}_S$ (12.2.2.1), usually denoted by $\chi_0 Y = \bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}}$. The following definition is the general version of Def. 12.4.2 in the sense that now we do not require the input soldering function to be surjective. A detailed example of the following definition will be given in Example 13.3.4.

Definition 13.3.1. Suppose

$$\varphi = \left(U = \coprod_{j=1}^N U_j \xrightarrow{f_\varphi} C_\varphi \xleftarrow{g_\varphi} V \right) \in \text{UWD}_{(U_1, \dots, U_N)}^V \quad (13.3.1.1)$$

for some $N \geq 0$. We will use the equalities

$$\begin{aligned} C_\varphi^{(\geq 1, \geq 0)} &= \text{Im}(f_\varphi) \\ C_\varphi &= C_\varphi^{(0,1)} \sqcup C_\varphi^{(\geq 1, \geq 0)} \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)} \\ V &= g_\varphi^{-1} C_\varphi^{(0,1)} \sqcup g_\varphi^{-1} C_\varphi^{(\geq 1, \geq 0)} \sqcup g_\varphi^{-1} C_\varphi^{(0, \geq 2)} \end{aligned} \quad (13.3.1.2)$$

below.

- (1) For each $c \in C_\varphi^{(\geq 1, \geq 0)}$, pick a preimage

$$u_c \in f_\varphi^{-1}(c) \subseteq U.$$

We will use the bijection

$$\{u_c\} = \left\{ u_c : c \in C_\varphi^{(\geq 1, \geq 0)} \right\} \xrightarrow[\cong]{f_\varphi} C_\varphi^{(\geq 1, \geq 0)} \quad (13.3.1.3)$$

and its inverse below.

- (2) For each $1 \leq j \leq N$ define a box $X_j = (X_j^{\text{in}}, X_j^{\text{out}}) \in \text{Box}_S$ as

$$X_j^{\text{out}} = \left\{ u_c \in U_j : c \in C_\varphi^{(\geq 1, \geq 0)} \right\} \subseteq U_j \quad \text{and} \quad X_j^{\text{in}} = U_j \setminus X_j^{\text{out}}. \quad (13.3.1.4)$$

Note that we have $\bar{X}_j = X_j^{\text{in}} \sqcup X_j^{\text{out}} = U_j$;

$$X^{\text{out}} = \prod_{j=1}^N X_j^{\text{out}} = \left\{ u_c : c \in C_\varphi^{(\geq 1, \geq 0)} \right\} \cong C_\varphi^{(\geq 1, \geq 0)};$$

$$X^{\text{in}} = \prod_{j=1}^N X_j^{\text{in}} = U \setminus \left\{ u_c : c \in C_\varphi^{(\geq 1, \geq 0)} \right\}.$$

(3) Define a box $Y = (Y^{\text{in}}, Y^{\text{out}}) \in \text{Box}_S$ as

$$\begin{aligned} Y^{\text{in}} &= g_\varphi^{-1} C_\varphi^{(0,1)}; \\ Y^{\text{out}} &= g_\varphi^{-1} C_\varphi^{(\geq 1, \geq 0)} \sqcup g_\varphi^{-1} C_\varphi^{(0, \geq 2)}. \end{aligned} \quad (13.3.1.5)$$

Note that $\bar{Y} = Y^{\text{in}} \sqcup Y^{\text{out}} = V$.

(4) Define $\psi \in \text{WD}_{(X_1, \dots, X_N)}^Y$ with delay nodes

$$\text{DN}_\psi = C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)}. \quad (13.3.1.6)$$

Recall the sets

$$\text{Dm}_\psi = Y^{\text{out}} \sqcup \bar{X}^{\text{in}} \sqcup \text{DN}_\psi \quad \text{and} \quad \text{Sp}_\psi = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\psi$$

of demand wires and of supply wires. The supplier assignment for ψ

$$\text{Dm}_\psi = g_\varphi^{-1} C_\varphi^{(\geq 1, \geq 0)} \sqcup g_\varphi^{-1} C_\varphi^{(0, \geq 2)} \sqcup [U \setminus \{u_c\}] \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)} \quad (13.3.1.7)$$

$s_\psi \downarrow$

$$\text{Sp}_\psi = g_\varphi^{-1} C_\varphi^{(0,1)} \sqcup \{u_c\} \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)}$$

is defined by the restrictions:

$$\begin{aligned} g_\varphi^{-1} C_\varphi^{(\geq 1, \geq 0)} \sqcup [U \setminus \{u_c\}] &\xrightarrow{(g_\varphi, f_\varphi)} C_\varphi^{(\geq 1, \geq 0)} \xrightarrow{f_\varphi^{-1}} \{u_c\}; \\ g_\varphi^{-1} C_\varphi^{(0, \geq 2)} &\xrightarrow{g_\varphi} C_\varphi^{(0, \geq 2)}; \\ C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)} &\xrightarrow{=} C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)}. \end{aligned}$$

Here f_φ^{-1} is the inverse of the bijection (13.3.1.3).

Remark 13.3.2. Consider Def. 13.3.1.

- (1) If $C_\varphi^{(0, \geq 0)} = \emptyset$ (i.e., f_φ is surjective), then Def. 13.3.1 reduces to Def. 12.4.2.
- (2) The definition (13.3.1.4) of each box X_j means that:
 - For each cable $c \in C_\varphi^{(\geq 1, \geq 0)} = \text{Im}(f_\varphi)$, one wire in $U = \prod_{j=1}^N U_j$, namely u_c , soldered to c is made into an output wire in ψ .
 - All other wires in U are made into input wires in ψ .

- (3) The definition (13.3.1.5) of the box Y means that:
- Elements in V that are soldered to $(0,1)$ -cables in φ are made into global input wires in ψ .
 - All other elements in V are made into global output wires in ψ .
- (4) The supplier assignment s_ψ in (13.3.1.7) satisfies the non-instantaneity requirement (2.2.9.2) because $Y^{\text{in}} = g_\varphi^{-1}C_\varphi^{(0,1)}$ is disjoint from the image of s_ψ , which is $\{u_c\} \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0,\geq 2)}$. In fact, $Y^{\text{in}} = g_\varphi^{-1}C_\varphi^{(0,1)}$ is exactly the set of external wasted wires in ψ .
- (5) Each delay node (13.3.1.6) is supplied by itself, i.e., $d = s_\psi d$ for each $d \in \text{DN}_\psi$.

Theorem 13.3.3. *Consider the operad map $\rho : \text{WD} \longrightarrow \text{UWD}$ in Theorem 13.1.4.*

- (1) ρ is surjective on colors.
- (2) In the context of Def. 13.3.1, we have that $\rho\psi = \varphi$. In particular, the operad map ρ is surjective on entries as well.

Proof. The color map of ρ is $\rho_0 = \chi_0 : \text{Box}_S \longrightarrow \text{Fin}_S$ (12.2.2.1), which is surjective by Theorem 12.4.1(1).

For the second assertion, the undirected wiring diagram

$$\rho\psi \in \text{UWD}(\overline{x}_1, \dots, \overline{x}_n) = \text{UWD}(u_1, \dots, u_N)$$

is by definition the cospan in (13.1.2.2). Since every delay node in ψ (13.3.1.6) is supplied by itself, the set of cables in $\rho\psi$ is $C_{\rho\psi} = \text{Sp}_\psi$, the set of supply wires in ψ . Furthermore, there is a bijection

$$\begin{aligned} C_{\rho\psi} = \text{Sp}_\psi &= g_\varphi^{-1}C_\varphi^{(0,1)} \sqcup \{u_c\} \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0,\geq 2)} & (13.3.3.1) \\ &\downarrow g_\varphi \sqcup f_\varphi \sqcup \text{Id} \cong \\ C_\varphi &= C_\varphi^{(0,1)} \sqcup C_\varphi^{(\geq 1, \geq 0)} \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0,\geq 2)} \end{aligned}$$

in which f_φ is the bijection (13.3.1.3).

By the definition of s_ψ (13.3.1.7), $\rho\psi \in \text{UWD}(_{U_1, \dots, U_N}^V)$ is the cospan (13.1.2.2)


$$\begin{array}{c}
 V = \overline{Y} = \overbrace{g_\varphi^{-1}C_\varphi^{(0,1)}}^{Y^{\text{in}}} \sqcup \overbrace{g_\varphi^{-1}C_\varphi^{(\geq 1, \geq 0)} \sqcup g_\varphi^{-1}C_\varphi^{(0, \geq 2)}}^{Y^{\text{out}}} \\
 \downarrow \text{Id}_{Y^{\text{in}}} \sqcup s_\psi|_{Y^{\text{out}}} = \text{Id} \sqcup f_\varphi^{-1}g_\varphi \sqcup g_\varphi \\
 U = \underbrace{[U \setminus \{u_c\}]}_{X^{\text{in}}} \sqcup \underbrace{\{u_c\}}_{X^{\text{out}}} \xrightarrow[\text{=} (f_\varphi^{-1}f_\varphi, \text{Id})]{(s_\psi|_{X^{\text{in}}}, \text{Id}_{X^{\text{out}}})} C_{\rho\psi} = g_\varphi^{-1}C_\varphi^{(0,1)} \sqcup \{u_c\} \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)}
 \end{array}$$

in which f_φ^{-1} is the inverse of the bijection (13.3.1.3). Combining this cospan for $\rho\psi$ with the bijection (13.3.3.1), there is a commutative diagram

$$\begin{array}{ccc}
 & V = g_\varphi^{-1}C_\varphi^{(0,1)} \sqcup g_\varphi^{-1}C_\varphi^{(\geq 1, \geq 0)} \sqcup g_\varphi^{-1}C_\varphi^{(0, \geq 2)} & \\
 & \downarrow \text{Id} \sqcup f_\varphi^{-1}g_\varphi \sqcup g_\varphi & \\
 & C_{\rho\psi} = g_\varphi^{-1}C_\varphi^{(0,1)} \sqcup \{u_c\} \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)} & \xrightarrow{g_\varphi} \\
 (f_\varphi^{-1}f_\varphi, \text{Id}) \nearrow & \downarrow g_\varphi \sqcup f_\varphi \sqcup \text{Id} \cong & \\
 U = [U \setminus \{u_c\}] \sqcup \{u_c\} & \xrightarrow{f_\varphi} & C_\varphi = C_\varphi^{(0,1)} \sqcup C_\varphi^{(\geq 1, \geq 0)} \sqcup C_\varphi^{(0,0)} \sqcup C_\varphi^{(0, \geq 2)}
 \end{array}$$

in Fin_S . In this diagram, the outer cospan is φ (13.3.1.1). Therefore, by Def. 7.1.3 we have proved $\varphi = \rho\psi$. \square

Example 13.3.4. This is an illustration of Def. 13.3.1 and Theorem 13.3.3. Consider the undirected wiring diagram $\varphi \in \text{UWD}(_{U_1, U_2}^V)$ in (7.1.6.1), depicted as



with $V = \{v_1, \dots, v_6\}$, $U_1 = \{u_1, \dots, u_6\}$, $U_2 = \{u^1, u^2\}$, and $C_\varphi = \{c_1, \dots, c_7\}$.

Following Def. 13.3.1 first note that we have the subsets

$$C_\varphi^{(0,0)} = \{c_4\}, \quad C_\varphi^{(0,1)} = \{c_5\}, \quad C_\varphi^{(0,\geq 2)} = \{c_1\}, \quad \text{and} \\ C_\varphi^{(\geq 1,\geq 0)} = \text{Im}(f_\varphi) = \{c_2, c_3, c_6, c_7\}.$$

Next, for each cable $c \in C_\varphi^{(\geq 1,\geq 0)}$, we are supposed to choose an f_φ -preimage $u_c \in U = U_1 \sqcup U_2$. We may choose, for example,

$$u_{c_2} = u_1, \quad u_{c_3} = u_2, \quad u_{c_6} = u_5, \quad \text{and} \quad u_{c_7} = u_6,$$

all in U_1 . With such choices, the boxes X_1 and $X_2 \in \text{Box}_S$ (13.3.1.4) are

$$X_1 = (X_1^{\text{in}}, X_1^{\text{out}}) = (\{u_3, u_4\}, \{u_1, u_2, u_5, u_6\}); \\ X_2 = (X_2^{\text{in}}, X_2^{\text{out}}) = (\{u^1, u^2\}, \emptyset).$$

The box $Y \in \text{Box}_S$ (13.3.1.5) is

$$(Y^{\text{in}}, Y^{\text{out}}) = (g_\varphi^{-1} C_\varphi^{(0,1)}, g_\varphi^{-1} C_\varphi^{(\geq 1,\geq 0)} \sqcup g_\varphi^{-1} C_\varphi^{(0,\geq 2)}) \\ = (\{v_6\}, \{v_1, v_2, v_3, v_4, v_5\}).$$

The set of delay nodes of $\psi \in \text{WD}_{(X_1, X_2)}^Y$ (13.3.1.6) is

$$\text{DN}_\psi = C_\varphi^{(0,0)} \sqcup C_\varphi^{(0,\geq 2)} = \{c_1, c_4\}.$$


The supplier assignment for ψ (13.3.1.7) is the function

$$\text{Dm}_\psi = Y^{\text{out}} \sqcup X^{\text{in}} \sqcup \text{DN}_\psi = \{v_1, v_2, v_3, v_4, v_5\} \sqcup \{u_3, u_4, u^1, u^2\} \sqcup \{c_1, c_4\} \\ \downarrow s_\psi \\ \text{Sp}_\psi = Y^{\text{in}} \sqcup X^{\text{out}} \sqcup \text{DN}_\psi = \{v_6\} \sqcup \{u_1, u_2, u_5, u_6\} \sqcup \{c_1, c_4\}$$

given by


$$s_\psi(v_1) = s_\psi(v_2) = c_1, \quad s_\psi(v_3) = u_1, \quad s_\psi(v_4) = s_\psi(v_5) = u_2, \\ s_\psi(u_3) = s_\psi(u^1) = u_2, \quad s_\psi(u_4) = s_\psi(u^2) = u_5, \\ s_\psi(c_1) = c_1, \quad \text{and} \quad s_\psi(c_4) = c_4.$$

The supply wire v_6 is an external wasted wire, and u_6 is an internal wasted wire in ψ . We may draw $\psi \in \text{WD}_{(X_1, X_2)}^Y$ as follows.



By Theorem 13.3.3(2) or a direct inspection, the map $\rho : \text{WD} \longrightarrow \text{UWD}$ sends ψ to φ .

Note that $\psi \in \text{WD}_{(X_1, X_2)}^Y$ is certainly not the only ρ -preimage of $\varphi \in \text{UWD}_{(u_1, u_2)}^V$. For example, the wiring diagram



also satisfies $\rho\psi' = \varphi$. Here the output box is

$$Z = (Z^{\text{in}}, Z^{\text{out}}) = (\{v_1, v_6\}, \{v_2, v_3, v_4, v_5\}) \in \text{Box}_S,$$

and $s_{\psi'}(c_1) = v_1$. Everything else is the same as in ψ .

Problems

This final chapter contains some problems from the earlier chapters about operads and (undirected) wiring diagrams.

Problem 14.1. Give a detailed proof of Prop. 2.1.6, which states that the two definitions of a colored operad—one in terms of May’s γ (Def. 2.1.2) and the other in terms of the \circ_i -compositions (Def. 2.1.4)—are equivalent. The equivalence of the unity axioms is rather easy to check. However, to prove the equivalence of the associativity axioms and the equivariance axioms in the two definitions, a fair amount of bookkeeping and notations are needed.

Problem 14.2. For the collection WD of S -wiring diagrams (Def. 2.2.11), write down its structure map γ (2.1.2.2) and prove that:

- (1) WD is a Box_S -colored operad in the sense of Def. 2.1.2.
- (2) This structure map γ corresponds to the \circ_i -compositions in Def. 2.3.3 in the sense of Prop. 2.1.6.

In [RS13] the operad WD was in fact defined in terms of the structure map γ .

Problem 14.3. Consider the 28 elementary relations in Section 3.3.

- (1) Give a detailed proof for each elementary relation. These proofs are similar to those for Lemma 2.3.6, Lemma 2.3.7, and Prop. 3.2.2.
- (2) For each elementary relation, draw a picture that depicts the operadic compositions, similar to those just before Prop. 3.3.9 and Prop. 3.3.11, if one was not given.

Problem 14.4. Write down the proof for Lemma 4.2.2.

Problem 14.5. In Example 4.2.3:

- (1) Write down precisely the wiring diagrams π , π_1 , and π_2 , including their supplier assignments.
- (2) Check carefully that there is indeed a decomposition $\pi = \pi_1 \circ \pi_2$.

Problem 14.6. In Example 4.3.2:

- (1) Write down precisely the wiring diagrams β_1 , β_2 , and β_3 , including their supplier assignments.
- (2) Check carefully that there is indeed a decomposition $\pi_2 = \beta_1 \circ \beta_2 \circ \beta_3$.

Problem 14.7. In Remark 5.1.6 it was stated that stratified simplices of type (1) and of type (2) are mutually exclusive. Write down a detailed proof for this claim.

Problem 14.8. For the wiring diagram in (2.2.14.1), without using Theorem 5.1.7, prove directly that it has a stratified presentation.

Problem 14.9. Check carefully the proof of Theorem 5.3.7, which is the finite presentation theorem for the operad WD_\bullet of normal wiring diagrams.

Problem 14.10. Give a direct proof of Theorem 5.4.8—the finite presentation theorem for the operad WD_0 of strict wiring diagrams—without referencing the proofs of Theorem 5.1.7, Lemma 5.2.7, Lemma 5.2.8, and Lemma 5.2.9.

Problem 14.11. Give a detailed proof that Def. 6.1.1 and Def. 6.1.2 of an operad algebra are indeed equivalent. The reader may consult [Yau16] (Chapter 16) for more information about operad algebras.

Problem 14.12. In Def. 6.2.1, check that the 28 generating axioms in fact correspond to the 28 elementary relations in the sense of the associativity diagram (6.1.2.1).

Problem 14.13. In the proof of Theorem 6.3.7—the finite presentation theorem for the propagator algebra—we checked the generating axioms (6.2.1.16) and (6.2.1.17) that are the least obvious. Give detailed proofs for the other 26 generating axioms for the propagator algebra.

Problem 14.14. In Remark 6.3.13 we pointed out that the structure map of the propagator algebra in [RS13], when applied to the generating wiring diagrams (section 3.1), reduces to our 8 generating structure maps in Def. 6.3.6. Check carefully that this is indeed the case.

Problem 14.15. Check carefully the proofs of Theorems 6.4.2 and 6.6.2, the finite presentation theorems for WD_\bullet -algebras and WD_0 -algebras.

Problem 14.16. In the proof of Theorem 6.5.7—the finite presentation theorem for the algebra of discrete systems—one generating axiom was written down in detail. Check the other 27 generating axioms carefully.

Problem 14.17. In the proof of Theorem 6.7.7—the finite presentation theorem for the algebra of open dynamical systems—we checked the generating axiom (6.2.1.16) corresponding to a double-loop. Give detailed proofs for the other 7 generating axioms for the algebra of open dynamical systems.

Problem 14.18. In Remark 6.7.8 we pointed out that the structure map of the algebra of open dynamical systems in [VSL14], when applied to the strict generating wiring diagrams—namely, ϵ , $\tau_{X,Y}$, $\theta_{X,Y}$, and $\lambda_{X,x}$ —reduces to our 4 generating structure maps in Def. 6.7.6. Check carefully that this is indeed the case.

Problem 14.19. Check carefully the proof of Propositions 7.3.5 and 7.3.13.

Problem 14.20. Check that each elementary relation in Section 8.2 is indeed an equality in UWD.

Problem 14.21. In Example 8.3.1, check that the iterated operadic composition (8.3.1.1) is the intended undirected wiring diagram $\varphi \circ \psi$.

Problem 14.22. In Example 8.3.2, check that the iterated operadic composition (8.3.2.1) is actually equal to ζ_Y .

Problem 14.23. In Example 8.3.3, check that the iterated operadic composition (8.3.3.1) is actually equal to ζ_Y .

Problem 14.24. Following the hint in Remark 11.1.3, formulate and prove a finite presentation theorem for a colored operad with given finite sets of generators and relations.

Problem 14.25. In the proofs of Theorems 11.2.5 and 11.4.7—the finite presentation theorems for the (typed) relational algebra—we checked one of the generating axioms. Give detailed proofs for the other 16 generating axioms.

Problem 14.26. Prove or disprove Spivak’s Conjecture 11.3.2 regarding the quotient freeness of the relational algebra. Then send me an email and tell me how you do it.

Problem 14.27. In Example 12.1.6, check that A^f is indeed an O-algebra.

Problem 14.28. In the proof of Theorem 12.2.4, check that it is actually sufficient to prove that the diagram (12.2.4.5) is a pushout in \mathbf{Fins} . Then check the equalities (12.2.4.6).

Problem 14.29. In the proof of Theorem 13.1.4:

- (1) Check that it is actually sufficient to prove that the diagram (13.1.4.6) is a pushout in \mathbf{Fins} .
- (2) In the diagram (13.1.4.6), check that the right vertical map and the map h are indeed well-defined.
- (3) Check that the definitions (13.1.4.7) actually yield a well-defined map η .
- (4) Check the equalities (13.1.4.8).

Bibliography

- [Awo10] S. Awodey, *Category Theory*, 2nd. ed., Oxford Logic Guides 52, Oxford Univ. Press, Oxford, 2010. 19, 135
- [AT69] M.F. Atiyah and I.G. MacDonal, *Introduction to Commutative Algebra*, Addison-Wesley, Massachusetts, 1969. 4
- [BE14] J.C. Baez and J. Erbele, *Categories in control*, arXiv:1405.6881. 5
- [BF15] J.C. Baez and B. Fong, *A compositional framework for passing linear networks*, arXiv:1504.05625. 134
- [BFP15] J.C. Baez, B. Fong, and B.S. Pollard, *A compositional framework for Markov processes*, arXiv:1508.06448. 134
- [BSZ14] F. Bonchi, P. Sobociński, and F. Zanasi, *A categorical semantics of signal flow graphs*, pp. 435-450, *Lecture Notes in Comp. Sci.* 8704, Springer, 2014. 5
- [Fon15] B. Fong, *Decorated cospans*, *Theory Appl. Categ.* 30 (2015), 1096–1120. 134
- [GK94] V. Ginzburg and M. Kapranov, *Koszul duality for operads*, *Duke Math. J.* 76 (1994), 203-272. 4
- [Hal74] P.R. Halmos, *Naive Set Theory*, Undergrad. Texts in Math., Springer, New York, 1974. 13
- [Hel78] S. Helgason, *Differential Geometry, Lie Groups, and Symmetric Spaces*, Academic Press, San Diego, 1978. 123
- [JY09] M.W. Johnson and D. Yau, *On homotopy invariance for algebras over colored PROPs*, *J. Homotopy and Related Structures* 4 (2009), 275-315. 16
- [JSV96] A. Joyal, R. Street, and D. Verity, *Traced monoidal categories*, *Mathematical Proceedings of the Cambridge Philosophical Society* 119 (1996), 447-468. 5
- [Kel05] G.M. Kelly, *On the operads of J.P. May*, *Reprints in Theory Appl. Categ.* 13 (2005), 1-13. 16
- [Lam69] J. Lambek, *Deductive systems and categories. II. Standard constructions and closed categories*, in: *1969 Category Theory, Homology Theory and their Applications, I* (Battelle Inst. Conf., Seattle, Wash., 1968, Vol. 1) p.76-122, Springer, Berlin, 1969. 2, 18, 19
- [Lei14] T. Leinster, *Basic Category Theory*, Cambridge Studies in Adv. Math. 143, Cambridge Univ. Press, Cambridge, 2014. 19

- [Mac63] S. Mac Lane, Natural Associativity and Commutativity, *Rice Univ. Studies* 49, 28-46. 4
- [Mac98] S. Mac Lane, *Categories for the working mathematician*, Grad. Texts in Math. 5, 2nd ed., Springer-Verlag, New York, 1998. 4, 19, 135
- [Mar96] M. Markl, Models for operads, *Comm. Algebra* 24 (1996), 1471-1500. 16
- [Mar08] M. Markl, Operads and PROPs, *Handbook of Algebra* 5, p.87-140, Elsevier, 2008. 19
- [MSS02] M. Markl, S. Shnider, and J. Stasheff, *Operads in Algebra, Topology and Physics*, Math. Surveys and Monographs 96, Amer. Math. Soc., Providence, 2002. 16
- [May72] J.P. May, The geometry of iterated loop spaces, *Lecture Notes in Math.* 271, Springer-Verlag, New York, 1972. 2, 16, 96
- [May97] J.P. May, Definitions: operads, algebras and modules, *Contemp. Math.* 202, p.1-7, 1997. 2, 16
- [Pin04] C.C. Pinter, *A Book of Set Theory*, Dover, New York, 2014. 13
- [Rot02] J.J. Rotman, *Advanced Modern Algebra*, Prentice Hall, New Jersey, 2002. 4
- [RS13] D. Rupel and D.I. Spivak, The operad of temporal wiring diagrams: formalizing a graphical language for discrete-time processes, arXiv:1307.6894. 1, 2, 4, 6, 8, 13, 21, 24, 31, 95, 107, 118, 213, 233, 249, 250
- [Spi13] D.I. Spivak, The operad of wiring diagrams: formalizing a graphical language for databases, recursion, and plug-and-play circuits, arXiv:1305.0297. 1, 2, 3, 8, 131, 132, 133, 137, 139, 143, 189, 190, 197, 200, 201, 203, 206, 213
- [Spi14] D.I. Spivak, *Category Theory for the Sciences*, MIT Press, 2014. 1, 7, 133
- [Spi15] D.I. Spivak, Nesting of dynamic systems and mode-dependent networks, arXiv:1502.07380. 1, 2, 21, 80, 89
- [Spi15b] D.I. Spivak, The steady states of coupled dynamical systems compose according to matrix arithmetic, arXiv:1512.00802. 1, 2, 80, 89, 96, 119, 121, 122
- [SSR15] D.I. Spivak, P. Schultz, and D. Rupel, String diagrams for traced and compact categories are oriented 1-cobordisms, arXiv:1508.01069. 5
- [VSL14] D. Vagner, D.I. Spivak, and E. Lerman, Algebras of open dynamical systems on the operad of wiring diagrams, arXiv:1408.1598. 1, 2, 3, 21, 80, 91, 96, 123, 124, 127, 251
- [Yau16] D. Yau, *Colored Operads*, Graduate Studies in Math. 170, Amer. Math. Soc., Providence, RI, 2016. 2, 14, 16, 19, 96, 97, 98, 250
- [YJ15] D. Yau and M.W. Johnson, *A Foundation for PROPs, Algebras, and Modules*, Math. Surveys and Monographs 203, Amer. Math. Soc., Providence, RI, 2015 2, 5, 197

Index

- 1-delay node, 34
- 1-internal wasted wire, 39
- 1-loop, 35
- 1-output wire, 146
- 1-wasted wire, 38
- 2-cell, 35

- algebra of discrete systems, 120
- algebra of open dynamical systems, 125
- associative law, 18
- associativity of 2-cells, 43
- associativity of a category, 20
- associativity of an algebra, 96
- associativity of an operad, 15, 17
- associativity of in-splits, 50
- associativity of out-splits, 52
- associativity of splits, 154
- associativity of undirected 2-cells, 152

- black box, 21
- block permutation, 16
- block sum, 16
- bottom equivariance, 16
- box, 21, 132

- cable, 132
- category, 19
- category of finite sets, 20
- class, 13
- coherence, 4
- color map, 210
- colored entries of an algebra, 96
- colored operad, 14, 17
- colored unit, 14
- commutative law, 18
- commutativity of 1-loops, 46
- commutativity of 1-wasted wires, 54
- commutativity of 2-cells, 44
- commutativity of in-splits, 50
- commutativity of loops, 156
- commutativity of out-splits, 53
- commutativity of splits, 154
- commutativity of undirected 2-cells, 152
- \circ_i -composition, 17
- \circ_i -composition in UWD, 138
- \circ_i -composition in WD, 26
- \circ_i -composition of structure maps, 97
- composition, 17
- composition of a simplex, 80
- composition of a simplex in UWD, 180
- concatenation, 14
- coproduct of boxes, 22
- coproduct of finite sets, 21
- cospan, 132
- cut, 18

- decomposition, 55, 166
- decomposition of unary wiring diagrams, 63, 68
- delay node, 22
- δ_d , 34
- demand, 22
- discrete system, 119
- Dm , 22
- DN , 22
- double-loop, 46
- dynamical systems, 1

- elementarily equivalent, 84
- elementarily equivalent in UWD, 183
- elementary equivalence, 84
- elementary equivalence in UWD, 183
- elementary relations, 54
- elementary relations in UWD, 156
- elementary subsimplex, 83

- elementary subsimplex in UWD, 182
- empty cell, 146
- empty profile, 14
- empty wiring diagram, 34
- entry map, 210
- entry of an operad, 14
- ϵ , 34, 146
- equivalence of rewiring diagrams, 23
- equivalent simplices, 83
- equivalent simplices in UWD, 183
- equivariance in UWD, 137, 140
- equivariance in WD, 25, 27
- equivariance of an algebra, 97
- equivariance of an operad, 16, 18
- external wasted wire, 23
- externally supplied element, 61

- Fin, 20
- Fin_S, 20
- finite presentation for the propagator algebra, 112
- finite presentation for the algebra of discrete systems, 122
- finite presentation for the algebra of open dynamical systems, 126
- finite presentation for the relational algebra, 199
- finite presentation for the typed relational algebra, 205
- finite presentation for UWD, 187
- finite presentation for UWD-algebras, 195
- finite presentation for WD, 89
- finite presentation for WD-algebras, 105
- finite presentation for WD_•, 90
- finite presentation for WD_•-algebras, 119
- finite presentation for WD₀, 93
- finite presentation for WD₀-algebras, 123

- generating undirected wiring diagrams, 148
- generating wiring diagrams, 38
- generators, 148
- global input, 22
- global output, 22
- graph groupoids, 5

- historical propagator, 107
- historical propagators of type X, 108
- historicity, 107
- horizontal associativity, 17
- horizontal associativity in UWD, 141
- horizontal associativity in WD, 28

- in-split, 36
- induced operad algebra, 212
- initial operad, 211
- input, 21
- input box, 22, 132
- input profile, 14
- input soldering function, 132
- internal input, 22
- internal output, 22
- internal wasted wire, 23
- internally supplied element, 61
- isomorphism of operad algebras, 201
- iterated loops, 176
- iterated splits, 173

- $\lambda_{(X, X_{\pm})}$, 147
- $\lambda_{X, X'}$, 35
- left unity, 16, 18
- length of a profile, 14
- loop, 147
- loop element, 61

- manifolds, 124
- map of operad algebras, 200
- map of operads, 210
- (m, n)-cable, 132, 162
- ($\geq m, n$)-cable, 162
- ($m, \geq n$)-cable, 162
- ($\geq m, \geq n$)-cable, 162
- mode-dependent networks, 1
- monoidal category, 4
- morphism, 19
- multicategory, 18
- multimaps, 18

- n -ary element, 14
- name change, 34
- no passing wires, 91
- non-instantaneity requirement, 23
- normal generating wiring diagram, 90
- normal simplex, 90
- normal stratified presentation, 90
- normal stratified simplex, 90
- normal wiring diagram, 89

- object, 19
- ω_* , 146
- $\omega^{X, X}$, 39
- $\omega_{Y, Y'}$, 38
- open dynamical system, 124
- operad, 14, 17
- operad algebra, 96
- operad algebra induced along a map, 212
- operad inclusion, 211
- operad map, 210
- operad map composition, 211
- operadic composition, 14, 17
- out-split, 37
- output, 21
- output box, 22
- output color, 14
- output soldering function, 132

- Pentagon Axiom, 4
- power set, 197
- presentation, 80, 180

- prewiring diagram, 22
- profile, 14
- propagator algebra, 110
- props, 5
- pushout, 135

- readout function, 119
- relational algebra of a set, 198
- right action, 14
- right permutation, 14
- right unity, 15, 18

- S-box, 21
- S-finite set, 21
- σ_{X,x_1,x_2} , 36
- $\sigma^{(X,x_1,x_2)}$, 148
- σ^Y,y_1,y_2 , 37
- signal-flow graphs, 5
- signed finite set, 21
- simplex, 80
- simplex in UWD, 180
- singly-typed wiring diagram, 133
- soldered to, 132
- Sp, 22
- Spivak's Conjecture, 201
- split, 148
- state set, 119
- stratified presentation, 82, 181
- stratified presentations exist, 82
- stratified presentations exist in UWD, 182
- stratified simplex, 81
- stratified simplex in UWD, 181
- strict elementary equivalences, 93
- strict elementary relation, 93
- strict generating wiring diagram, 93
- strict simplex, 93
- strict stratified presentation, 93
- strict stratified simplex, 93
- strict wiring diagram, 91
- string diagrams, 5
- structure map of an algebra, 96
- sub-operad, 211
- subsimplex, 83
- subsimplex in UWD, 182
- substitution, 18
- supplier, 23
- supplier assignment, 22
- supply, 22
- supply wire, 23
- symmetric group, 14
- symmetric group action, 14
- symmetric operad, 16

- tangent bundle, 124
- $\tau_{X,Y}$, 34, 146
- terminal operad, 211
- $\theta_{(X,Y)}$, 147

- $\theta_{X,Y}$, 35
- top equivariance, 16
- truncation, 107
- typed relational algebra, 204
- typed wiring diagram, 133

- underline notation, 16
- undirected 2-cell, 147
- undirected name change, 146
- undirected prewiring diagram, 132
- undirected wiring diagram, 133
- units in UWD, 137
- units in WD, 25
- unity in UWD, 140
- unity in WD, 27
- unity of 2-cells, 43
- unity of a category, 20
- unity of an algebra, 96
- unity of an operad, 15, 17
- update function, 119
- UWD, 133
- UWD is an operad, 143
- UWD-algebra, 190

- value assignment, 21
- vector field, 125
- vertical associativity, 17
- vertical associativity in UWD, 142
- vertical associativity in WD, 30
- vertical notation, 16

- wasted cable, 132
- WD, 23
- WD is an operad, 31
- WD-algebra, 98
- WD_\bullet , 89
- WD_\bullet is an operad, 90
- WD_\bullet -algebra, 118
- WD_0 , 91
- WD_0 is an operad, 92
- WD_0 -algebra, 123
- wheeled props, 5
- wiring diagram, 23