

A Proper Definition of Higher Order Rigidity

Tomohiro Tachi

October 22, 2024

Abstract

[Connelly and Servatius, 1994] shows the difficulty of properly defining n -th order rigidity and flexibility of a bar-and-joint framework for higher order ($n \geq 3$) through the introduction of a cusp mechanism. I propose a “proper” definition of the order of rigidity by the order of elongation of the bars with respect to the arclength along the path in the configuration space. We show that the classic definition using formal n -th derivative of the length constraint is a sufficient condition for the n -th flexibility in the proposed definition and also a necessary condition only for $n = 1, 2$.

1 Introduction

Classically, n -th order infinitesimal flexibility [or rigidity] is defined by the existence [or nonexistence] of nominal k -th derivative of the vertex coordinates for $k = 1, \dots, n$, called k -th order flex, that make the 1-st to n -th order derivative of length constraints being 0, and that the first order flex is nontrivial. This is a natural definition derived by the Taylor series expansion of the edge length. Intuitively, the higher the order, the closer the system is to a finite mechanism. So, the proper definition should satisfy the following: (1) n -th order rigidity implies $n + 1$ -th order rigidity and (2) n -th order rigidity implies finite rigidity (equivalently, (1') $n + 1$ -th order flexibility implies n -th order rigidity and (2) finite flexibility implies n -th order flexibility). However, the cusp mechanism introduced in [Connelly and Servatius, 1994] is a counterexample, which is third order rigid but is finitely flexible; so the classic definition of higher order rigidity is not proper.

I propose a “proper” definition of n -th order rigidity using the arclength along the configuration space to solve this issue. The proposed definition is compatible with the classic definition, in the sense that the classic definition is a sufficient condition for the n -th flexibility in the proposed definition, and that the first and second order rigidity are equivalent in both definitions.

2 Definition

Definition 1 (Finite Flexibility of a bar-and-joint framework). A *bar-and-joint framework* or a *truss*, is a system of V vertices in \mathbb{R}^3 and E bars. Each vertex

coordinate is \mathbf{x}_u ($u = 1, \dots, V$), and a bar $e_{u,v}$ connecting between vertices u and v have prescribed length $\ell_{u,v}$. A *configuration* is a set of \mathbf{x}_u ($u = 1, \dots, V$) satisfying the length of $e_{u,v}$ being $\ell_{u,v}$. The configuration can be described as a point \mathbf{X} in \mathbb{R}^{3V} by concatenating the vertex coordinates as a single column. The *configuration space* of the truss is the set of configurations in \mathbb{R}^{3V} . Here, we assume that sufficient number of vertices are fixed in space, so that the rigid body motion of the whole cannot happen. We say the system (*finitely flexible*) at a configuration \mathbf{X}_0 if there is a non-trivial C^∞ continuous path $\mathbf{X}(t)$ in the configuration space passing through $\mathbf{X}(0) = \mathbf{X}_0$ that lies entirely in the configuration space; otherwise it is (*finitely rigid*).

Precisely, let $\mathbf{x}_u = [x_u, y_u, z_u]^\top$ denote the coordinate of vertex u ($u = 1, \dots, V$); then the configuration of the truss is

$$\mathbf{X} = \begin{bmatrix} \mathbf{x}_1 \\ \vdots \\ \mathbf{x}_u \\ \vdots \\ \mathbf{x}_V \end{bmatrix} = \begin{bmatrix} x_1 \\ y_1 \\ z_1 \\ \vdots \\ x_V \\ y_V \\ z_V \end{bmatrix},$$

Also, let the e -th edge of all E edges be incident to u and v and has prescribed length $\ell_{u,v}$. Then, the length of the edge is preserved and thus the elongation measured by the squared length is

$$D_e(\mathbf{X}) := (\mathbf{x}_u - \mathbf{x}_v)^\top (\mathbf{x}_u - \mathbf{x}_v) - \ell_{u,v}^2,$$

must be 0 for each edge. Note that D_e is a proper measure for the actual elongation $d_e := \|\mathbf{x}_u - \mathbf{x}_v\| - \ell_{u,v}$ because $D_e = (\|\mathbf{x}_u - \mathbf{x}_v\| + \ell_{u,v})d_e = \Theta(d_e)$ as t approaches to 0 because the bar lengths are finite and $\|\mathbf{x}_u - \mathbf{x}_v\| + \ell_{u,v} \neq 0$. This can be represented as a vector equation $\mathbf{D}(\mathbf{X}) = \mathbf{0}_E$, where e -th element of \mathbf{D} is D_e , i.e.,

$$\mathbf{D}(\mathbf{X}) = \begin{bmatrix} D_1(\mathbf{X}) \\ \vdots \\ D_e(\mathbf{X}) \\ \vdots \\ D_E(\mathbf{X}) \end{bmatrix}$$

Definition 2 (Proposed Definition of n -th order rigidity). A pin-and-joint framework is *n -th order infinitesimally flexible* ($n \in \mathbb{N}$) at a configuration \mathbf{X}_0 if there is a non-trivial C^∞ continuous path $\mathbf{X}(t)$ in the configuration space passing through $\mathbf{X}(0) = \mathbf{X}_0$ that keeps the order of the elongation D_e for every edge e in $o(s^n)$ as s approaches to 0, where $s = s(t) = \int_0^t \frac{d\|\mathbf{X}(t)\|}{dt} dt$ is the arclength

along the path¹, otherwise it is n -th order infinitesimally rigid.

Theorem 3 (Proper). *By definition, n -th order rigidity implies $n + 1$ -th order rigidity. n -th order rigidity implies finite rigidity.*

3 Flex and Flexibility

Now we compare the proposed definition with the classic definition. Consider a motion $\mathbf{X}(t)$ where $t = 0$ represents the initial state. The change of squared length of edge $e = (u, v)$ is $D_e(t) = D_e(\mathbf{X}(t))$; then $D_e(0) = 0$. Now the Taylor series expansion of the squared length gives

$$D_e(t) = \sum_{k=1}^n \frac{1}{k!} \sum_{a=0}^k \binom{k}{a} (\mathbf{x}_u^{(a)} - \mathbf{x}_v^{(a)})^\top (\mathbf{x}_u^{(k-a)} - \mathbf{x}_v^{(k-a)}) t^k + o(t^n) \quad (1)$$

Definition 4 (Classic Definition). The formal derivatives $(\mathbf{X}^{(1)} \dots, \mathbf{X}^{(n)})$ satisfying

$$\sum_{a=0}^k \binom{k}{a} (\mathbf{x}_u^{(a)} - \mathbf{x}_v^{(a)})^\top (\mathbf{x}_u^{(k-a)} - \mathbf{x}_v^{(k-a)}) = 0, \quad (2)$$

where $\mathbf{X}^{(0)} := \mathbf{X}$, for every bar connecting u and v and for all $k = 1, \dots, n$ is called n -th order flex.

Theorem 5 (Classic n -th Order Flexibility is Sufficient). *A bar-and-joint framework is n -th order flexible if there is n -th order flex $(\mathbf{X}^{(1)} \dots, \mathbf{X}^{(n)})$ with nontrivial first order flex $\mathbf{X}^{(0)} \neq \mathbf{0}$.*

Proof. Given n -th order flex, $(\mathbf{X}^{(1)} \dots, \mathbf{X}^{(n)})$, construct a path $\mathbf{X}(t) = \mathbf{X}_0 + \mathbf{X}^{(1)}t + \frac{1}{2}\mathbf{X}^{(2)}t^2 + \dots + \frac{1}{n!}\mathbf{X}^{(n)}t^n$, so that k -th derivative of the curve at the initial state equals the k -th term of the given flex. Then, $D_e(t) - \ell_e^2 = o(t^n)$. The arclength along this path is first order with respect to t , i.e., $s = \Theta(t)$ because $\frac{ds}{dt} = \|\mathbf{X}^{(1)}\| \neq 0$. Therefore, $D_e(t) - \ell_e^2 = o(s^n)$, and thus it is n -th order flexible. \square

Theorem 6 (First and Second Order). *A bar-and-joint framework is first order flexible if and only if there is nontrivial first order flex $\mathbf{X}^{(1)}$. A bar-and-joint framework is second order flexible if there is second order flex $(\mathbf{X}^{(1)}, \mathbf{X}^{(2)})$ with nontrivial first order flex $\mathbf{X}^{(1)}$.*

¹Here, we discuss the order of error as t approaches to 0. The big O notation $f(t) = O(g(t))$ represents the upper bound, i.e., there exists a constant $k > 0$ such that $|g(t)| \leq k|f(t)|$ for a sufficiently small $t > 0$, while small o notation $f(t) = o(g(t))$ represents that g dominates f , i.e., for any value $k > 0$, $|g(t)| \leq k|f(t)|$ for a sufficiently small $t > 0$. For example, $t^2 = O(t^2) = o(t)$. Also, big Omega $f(t) = \Omega(g(t))$ is used to represent the lower bound i.e., $k > 0$ such that $|g(t)| \geq k|f(t)|$ for a sufficiently small $t > 0$. If $f(t) = O(g(t))$ and $f(t) = \Omega(g(t))$ at the same time, we get a tight order expression $f(t) = \Theta(g(t))$.

Proof. For necessity for $n = 1, 2$ cases, consider that $s = \Theta(t^n)$ and thus $\frac{d^k s}{dt^k} = 0$ ($k = 1, \dots, n - 1$) and $\frac{d^n s}{dt^n} \neq 0$. Then, take the first $2n$ term of (1).

$$D_e(t) = \frac{2}{n!} \left(\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)} \right)^\top \left(\mathbf{x}_u^{(n)} - \mathbf{x}_v^{(n)} \right) t^n + o(t^n) \quad (3)$$

and

$$\begin{aligned} D_e(t) &= \sum_{k=0}^{n-1} \frac{2}{(n+k)!} \left(\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)} \right)^\top \left(\mathbf{x}_u^{(n+k)} - \mathbf{x}_v^{(n+k)} \right) t^{n+k} \\ &+ \frac{1}{2n!} \left(2 \left(\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)} \right)^\top \left(\mathbf{x}_u^{(2n)} - \mathbf{x}_v^{(2n)} \right) + \binom{2n}{n} \left(\mathbf{x}_u^{(n)} - \mathbf{x}_v^{(n)} \right)^\top \left(\mathbf{x}_u^{(n)} - \mathbf{x}_v^{(n)} \right) \right) t^{2n} \\ &+ o(t^{2n}) \end{aligned} \quad (4)$$

If we substitute $\rho_i^{(n)} \rightarrow \rho_i^{(1)}$ and $\frac{1}{2} \binom{2n}{n} \rho_i^{(2n)} \rightarrow \rho_i^{(2)}$, then t^n term of (3) eliminates only if there exists a non-trivial first order flex, and t^{2n} term of (4) eliminates only if there exists a second order flex with non-trivial first order flex. \square

Notice that the approach used in the proof does not extend any longer. For example, the coefficient of t^{3n} term eliminates only if

$$\begin{aligned} &2 \left(\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)} \right)^\top \left(\mathbf{x}_u^{(3n)} - \mathbf{x}_v^{(3n)} \right) + 2 \binom{3n}{n} \left(\mathbf{x}_u^{(n)} - \mathbf{x}_v^{(n)} \right)^\top \left(\mathbf{x}_u^{(2n)} - \mathbf{x}_v^{(2n)} \right) \\ &+ \sum_{k=1}^{n-1} \binom{3n}{n+k} \left(\mathbf{x}_u^{(n+k)} - \mathbf{x}_v^{(n+k)} \right)^\top \left(\mathbf{x}_u^{(2n-k)} - \mathbf{x}_v^{(2n-k)} \right) = 0. \end{aligned} \quad (5)$$

The first two terms represent the third order flex, but there are extra terms making the equation satisfy in a different way making use of from $n+1$ to $2n-1$ terms. This is an interpretation of the result of [Connelly and Servatius, 1994] that third order flexibility cannot be defined by the existence of third order flex.

4 Cusp Mechanism

Let us check how the “flexes” of a cusp mechanism could be represented in the example of connected Watt’s mechanism introduced in [Connelly and Servatius, 1994]. Refer to Figure 1.

In this mechanism, we assume the parameterization $s = \Theta(t^2)$. Then, the




Figure 1: Cusp mechanism constructed by connecting a pair of Watt's mechanisms.

derivative of D_e up to 6-th order is

$$D_e^{(1)}(0) = 0 \quad (6)$$

$$\frac{1}{2}D_e^{(2)}(0) = (\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)})^\top (\mathbf{x}_u^{(2)} - \mathbf{x}_v^{(2)}) \quad (7)$$

$$\frac{1}{2}D_e^{(3)}(0) = (\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)})^\top (\mathbf{x}_u^{(3)} - \mathbf{x}_v^{(3)}) \quad (8)$$

$$\begin{aligned} \frac{1}{2}D_e^{(4)}(0) &= (\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)})^\top (\mathbf{x}_u^{(4)} - \mathbf{x}_v^{(4)}) \\ &\quad + 3(\mathbf{x}_u^{(2)} - \mathbf{x}_v^{(2)})^\top (\mathbf{x}_u^{(2)} - \mathbf{x}_v^{(2)}) \end{aligned} \quad (9)$$

$$\begin{aligned} \frac{1}{2}D_e^{(5)}(0) &= (\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)})^\top (\mathbf{x}_u^{(5)} - \mathbf{x}_v^{(5)}) \\ &\quad + 10(\mathbf{x}_u^{(2)} - \mathbf{x}_v^{(2)})^\top (\mathbf{x}_u^{(3)} - \mathbf{x}_v^{(3)}) \end{aligned} \quad (10)$$

$$\begin{aligned} \frac{1}{2}D_e^{(6)}(0) &= (\mathbf{x}_u^{(0)} - \mathbf{x}_v^{(0)})^\top (\mathbf{x}_u^{(6)} - \mathbf{x}_v^{(6)}) \\ &\quad + 15(\mathbf{x}_u^{(2)} - \mathbf{x}_v^{(2)})^\top (\mathbf{x}_u^{(4)} - \mathbf{x}_v^{(4)}) \\ &\quad + 10(\mathbf{x}_u^{(3)} - \mathbf{x}_v^{(3)})^\top (\mathbf{x}_u^{(3)} - \mathbf{x}_v^{(3)}) \end{aligned} \quad (11)$$

The mechanism is third-order flexible if and only if (6)–(11) are zero.

Point \mathbf{p}_1 rotating along a circle, whose radius bar direction is initially $\begin{bmatrix} 1 \\ 0 \end{bmatrix}$, should have the following flexes:

$$\begin{aligned} &(\mathbf{p}_1^{(1)}, \mathbf{p}_1^{(2)}, \mathbf{p}_1^{(3)}, \mathbf{p}_1^{(4)}, \mathbf{p}_1^{(5)}, \mathbf{p}_1^{(6)}) = \\ &\left(\begin{bmatrix} 0 \\ 0 \end{bmatrix}, \begin{bmatrix} 0 \\ a_1 \end{bmatrix}, \begin{bmatrix} 0 \\ b_1 \end{bmatrix}, \begin{bmatrix} -3a_1^2 \\ c_1 \end{bmatrix}, \begin{bmatrix} -10a_1b_1^2 \\ d_1 \end{bmatrix}, \begin{bmatrix} -15a_1c_1 - 10b_1^2 \\ e_1 \end{bmatrix} \right) \end{aligned} \quad (12)$$

By symmetry, point \mathbf{p}_2 has the following 6-th order flexes:

$$\begin{aligned} & \left(\mathbf{p}_2^{(1)}, \mathbf{p}_2^{(2)}, \mathbf{p}_2^{(3)}, \mathbf{p}_2^{(4)}, \mathbf{p}_2^{(5)}, \mathbf{p}_2^{(6)} \right) = \\ & \left(\begin{bmatrix} 0 \\ 0 \end{bmatrix}, \begin{bmatrix} 0 \\ a_2 \end{bmatrix}, \begin{bmatrix} 0 \\ b_2 \end{bmatrix}, \begin{bmatrix} 0 \\ c_2 \end{bmatrix}, \begin{bmatrix} 3a_2^2 \\ 10a_2b_2 \\ d_2 \end{bmatrix}, \begin{bmatrix} 15a_2c_2 + 10b_2^2 \\ e_2 \end{bmatrix} \right) \end{aligned} \quad (13)$$

Now, consider the bar connecting \mathbf{p}_1 and \mathbf{p}_2 , whose initial direction is $(\mathbf{p}_2 - \mathbf{p}_1) = \begin{bmatrix} 1 \\ 1 \end{bmatrix}$. By (7) and (8) being 0, we get $a_1 = a_2 = a$ and $b_1 = b_2 = b$. By (9) and (10) being 0, we get $c_1 - c_2 = 6a^2$ and $d_1 - d_2 = 20ab$. By (11) being 0, we get $e_1 - e_2 = 15a(c_1 + c_2) + 20b^2$.

The midpoint \mathbf{q} of \mathbf{p}_1 and \mathbf{p}_2 have the following flexes:

$$\begin{aligned} & \left(\mathbf{q}^{(1)}, \mathbf{q}^{(2)}, \mathbf{q}^{(3)}, \mathbf{q}^{(4)}, \mathbf{q}^{(5)}, \mathbf{q}^{(6)} \right) = \\ & \left(\begin{bmatrix} 0 \\ 0 \end{bmatrix}, \begin{bmatrix} 0 \\ a \end{bmatrix}, \begin{bmatrix} 0 \\ b \end{bmatrix}, \begin{bmatrix} 0 \\ \frac{1}{2}(c_1 + c_2) \end{bmatrix}, \begin{bmatrix} 0 \\ \frac{1}{2}(d_1 + d_2) \end{bmatrix}, \begin{bmatrix} -45a^3 \\ \frac{1}{2}(e_1 + e_2) \end{bmatrix} \right) \end{aligned} \quad (14)$$

By symmetry, the midpoint $\bar{\mathbf{q}}$ of the other Watt's mechanism have the following flexes:

$$\begin{aligned} & \left(\bar{\mathbf{q}}^{(1)}, \bar{\mathbf{q}}^{(2)}, \bar{\mathbf{q}}^{(3)}, \bar{\mathbf{q}}^{(4)}, \bar{\mathbf{q}}^{(5)}, \bar{\mathbf{q}}^{(6)} \right) = \\ & \left(\begin{bmatrix} 0 \\ 0 \end{bmatrix}, \begin{bmatrix} 0 \\ \bar{a} \end{bmatrix}, \begin{bmatrix} 0 \\ \bar{b} \end{bmatrix}, \begin{bmatrix} 0 \\ \frac{1}{2}(\bar{c}_1 + \bar{c}_2) \end{bmatrix}, \begin{bmatrix} 0 \\ \frac{1}{2}(\bar{d}_1 + \bar{d}_2) \end{bmatrix}, \begin{bmatrix} 45\bar{a}^3 \\ \frac{1}{2}(\bar{e}_1 + \bar{e}_2) \end{bmatrix} \right) \end{aligned} \quad (15)$$

Horizontal bar connecting \mathbf{q} and $\bar{\mathbf{q}}$ has the direction of $\begin{bmatrix} 1 \\ 0 \end{bmatrix}$. For this bar, (6)-(8) are all 0. Now from (9) being 0, we get $a = \bar{a}$, which automatically make (10) 0. The last term (11) being 0 gives $9a^3 + (\bar{b} - b)^2 = 0$. This equation well describes the assymmetric behavior of the mechanism at the cusp point (Figure 2);

1. it forces that $a < 0$, meaning that the horizontal bar must drop down instead of going up; and
2. the sign of $\bar{b} - b = \pm\sqrt{-a^3}$ determines which way the bar is going to be tilted.

5 Discussion

The definition of measuring the order of edge elongation with respect to the arclength along the kinematic path solves the issue of infinitesimal rigidity. There are variants of the measure we can use instead of arclength, e.g., the displacement $d = \|\mathbf{X}(t) - \mathbf{X}_0\|$ because they are related to each other in first order. In fact, the definition straightforwardly relates the displacement and the elongation of the element, so I believe it is a “natural” definition that engineers would agree.




Figure 2: The bifurcation of the motion of horizontal bar.

Non integer number of degrees of rigidity can be potentially defined in the proposed definition. An open question arises from here: are there systems with tightly non-integer order of rigidity, e.g., are there 3-rd order flexible but 3.5-th order rigid systems?

References

- [Connelly and Servatius, 1994] Connelly, R. and Servatius, H. (1994). Higher-order rigidity—what is the proper definition? *Discrete & Computational Geometry*, 11:193–200.