What quantum "state" really is?

Alexander M. SOIGUINE

Copyright © 2014

Abstract: To get out of logical deadlock in interpreting gedanken experiments like "Schrodinger cat", actual meaning of a "wave function", or a "state", in the case of complex two-dimensional Hilbert space, is shown to be an element of even subalgebra of geometric algebra [1], [2] over three-dimensional Euclidian space.

ב. לא תִהְיֶה אַחֲרֵי רַבִּים לְרָעֹת וְלא תַעֲנֶה עַל רִב לְנְטֹת אַחֲרֵי רַבִּים לְהַטֹת: Exodus 23:2¹

1. Introduction

The geometric algebra G_3^+ [1] formalism is more profound compared to formal quantum mechanical representation of two-state observables by "complex" amplitudes as components of elements in two-dimensional Hilbert space. It has been used in to describe tossed coin experiment that was pretty similar to traditional quantum mechanical formalism [3].

Mathematical frame will be here the even subalgebra $G_3^{\scriptscriptstyle +}$ of elements:

$$so(\alpha, \beta, S) = \alpha + \beta I_s$$

of geometric algebra G_3 over Euclidian space E_3 . G_3 has the basis

 $\{1, e_1, e_2, e_3, e_1e_2, e_2e_3, e_3e_1, e_1e_2e_3\},\$

¹ You shall not follow the majority for evil, and you shall not respond concerning a lawsuit to follow many to pervert [justice].

where $\{e_i\}$ are orthonormal basis vectors in E_3 , $\{e_ie_j\}$ - oriented, mutually orthogonal unit value areas spanned by e_i and e_j as edges, $e_1e_2e_3$ - unit value oriented volume spanned by ordered edges e_1 , e_2 and e_3 .

Subalgebra G_3^+ is spanned by $\{1, e_1e_2, e_2e_3, e_3e_1\}$. Variables α and β in $so(\alpha, \beta, S)$ are (real²) scalars, I_s is a unit size oriented area (lefthanded or righthanded) in an arbitrary given plane $S \subset E_3$.

I explained in detail [4], [5] that elements $so(\alpha, \beta, S) = \alpha + \beta I_s$ only differ from what is traditionally called "complex numbers" by the fact that $S \subset E_3$ is an arbitrary, variable plane and is not the whole space of game. Putting it simply, $\alpha + \beta I_s$ are "complex numbers" depending on E_2 embedded into E_3 . E_2 is the space where S belongs. Traditional "imaginary unit" i is just I_s when it is not necessary to specify the plane – everything is going on in one fixed plane, not in 3D world. Fully formal way of using i as a "number", just with additional algebraic property $i^2 = -1$, may be a source of deeply wrong interpretations, particularly in quantum mechanics.

2. Rotations and elements of G_3^+

If g_3 is element of G_3 , its rotation in 3D can be written as [1], [2]:

$$g_3 \rightarrow (\alpha - \beta I_s)g_3(\alpha + \beta I_s)$$

where $\alpha + \beta I_s = \alpha + \beta (b_1 e_2 e_3 + b_2 e_3 e_1 + b_3 e_1 e_2)$ is unit value element of G_3^+ , that's $\alpha^2 + \beta^2 = 1$ and $b_1^2 + b_2^2 + b_3^2 = 1$. I will name such elements G_3^+ - states. G_3^+ - states can also be considered as points on unit radius sphere S^3 . Parameter α is cosine of half of angle of rotation, I_s is unit value bivector in plane S orthogonal to axis of rotation³. Since $\alpha^2 + \beta^2 = 1$ we can write

$$g_3 \rightarrow (\cos\frac{\varphi}{2} - \sin\frac{\varphi}{2}I_s)g_3(\cos\frac{\varphi}{2} + \sin\frac{\varphi}{2}I_s) \equiv \exp\left(-\frac{\varphi}{2}I_s\right)g_3\exp\left(\frac{\varphi}{2}I_s\right)$$

Particularly, if g_3 is a bivector, $C = C_1 e_2 e_3 + C_2 e_3 e_1 + C_3 e_1 e_2^4$ (representing, for example, object with axial symmetry), its rotation has symmetry:

² Scalars should always be real. "Complex" scalars are not scalars.

³ Axis of rotation together with the bivector orientation should be compatible with orientation of $e_1e_2e_3$.

⁴ I will often identically use the same term for bivector and its plane.

$$C \to \exp\left(-\frac{\varphi}{2}I_s\right)C\exp\left(\frac{\varphi}{2}I_s\right) = \exp\left(-\frac{\varphi}{2}I_s\right)\exp\left(-\frac{\vartheta}{2}I_c\right)C\exp\left(\frac{\vartheta}{2}I_c\right)\exp\left(\frac{\varphi}{2}I_s\right),$$

that simply means that nothing changes if bivector is also rotated in its own plane [3]. It formally follows from:

$$(\alpha - \beta I_s)C(\alpha + \beta I_s) = (\alpha^2 - \beta^2)C - 2\alpha\beta(I_s \times C) - 2\beta^2 I_s(I_s \cdot C), \qquad (2.1)$$

where $I_s \times C = \frac{1}{2} (I_s C - CI_s)$, $I_s \cdot C = \frac{1}{2} (I_s C + CI_s)$. That obviously means that if we rotate bivector with unit element $so(\alpha, \beta, S)$ and both have parallel bivector planes, that's $I_s = C$, then bivector C remains the same.

If we observe a real physical object identified by bivector, say axially symmetric object, and the result of observation is just its orientation in 3D, its rotation in its own plane around central axis is not detectable. Angle, or phase, of such rotation should be considered as unspecified variable [3]. But that does not mean the variable does not comprise some physically meaningful feature.

If
$$C = e_2 e_3$$
 then:

$$(\alpha - \beta I_{s})e_{2}e_{3}(\alpha + \beta I_{s}) = (\alpha - \beta(b_{1}e_{2}e_{3} + b_{2}e_{3}e_{1} + b_{3}e_{1}e_{2}))e_{2}e_{3}(\alpha + \beta(b_{1}e_{2}e_{3} + b_{2}e_{3}e_{1} + b_{3}e_{1}e_{2})) = (\alpha - \beta_{1}e_{2}e_{3} - \beta_{2}e_{3}e_{1} - \beta_{3}e_{1}e_{2})e_{2}e_{3}(\alpha + \beta_{1}e_{2}e_{3} + \beta_{2}e_{3}e_{1} + \beta_{3}e_{1}e_{2}) = (\alpha^{2} + \beta_{1}^{2} - \beta_{2}^{2} - \beta_{3}^{2})e_{2}e_{3} + 2(\alpha\beta_{3} + \beta_{1}\beta_{2})e_{3}e_{1} + 2(\beta_{1}\beta_{3} - \alpha\beta_{2})e_{1}e_{2}, \text{ where } \beta_{i} \equiv \beta b_{i}.$$

This is classical Hopf fibration $S^3 \to S^2$: $so(\alpha, \beta, S) \xrightarrow{e_2e_3} C_{rot}$, where

$$C_{rot} = (\alpha^2 + \beta_1^2 - \beta_2^2 - \beta_3^2)e_2e_3 + 2(\alpha\beta_3 + \beta_1\beta_2)e_3e_1 + 2(\beta_1\beta_3 - \alpha\beta_2)e_1e_2$$
(2.2)

Also it shows that "imaginary" number i in that Hopf fibration should geometrically be unit value oriented area e_2e_3 orthogonal to basis vector e_1 . Orientations of e_1 and e_2e_3 must be in agreement with $e_1e_2e_3$ orientation.

Generalized Hopf fibration can be generated by any bivector C:

$$S^{3} \rightarrow S^{2} : so(\alpha, \beta, S) \xrightarrow{C} C_{rot},$$

and (2.1) gives the result.

Often it is more convenient to deal with this result explicitly written in the basis bivector components. We know the result (2.2) for $so(\alpha, \beta, S) \xrightarrow{e_2e_3} C_{rot}$. For two other basis bivector components we have:

$$so(\alpha, \beta, S) \xrightarrow{e_3e_1} C_{rot} = 2(\beta_1\beta_2 - \alpha\beta_3)e_2e_3 + [(\alpha^2 + \beta_2^2) - (\beta_1^2 + \beta_3^2)]e_3e_1 + 2(\alpha\beta_1 + \beta_2\beta_3)e_1e_2$$

$$so(\alpha, \beta, S) \xrightarrow{e_1e_2} C_{rot} = 2(\alpha\beta_2 + \beta_1\beta_3)e_2e_3 + 2(\beta_2\beta_3 - \alpha\beta_1)e_3e_1 + [(\alpha^2 + \beta_3^2) - (\beta_1^2 + \beta_2^2)]e_1e_2$$

Then:

$$so(\alpha, \beta, S) \xrightarrow{C_{1}e_{2}e_{3}+C_{2}e_{3}e_{1}+C_{3}e_{1}e_{2}} C_{rot} = C_{1}([(\alpha^{2} + \beta_{1}^{2}) - (\beta_{2}^{2} + \beta_{3}^{2})]e_{2}e_{3} + 2(\alpha\beta_{3} + \beta_{1}\beta_{2})e_{3}e_{1} + 2(\beta_{1}\beta_{3} - \alpha\beta_{2})e_{1}e_{2}) + C_{2}(2(\beta_{1}\beta_{2} - \alpha\beta_{3})e_{2}e_{3} + [(\alpha^{2} + \beta_{2}^{2}) - (\beta_{1}^{2} + \beta_{3}^{2})]e_{3}e_{1} + 2(\alpha\beta_{1} + \beta_{2}\beta_{3})e_{1}e_{2}) + C_{3}(2(\alpha\beta_{2} + \beta_{1}\beta_{3})e_{2}e_{3} + 2(\beta_{2}\beta_{3} - \alpha\beta_{1})e_{3}e_{1} + [(\alpha^{2} + \beta_{3}^{2}) - (\beta_{1}^{2} + \beta_{2}^{2})]e_{1}e_{2}) =$$

$$(C_{1}[(\alpha^{2} + \beta_{1}^{2}) - (\beta_{2}^{2} + \beta_{3}^{2})] + 2C_{2}(\beta_{1}\beta_{2} - \alpha\beta_{3}) + 2C_{3}(\alpha\beta_{2} + \beta_{1}\beta_{3}))e_{2}e_{3} + (2C_{1}(\alpha\beta_{3} + \beta_{1}\beta_{2}) + C_{2}[(\alpha^{2} + \beta_{2}^{2}) - (\beta_{1}^{2} + \beta_{3}^{2})] + 2C_{3}(\beta_{2}\beta_{3} - \alpha\beta_{1}))e_{3}e_{1} + (2C_{1}(\beta_{1}\beta_{3} - \alpha\beta_{2}) + 2C_{2}(\alpha\beta_{1} + \beta_{2}\beta_{3}) + C_{3}[(\alpha^{2} + \beta_{3}^{2}) - (\beta_{1}^{2} + \beta_{2}^{2})])e_{1}e_{2}$$

$$(2.3)$$

Remark 2.1

If we take bivector expanded not in $\{e_2e_3, e_3e_1, e_1e_2\}$ but in arbitrary basis $\{B_1, B_2, B_3\}$, satisfying the same multiplication rules $B_1B_2 = -B_3, B_1B_3 = B_2, B_2B_3 = -B_1$, that's $\alpha + \beta I_s = \alpha + \beta (b_1B_1 + b_2B_2 + b_3B_3) = \alpha + \beta_1B_1 + \beta_1B_1 + \beta_1B_1, \beta_i = \beta b_i$, then, for example, the result of rotation of B_1 is:

$$(\alpha^{2} + \beta_{1}^{2} - \beta_{2}^{2} - \beta_{3}^{2})B_{1} + 2[(\alpha\beta_{3} + \beta_{1}\beta_{2})B_{2} - (\alpha\beta_{2} - \beta_{1}\beta_{3})B_{3}],$$

exactly the same as in the $\{e_2e_3, e_3e_1, e_1e_2\}$ case. So, (2.3) remains valid when replacing $\{e_2e_3, e_3e_1, e_1e_2\}$ with $\{B_1, B_2, B_3\}$.

3. G_3^+ - states instead of wave functions

3.1. Two component quantum states and G_3^+ - states

Let's firstly establish clear relations between the two state wave functions $|\psi\rangle = (c_1, c_2)^T$, where the components c_1, c_2 of the column are "complex" numbers, and elements $so(\alpha, \beta, S) \equiv \alpha + \beta I_s = \alpha + \beta (b_1e_2e_3 + b_2e_3e_1 + b_3e_1e_2)$, $\alpha^2 + \beta^2 = 1$, $b_1^2 + b_2^2 + b_3^2 = 1$.

 G_3^+ - states $so(\alpha, \beta, S) \equiv \alpha + \beta I_s$ are elements of S^3 . Common approach of treating S^3 , which sits in R^4 , is identification of R^4 with C^2 , two dimensional space of "complex" numbers, that is based on their equal dimensionalities:

$$R^{4} \supset S^{3} = \{ z = (z_{1}, z_{2}) \in C^{2}; |z|^{2} = \overline{z}_{1}z_{1} + \overline{z}_{2}z_{2} = 1 \}$$
(3.1)

We are considering elements of S^3 as unit value G_3^+ - states $\alpha + \beta I_s$, $\alpha^2 + \beta^2 = 1$, and should strictly follow the requirement that, if "complex" numbers are involved somewhere, their plane must be explicitly defined. When (3.1) is formally used, a tacit common quantum mechanical assumption is that z_1 and z_2 have the same "complex" plane, otherwise complex conjugation is not well defined [5]. Let's make all that unambiguously clear.

Take a G_3^+ - state:

$$so(\alpha, \beta, S) \equiv so(\alpha, \beta) = \alpha + \beta_1 e_2 e_3 + \beta_2 e_3 e_1 + \beta_3 e_1 e_2, \ \beta_i \equiv \beta b_i$$

We want to rewrite it as a couple of "complex" numbers, used in (3.1), with an explicitly defined plane. I will initially take a "complex" plane as one of the spanned by $\{e_2, e_3\}$, $\{e_3, e_1\}$ or $\{e_1, e_2\}$.

For $\{e_2, e_3\}$ we get:

$$so(\alpha, \vec{\beta}) = (\alpha + \beta_1 e_2 e_3) + \beta_2 e_2 e_3 e_1 e_2 + \beta_3 e_1 e_2 = (\alpha + \beta_1 e_2 e_3) + (\beta_3 + \beta_2 e_2 e_3) e_1 e_2 \equiv z_1^{2,3} + z_2^{2,3} e_1 e_2$$

For $\{e_3, e_1\}$:

$$so(\alpha, \beta) = (\alpha + \beta_2 e_3 e_1) + \beta_3 e_3 e_1 e_2 e_3 + \beta_1 e_2 e_3 = (\alpha + \beta_2 e_3 e_1) + (\beta_1 + \beta_3 e_3 e_1) e_2 e_3 \equiv z_1^{3,1} + z_2^{3,1} e_2 e_3$$

And for $\{e_1, e_2\}$:

$$so(\alpha, \vec{\beta}) = (\alpha + \beta_3 e_1 e_2) + \beta_1 e_1 e_2 e_3 e_1 + \beta_2 e_3 e_1 = (\alpha + \beta_3 e_1 e_2) + (\beta_2 + \beta_1 e_1 e_2) e_3 e_1 \equiv z_1^{1,2} + z_2^{1,2} e_3 e_1$$

Remark 3.1.1

One can notice that the second members in all three cases can be written in two ways. For example:

$$z_2^{2,3}e_1e_2 = (\beta_3 + \beta_2e_2e_3)e_1e_2 = (\beta_2 - \beta_3e_2e_3)e_3e_1.$$

It can be checked that geometrically both give the same bivector.

So, we have three basic maps $so(\alpha, \beta, S) \xleftarrow{e_i e_j} (z_1^{i,j}, z_2^{i,i})$ defined by "complex" planes $\{e_i, e_j\}$. If we are speaking about identification of S^3 and C^2 , we need to explicitly say which plane we use, particularly, which of the three basis (in 3D) "complex" planes we are working in.

The "complex" plane can be different from any of basis planes $\{e_i e_j\}$. Instead of basis of three bivectors $\{e_2 e_3, e_3 e_1, e_1 e_2\}$ we can take, as above, $\{B_1, B_2, B_3\}$. If $S^3 \ni so(\alpha, \beta, S) \equiv \alpha + \beta I_s$ is expanded in basis $\{B_1, B_2, B_3\}$:

$$\alpha + \beta I_{s} = \alpha + \beta (b_{1}B_{1} + b_{2}B_{2} + b_{3}B_{3}) = \alpha + \beta_{1}B_{1} + \beta_{1}B_{1} + \beta_{1}B_{1}, \beta_{i} = \beta b_{i},$$

then, for example, taking B_1 as "complex" plane we get:

$$\alpha + \beta_1 B_1 + \beta_1 B_1 + \beta_1 B_1 = \alpha + \beta_1 B_1 + \beta_2 B_1 B_3 + \beta_3 B_3 = \alpha + \beta_1 B_1 + (\beta_3 + \beta_2 B_1) B_3 \rightarrow ((\alpha + \beta_1 B_1), (\beta_3 + \beta_2 B_1)) \equiv (z_1, z_2)$$

Let's get back to the case of "complex" plane spanned by $\{e_2, e_3\}$:

$$so(\alpha, \vec{\beta}) = (\alpha + \beta_1 e_2 e_3) + \beta_2 e_2 e_3 e_1 e_2 + \beta_3 e_1 e_2 = (\alpha + \beta_1 e_2 e_3) + (\beta_3 + \beta_2 e_2 e_3) e_1 e_2 \equiv z_1^{2,3} + z_2^{2,3} e_1 e_2,$$

In this case wave function $|\psi\rangle = (z_1^{2,3}, z_2^{2,3})^T$ corresponding to $so(\alpha, \beta, S)$ is:

$$\left|\psi\right\rangle = \left(\alpha + \beta_{1}e_{2}e_{3}, \beta_{3} + \beta_{2}e_{2}e_{3}\right)^{T}$$
(3.2)

Let's consider the Pauli's matrices⁵, basis of "observables" in traditional quantum mechanics:

$$\hat{\sigma}_1 = \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix}, \ \hat{\sigma}_2 = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}, \ \hat{\sigma}_3 = \begin{pmatrix} 0 & i \\ -i & 0 \end{pmatrix}, \ (i \equiv e_2 e_3)$$

⁵ Some modifications were necessary to follow handedness.

which are in one-to-one correspondence with our basis bivectors, namely all G_3^+ geometric algebra equations can be expressed in terms of $\hat{\sigma}_k$ through $e_2e_3 = I_3\hat{\sigma}_1$, $e_3e_1 = I_3\hat{\sigma}_2$ and $e_1e_2 = I_3\hat{\sigma}_3$, where $I_3 \equiv e_1e_2e_3$ [4].

Usual quantum mechanical calculations with Pauli's matrices give the following:

$$\langle \psi | \hat{\sigma}_1 | \psi \rangle = \alpha^2 + \beta_1^2 - \beta_2^2 - \beta_3^2, \ \langle \psi | \hat{\sigma}_2 | \psi \rangle = 2(\alpha \beta_3 + \beta_1 \beta_2), \ \langle \psi | \hat{\sigma}_3 | \psi \rangle = 2(\beta_1 \beta_3 - \alpha \beta_2),$$

where $\langle \psi |$ is element conjugated to $|\psi \rangle$:

$$\langle \psi | = (\alpha - \beta_1 e_2 e_3, \beta_3 - \beta_2 e_2 e_3)$$

Each of the products $\langle \psi | \hat{\sigma}_i | \psi \rangle$ gives only one component of usual Hopf fibration, contrary to $(\alpha - \beta I_s)e_2e_3(\alpha + \beta I_s)$, giving full vector. It looks like in the mapping $so(\alpha, \beta, S) \in G_3^+ \sim S^3 \rightarrow C^2 \ni |\psi\rangle$ some information was lost. Indeed, information was lost in several ways. Only one particular basis plane remains in $|\psi\rangle$ as "complex" plane. Then, algebraic coincidence of multiplication rules for Pauli matrices and basis bivectors $\{e_ie_j\}$ is not equivalent to their geometrical identity: the matrices do not have an appropriate geometrical sense. And also the products $\langle \psi | \hat{\sigma}_i | \psi \rangle$ are scalar products of two vectors, where $|\psi\rangle$ contains complex conjugation relative to plane which is preselected as "complex" one. The whole design of $\langle \psi | \hat{\sigma}_i | \psi \rangle$ was aimed at receiving three components of rotation $(\alpha - \beta I_s)e_2e_3(\alpha + \beta I_s)$, without actual geometrical sense of operations. Not surprising that it was possible to formally prove [6] that "hidden variables" do not exist in the Hilbert space formalism.

Following the paradigm of [3] I assume that actual meaning of quantum mechanical wave functions, at least in the case of axially symmetric objects, is that the functions should be elements of G_3^+ , $(\alpha + \beta I_s)$, returning observation of bivectors *C* representing orientation of physical objects:

$$C \rightarrow (\alpha - \beta I_s)C(\alpha + \beta I_s)$$

Then Schrodinger equation should correspond to equation governing changes in time of a G_3^+ - state. So, the actual difference between "classical" and "quantum" mechanics is only shift of viewpoint: instead of dealing with equations describing an axially symmetric physical object orientation, as in classical mechanics, we deal in quantum mechanics with equations describing evolution in time of the operation, G_3^+ - state, which returns the physical object orientation.

3.2. Stable states in terms of G_3^+ - states

In traditional quantum mechanics "state" of magnetic dipole in static magnetic field is defined by wave function $|\psi\rangle = z_1|0\rangle + z_2|1\rangle$ with the two basis "stable states" $|0\rangle$ and $|1\rangle$. In our terms the two "states" are, correspondingly, the set of all G_3^+ - states $\alpha + \beta_1 e_2 e_3$, with $\alpha^2 + \beta_1^2 = 1$, and the set of all G_3^+ - states $\beta_2 e_3 e_1 + \beta_3 e_1 e_2$, with $\beta_2^2 + \beta_3^2 = 1$. The bivector plane $e_2 e_3$ is taken as "complex plane"⁶. When any of the first kind of "stable G_3^+ - states" $\alpha + \beta_1 e_2 e_3$ acts on $e_2 e_3$ we get:

$$(\alpha - \beta_1 e_2 e_3) e_2 e_3 (\alpha + \beta_1 e_2 e_3) = (\alpha^2 + \beta_1^2) e_2 e_3 = e_2 e_3$$

With the second kind, $\beta_2 e_3 e_1 + \beta_3 e_1 e_2$, we have:

$$(-\beta_2 e_3 e_1 - \beta_3 e_1 e_2) e_2 e_3 (\beta_2 e_3 e_1 + \beta_3 e_1 e_2) = -(\beta_2^2 + \beta_3^2) e_2 e_3 = -e_2 e_3.$$

This is actual meaning of quantum mechanical "stable states": any single one from the set of all G_3^+ - states, corresponding to $|0\rangle$, leaves e_2e_3 unchanged, just rotates e_2e_3 in its own plane. Every single G_3^+ - state from the set of all G_3^+ - states, corresponding to $|1\rangle$, flips e_2e_3 .

Let's take an arbitrary bivector $C = C_1e_2e_3 + C_2e_3e_1 + C_3e_1e_2$. Transforming it with $\alpha + \beta_1e_2e_3$ we get:

$$(\alpha - \beta_1 e_2 e_3)C(\alpha + \beta_1 e_2 e_3) = C_1 e_2 e_3 + \left[(\alpha - \beta_1^2)C_2 - 2\alpha\beta_1 C_3\right]e_3 e_1 + \left[(\alpha - \beta_1^2)C_3 + 2\alpha\beta_1 C_2\right]e_1 e_2$$

Parameterization $\alpha = \cos \varphi$, $\beta_1 = \sin \varphi$ gives:

$$(\alpha - \beta_1 e_2 e_3)C(\alpha + \beta_1 e_2 e_3) = C_1 e_2 e_3 + (C_2 \cos 2\varphi - C_3 \sin 2\varphi)e_3 e_1 + (C_2 \sin 2\varphi + C_3 \cos 2\varphi)e_1 e_2, \quad (3.3)$$

which means that the bivector component in e_2e_3 does not change, while bivector $C_2e_3e_1 + C_3e_1e_2$ is rotated by angle 2φ around the axis of intersection of e_3e_1 and e_1e_2 .

Taking a G_3^+ - state from the set of second kind basis G_3^+ - states $\beta_2 e_3 e_1 + \beta_3 e_1 e_2$ we get the result:

$$(-\beta_2 e_3 e_1 - \beta_3 e_1 e_2)C(\beta_2 e_3 e_1 + \beta_3 e_1 e_2) = -C_1 e_2 e_3 + [(\beta_2^2 - \beta_3^2)C_2 + 2\beta_2 \beta_3 C_3]e_3 e_1 + [(\beta_3^2 - \beta_2^2)C_3 + 2\beta_2 \beta_3 C_2]e_1 e_2$$

Again, using parameterization $\beta_2 = \cos \vartheta$, $\beta_3 = \sin \vartheta$, we get:

⁶ It does not actually matter which bivector in 3D is taken.

$$(-\beta_2 e_3 e_1 - \beta_3 e_1 e_2) C(\beta_2 e_3 e_1 + \beta_3 e_1 e_2) = -C_1 e_2 e_3 + (C_2 \cos 2\vartheta + C_3 \sin 2\vartheta) e_3 e_1 + (C_2 \sin 2\vartheta - C_3 \cos 2\vartheta) e_1 e_2$$
(3.4)

In addition to flipping the e_2e_3 component of C, (3.4) shows that $\beta_2e_3e_1 + \beta_3e_1e_2$ rotates $C_2e_3e_1 + C_3e_1e_2$ by $2\mathcal{P}$ around the axis of intersection of e_3e_1 and e_1e_2 , but in opposite direction compared to the case of G_3^+ - state of the first kind, $\alpha + \beta_1e_2e_3$.

Let's take G_3^+ - state written in arbitrary bivector basis $\{B_1, B_2, B_3\}$, $B_1B_2 = -B_3$, $B_1B_3 = B_2$, $B_2B_3 = -B_1$. The two above states then correspond to two sets of G_3^+ - states:

$$|0\rangle \leftrightarrow \{\forall (\alpha + \beta_1 B_1) : \alpha^2 + \beta_1^2 = 1\}$$
$$|1\rangle \leftrightarrow \{\forall (\beta_2 B_2 + \beta_3 B_3) : \beta_2^2 + \beta_3^2 = 1\}$$

If an arbitrary bivector is expanded in basis $\{B_1, B_2, B_3\}$, $C = C_1B_1 + C_2B_2 + C_3B_3$, then for G_3^+ - states from the classes of equivalence $|0\rangle$ or $|1\rangle$ we have, using (2.3) with $e_2e_3 \rightarrow B_1$, $e_3e_1 \rightarrow B_2$, $e_1e_2 \rightarrow B_3$,

$$(\alpha - \beta_1 B_1)C(\alpha + \beta_1 B_1) = C_1 B_1 + [C_2(\alpha^2 - \beta_1^2) - 2C_3\alpha\beta_1]B_2 + [C_3(\alpha^2 - \beta_1^2) + 2C_2\alpha\beta_1]B_3 = C_1 B_1 + (C_2\cos 2\varphi - C_3\sin 2\varphi)B_2 + (C_2\sin 2\varphi + C_3\cos 2\varphi)B_3$$


$$(-\beta_2 B_2 - \beta_3 B_3)C(\beta_2 B_2 + \beta_3 B_3) = -C_1 B_1 + [C_2(\beta_2^2 - \beta_3^2) + 2C_3 \beta_2 \beta_3]B_2 + [2C_2 \beta_2 \beta_3 - C_3(\beta_2^2 - \beta_3^2)]B_3 = -C_1 B_1 + (C_2 \cos 2\theta + C_3 \sin 2\theta)B_2 + (C_2 \sin 2\theta - C_3 \cos 2\theta)B_3$$

The bottom line is:

- When using any G_3^+ - state $\alpha + \beta_1 B_1, \alpha^2 + \beta_1^2 = 1$ from the equivalence class $|0\rangle$ to observe the result of transformed bivector $C = C_1 B_1 + C_2 B_2 + C_3 B_3$, the component C_1 remains unchanged, though C rotates around the axis orthogonal to B_1 by angle 2φ defined by $\alpha = \cos \varphi$ and $\beta_1 = \sin \varphi$; the C projection components onto B_2 and B_3 get changed as rotated by the same angle around the same axis.

- When using any G_3^+ - state $\beta_2 e_3 e_1 + \beta_3 e_1 e_2$, $\beta_2^2 + \beta_3^2 = 1$ from the equivalence class $|1\rangle$ to observe the result of transformed bivector $C = C_1 B_1 + C_2 B_2 + C_3 B_3$, the component C_1 flips, $C_1 \rightarrow -C_1$, though no rotation of C around axis orthogonal to B_1 is detected; the C projection components onto B_2 and B_3 get transformed as rotated by angle $2\mathcal{G}$ defined by $\beta_2 = \cos \vartheta$, $\beta_3 = \sin \vartheta$ around the axis orthogonal to B_1 but rotation direction is opposite to the first case of $|0\rangle$.

In the case of $|0\rangle$ rotation in B_1 plane "drags" rotations of two other bivector C projections. In the case of $|1\rangle$ B_2 and B_3 components rotate, while any vector in the B_1 component remains fixed.



The "dragging" phenomenon will be considered in the next subsection in the connection with Clifford translations and quantum mechanical state equivalence transformations $|\psi\rangle \rightarrow e^{i\theta} |\psi\rangle$.

3.3. Clifford translations in terms of G_3^+ - states

In quantum mechanics two state system wave functions are considered equivalent when related by $|\psi\rangle \rightarrow e^{i\theta} |\psi\rangle^7$. This is not true, as was shown in previous subsection, for G_3^+ - states which give more detailed information because are associated with explicitly defined "complex" planes in 3D.

Let's look at Clifford translations in terms of $\,G_{\!_3}^{\scriptscriptstyle +}$ - states of the class

$$|0\rangle \leftrightarrow \{\forall (\alpha + \beta_1 B_1): \alpha^2 + \beta_1^2 = 1\}$$

in dynamical situation when phase θ is changing in time.

⁷ This type of transformation is often called Clifford translations.

Clifford translations should accurately be written in 3D as $so(\alpha, \vec{\beta}) \rightarrow e^{I_s \theta} so(\alpha, \vec{\beta})$. Again, I will initially consider, to simplify calculations, the cases when unit bivector I_s lies in one of the coordinate planes: $I_s = e_2 e_3$, $I_s = e_3 e_1$ or $I_s = e_1 e_2$.

If $I_s = e_2 e_3$ then "velocity" of Clifford translation is:

$$\frac{d}{dt} \Big[e^{e_2 e_3 \theta} so(\alpha, \vec{\beta}) \Big] = \frac{d}{dt} \Big[\cos \theta + e_2 e_3 \sin \theta \Big] so(\alpha, \vec{\beta}) = \Big[(\sin \theta) e_2 e_3 e_2 e_3 + (\cos \theta) e_2 e_3 \Big] so(\alpha, \vec{\beta}) \theta' = e^{e_2 e_3 \theta} e_2 e_3 so(\alpha, \vec{\beta}) \theta'$$

This G_3^+ - state is orthogonal to the Clifford translation orbit $e^{e_2 e_3 \theta} so(\alpha, \vec{\beta})$ and spans one-dimensional vertical subspace of the Clifford orbit tangent space.

Two more G_3^+ - states, $e^{e_2 e_3 \theta} e_3 e_1 so(\alpha, \vec{\beta}) \theta'$, $e^{e_2 e_3 \theta} e_1 e_2 so(\alpha, \vec{\beta}) \theta'$, are orthogonal to $e^{e_2 e_3 \theta} so(\alpha, \vec{\beta})$, $e^{e_2 e_3 \theta} e_2 e_3 so(\alpha, \vec{\beta}) \theta'$ and to each other. They span two-dimensional horizontal subspace of the Clifford orbit tangent space.

Using other two planes for Clifford translations, $I_s = e_3 e_1$ and $I_s = e_1 e_2$, we get correspondingly vertical tangents $e^{e_3 e_1 \theta} e_3 e_1 so(\alpha, \vec{\beta})\theta'$ and $e^{e_1 e_2 \theta} e_1 e_2 so(\alpha, \vec{\beta})\theta'$, and couples of horizontal tangents

$$\{e^{e_3e_1\theta}e_2e_3so(\alpha,\vec{\beta})\theta', e^{e_3e_1\theta}e_1e_2so(\alpha,\vec{\beta})\theta'\}, \{e^{e_1e_2\theta}e_3e_1so(\alpha,\vec{\beta})\theta', e^{e_1e_2\theta}e_2e_3so(\alpha,\vec{\beta})\theta'\}.$$

Generalizing the above results to an arbitrary great circle plane spanned by unit bivector I_s of Clifford translation $so(\alpha, \vec{\beta}) \rightarrow e^{I_s \theta} so(\alpha, \vec{\beta})$, we have the following:

- the vertical tangent of the translation (speed along fiber) is $e^{I_s\theta}I_s so(\alpha, \vec{\beta})\theta'$
- two tangents, spanning the horizontal subspace of the tangent space, are $e^{I_S\theta}I_{S_1}so(\alpha, \vec{\beta})\theta'$ and $e^{I_S\theta}I_{S_2}so(\alpha, \vec{\beta})\theta'$, where S_1 and S_2 are two planes in 3D orthogonal to S and to each other.

1. Conclusions

- The two state wave functions $|\psi\rangle = (c_1, c_2)^T$, where the components c_1, c_2 of the column are "complex" numbers, are objects with lost information about actual physical states.
- Loosing of information happened due to formal using of "imaginary units" in pure algebraic way.

- "States" should really be elements $so(\alpha, \beta, S) \equiv \alpha + \beta I_s =$

 $\alpha + \beta (b_1 e_2 e_3 + b_2 e_3 e_1 + b_3 e_1 e_2), \ \alpha^2 + \beta^2 = 1, \ b_1^2 + b_2^2 + b_3^2 = 1, \text{ of even geometrical algebra } G_3^+, \text{ unambiguously representing rotations in 3D.}$

- Actual difference between "classical" and "quantum" mechanics is only shift of viewpoint: instead of dealing with equations describing an axially symmetric physical object orientation, as in classical mechanics, quantum mechanics deals with equations describing evolution in time of the operation, G_3^+ - state, which returns the physical object orientation.

Works Cited

- D. Hestenes, New Foundations of Classical Mechanics, Dordrecht/Boston/London: Kluwer Academic Publishers, 1999.
- [2] C. Doran and A. Lasenby, Geometric Algebra for Physicists, Cambridge: Cambridge University Press, 2010.
- [3] A. Soiguine, "A tossed coin as quantum mechanical object," September 2013. [Online]. Available: http://arxiv.org/abs/1309.5002.
- [4] A. Soiguine, Vector Algebra in Applied Problems, Leningrad: Naval Academy, 1990 (in Russian).
- [5] A. Soiguine, "Complex Conjugation Realtive to What?," in *Clifford Algebras with Numeric and Symbolic Computations*, Boston, Birkhauser, 1996, pp. 285-294.
- [6] J. v. Neumann, Mathematical Foundations of Quantum Mechanics, Princeton: Priceton University Press, 1955.