

Optimal Layout Synthesis for Quantum Circuits as Classical Planning

Irfansha Shaik
Department of Computer Science
Aarhus University
Aarhus, Denmark
Irfansha.Shaik@cs.au.dk

Jaco van de Pol
Department of Computer Science
Aarhus University
Aarhus, Denmark
Jaco@cs.au.dk

Abstract—In Layout Synthesis, the logical qubits of a quantum circuit are mapped to the physical qubits of a given quantum hardware platform, taking into account the connectivity of physical qubits. This involves inserting SWAP gates before an operation is applied on distant qubits. Optimal Layout Synthesis is crucial for practical Quantum Computing on current error-prone hardware: Minimizing the number of SWAP gates directly mitigates the error rates when running quantum circuits.

In recent years, several approaches have been proposed for minimizing the required SWAP insertions. The proposed exact approaches can only scale to a small number of qubits. Proving that a number of swap insertions is optimal is much harder than producing near optimal mappings.

In this paper, we provide two encodings for Optimal Layout Synthesis as a classical planning problem. We use optimal classical planners to synthesize the optimal layout for a standard set of benchmarks. Our results show the scalability of our approach compared to previous leading approaches. We can optimally map circuits with 9 qubits onto a 14 qubit platform, which could not be handled before by exact methods.

Index Terms—Layout Synthesis, Transpiling, Quantum Circuits, Classical Planning, SAT Planning, Optimal Planning

I. INTRODUCTION

Quantum algorithms can speed up certain computational problems. For example, Shor’s Algorithm [1] provides an exponential speed-up for factorisation, and Grover’s algorithm [2] provides a quadratic speed-up for database search. In recent years, quantum computing is envisaged as a way to solve hard problems [3] that are currently out of reach for classical computers. Formulating new algorithms to solve more problems faster on quantum computers, and enabling compilation of those algorithms on actual quantum hardware is of great interest.

In this paper, we focus on the latter part, especially mapping a quantum circuit to an arbitrary quantum architecture. Following [4], we distinguish logical synthesis and layout synthesis for quantum circuits. *Logical synthesis* constructs an (efficient) quantum circuit of quantum gates on a number of logical qubits. Following [5]–[7], arbitrary quantum circuits can be represented by a few simple gates. We assume that the resulting quantum circuit consists of any standard unary gates and binary Controlled-NOT (CNOT) gates. A CNOT gate acts on two qubits. If the control qubit is true, then the target qubit

is flipped. After logical synthesis, the gates and the order of their application to the logical qubits is fixed.

We focus on *Layout synthesis*, mapping the logical qubits onto the qubits of some physical hardware platform. High level algorithms assume that every pair of (logical) qubits is connected. However, in actual hardware platforms, often only a subset of (physical) qubit connections are realized. So one needs to compile the logical circuit to a physical hardware platform, such that every CNOT gate is applied only on neighboring qubits. It is not always possible to find a fixed mapping from logical qubits to physical qubits, such that every CNOT is applied on neighbors. In such cases, SWAP gates can be inserted, to swap the values of two connected qubits. A SWAP gate can be built from 3 CNOT gates. The goal of layout synthesis is to insert a minimal number of SWAP gates into the circuit, to move logical qubits to physical qubits, satisfying all neighbor constraints on subsequent CNOT gates.

State-of-the-Art and Related Work: Layout Synthesis has many names, for example, Transpilation, Compilation, Routing problem etc. An extensive overview and comparison of existing approaches is provided in [4], discussing both exact and heuristic approaches. Several heuristic approaches exist, for instance based on Dynamic Programming [8], A* search [9], and Temporal Planning [10]–[13]. Concrete tools include Qiskit’s SABRE [14] and Hardware-Aware (HA) [15]. While the state-of-the-art heuristic approaches are fast and scalable, it has been observed that the solutions are non-optimal [16]. In fact, [4] observed large optimality gaps, up to 1.5-12x and 5-45x on average on major quantum computing platforms.

For practical Quantum Computing on current NISQ machinery (noisy, intermediate scale quantum computers), the primary goal is to reduce the error rate. Since with each new gate the error rate increases, it is essential to minimize the number of additional SWAP gates in the Layout Synthesis. Therefore, in this paper we will focus on exact approaches.

Recently, several exact approaches have been proposed for optimal Layout Synthesis. An exact approach based on Dynamic Programming was proposed in [17], but it scales only to small circuits. Layout Synthesis was formulated as an SMT encoding in [16], where propositional constraints are given for satisfying connectivity and integer costs are assigned to additional swap gates. The authors report improved

optimal plans compared to heuristic approaches. They use an exponential number of variables to represent all permutations for the initial mapping. In a followup work [18], optimal subarchitectures are considered to reduce the number of permutations by mapping to a subset of physical qubits. In [19], the tool OLSQ is presented, based on an improved SMT encoding of permutations using a polynomial number of variables in the number of qubits. Those authors also allow optimizing error rates when individual error rates are given for qubits and gates. In [20], it is proposed to solve Layout Synthesis as a MAXSAT problem.

In theory, both SMT and MAXSAT approaches can prove lower bounds on the number of SWAP gates, thus guaranteeing optimality. However, optimal Layout Synthesis is an NP-complete problem [21]. In practice, most tools make some approximations. For instance, they limit the number of added swap gates, or they switch to heuristic search after some time limit. For example, the tool `satmap` by [20] only produces near optimal solutions, due to restriction on number of swap insertions. Even with these restrictions, all three approaches report improved optimality compared to heuristic approaches. However, the improved (near) optimality comes at the cost of time and memory. We aim at improving the performance, while preserving the optimality of the exact approaches.

Contribution: In this paper, we provide the first encoding of Optimal Layout Synthesis as a classical planning problem. The possible actions in this planning problem are: 1) to map a logical qubit to an initial physical qubit; 2) to apply a CNOT gate to the proper qubits; or 3) to insert an additional SWAP gate. In the latter case, we allow swapping logical qubits, as well as swapping a logical qubit with an extra ancillary qubit, since this can lead to even shorter plans. The conditions on the actions ensure that the solution satisfies all constraints. The shortest plan corresponds to a layout with the minimal number of SWAP gates. This enables the use of optimal planning tools to find the optimal layout.

In fact, we provide two encodings. The first one is based on *global levels* to resolve dependencies. Viewing these levels as discrete time stamps, this encoding is close to the temporal planning approach [10]–[13], but we use the simpler fragment of classical planning, and moreover our encoding is exact, while their approach minimizes makespan, but not necessarily the number of SWAP gates. Our second, more efficient but still exact encoding, avoids the explicit representation of time steps and is based on the relative order induced by *local dependencies* between CNOT gates.

We implemented both encodings in a translation tool in Python. It takes two inputs: a quantum circuit with unary and CNOT binary gates in the standard OPENQASM 2.0 format [6], and a directed graph, modeling the connectivity graph of a hardware architecture platform. We use Qiskit libraries [22] for parsing, printing and extracting layers from a given circuit. Initially, we ignore unary gates and compute the dependencies between the CNOT gates. The output of the translator is a planning problem represented in PDDL (Planning Domain Definition Language) [23]. This enables

to use off-the-shelf classical planners for computing optimal plans for these PDDL instances. The optimal plan is translated back to an OPENQASM circuit by re-inserting the unary gates.

We experimented with the planner Fast Downward [24] (with multiple backends [25], [26]) and with Madagascar [27], which is based on an encoding into SAT (propositional satisfiability). Other planners, like those based on QBF (Quantified Boolean Logic) [28] could be used as well. We report the performance of our two approaches on some standard benchmarks and compare them to a number of existing exact (QMAP [18], [29] and OLSQ [19]) and heuristic approaches (QISKIT’s SABRE [14]). As reported before, the heuristic approach SABRE is very fast, but often uses more SWAP gates than necessary. In all solved cases, we computed the correct minimal number of required SWAP gates. We show that the performance of our approaches is better than previous exact approaches. Moreover, our Local encoding performs much better than our Global encoding. The existing tool QMAP performed better than OLSQ in our experiments on a 5 qubit platform. On the other hand, OLSQ performed better than QMAP on a 14 qubit platform. Our Local approach is up to two orders faster than OLSQ and solves 8 unique instances that OLSQ could not solve in 3 hours. Our approach finds optimal mappings of 9-qubit circuits onto a 14-qubit platform, where previous exact tools, OLSQ and QMAP, could only map 5-qubit and 4 qubits circuits respectively on the same platform.

II. PRELIMINARIES

A. Layout Synthesis for Quantum Circuits

Layout Synthesis is mapping a logical circuit to some physical quantum computer architecture. Higher level algorithms make some assumptions, for example one-to-one connectivity is assumed among all qubits. However, physical architectures can have many restrictions, for example limited connectivity between qubits where binary gates can be applied. Particular qubits could also have different error rates and time durations. One takes into account such considerations when mapping to some architecture. In case no mapping exists such that the logical circuit can be mapped, SWAP gates can be added between neighbors to move the logical qubits to connected qubits. Note that using ancillary qubits can reduce the number of required SWAP gates. In this work, we focus on minimizing the number of SWAP gates and consider the use of planning for error rate optimization as future work .

We illustrate layout synthesis on an adder circuit, a standard example from [19]. The traditional circuit representation of the circuit is shown in Fig. 1. It contains 10 binary CNOT gates and 13 unary gates. Fig. 2 shows the adder circuit in OPENQASM format (with gate numbers as comments).

Figure 2 also provides a DAG representation with dependencies between gates, as computed by Qiskit [22]. The green nodes (inputs) are logical qubits, whereas the red nodes represent the (binary) CNOT gates, and the other nodes are unary gates. We use the gate numbers to represent the dependencies between gates in the DAG. There are 11 layers in total, if we do not count the top qubit layer (the inputs are not part of the

circuit). All gates in the same layer act on independent qubits, so they can be executed independently. We use this fact in Section III-A to handle dependencies between CNOT gates.

Figure 3 illustrates the IBM platform IBM-QX2 with 5 physical qubits. In general, the connections between qubits are directed, and our approach can handle directed coupling graphs. However, other exact tools can only handle symmetric connections, so for a fair comparison we only consider bidirectional platforms in this paper.

To map the adder circuit onto any platform, one needs 4 physical qubits connected as a square since it has CNOT gates on the qubit pairs $(q_0, q_1), (q_1, q_2), (q_2, q_3), (q_3, q_0)$. However, IBM-QX2 has no 4 qubits that are connected in the form of a square, thus SWAP gates are needed. We observe from our results in Table I that 1 SWAP insertion is sufficient. The circuit in Figure 5 shows the mapped circuit with 1 additional SWAP gate. First, the logical qubits q_0, q_1, q_2, q_3 of the circuit are mapped to physical qubits q_0, q_1, q_2, q_3 . For the mapped circuit, the gates g_{11}, g_{12} must be swapped in the original circuit and a SWAP gate is added in between them. Since g_{11}, g_{12} are in the same layer, they are independent, and this swap does not change the correctness. All gates after g_{11} and g_{12} must be mapped to the swapped physical qubits: Essentially, from this point on, q_2 and q_3 are interchanged.

The Melbourne platform (Fig. 4) contains a subset of 4 qubits that form a square. Consequently, the adder circuit does not require any additional SWAP gates when mapped on Melbourne. We can indeed find a mapping without any SWAP gates as shown in Table II.

B. Classical Planning

One of the main applications of Automated Planning [30] is scheduling. In Section III, we will model Layout Synthesis as a planning problem. Classical Planning is finding a valid sequence of deterministic actions from a single initial state to some goal state, where the initial state and the effect of all actions are completely known. The *Planning Domain Definition Language* (PDDL) [23] is a standard domain-specific language for classical planning problems used in International Planning Competitions (IPC). As shown in Listing 1: The domain file specifies types, predicates and actions. For predicates one can optionally specify types, as we will later see in the Section III. PDDL is an action-centered language; the actions essentially specify how the world changes by preconditions and effects. Action conditions and effects are represented similar to First-Order-Logic, using parameters to achieve compact descriptions. An example for an action is `map_initial`




Fig. 1. Adder circuit before mapping to IBM-QX2.

```

OPENQASM 2.0;
include "qelib1.inc";
qreg q[4];
x q[0]; //g1
x q[1]; //g2
h q[3]; //g3
cx q[2], q[3]; //g4
t q[0]; //g5
t q[1]; //g6
t q[2]; //g7
tdg q[3]; //g8
cx q[0], q[1]; //g9
cx q[2], q[3]; //g10
cx q[3], q[0]; //g11
cx q[1], q[2]; //g12
cx q[0], q[1]; //g13
cx q[2], q[3]; //g14
tdg q[0]; //g15
tdg q[1]; //g16
tdg q[2]; //g17
t q[3]; //g18
cx q[0], q[1]; //g19
cx q[2], q[3]; //g20
s q[3]; //g21
cx q[3], q[0]; //g22
h q[3]; //g23

```




Fig. 2. Adder circuit in OPENQASM format and in DAG format, showing the gate dependencies.

with parameters $?l$ and $?q$ in Section III-A. The problem file specifies objects, initial state and goal conditions as shown in Listing 2. Initial and Goal states are represented using a set of (negated) propositions.

Given a planning problem in PDDL format, one can use off-the-shelf planners such as Fast Downward, Madagascar, etc. A planning problem description can also assign costs to actions. In Planning competitions, planners are categorized based on how they handle these costs. Optimal Planners return only plans with optimal cost; Satisfying Planners, on the other hand, return some plan quickly, regardless of the cost. Nevertheless, given enough time, some satisfying planners such as Fast Downward Stone Soup (FDSS) [24] can optimize the cost to a large extent. Note that if cost is not specified, each action is considered to have cost 1.




Fig. 3. Coupling map for IBM-QX2 (Tenerife)




Fig. 4. Coupling map for IBM Melbourne




Fig. 5. Adder circuit after mapping to IBM-QX2, with 1 optimal swap insertion.

Listing 1. Domain file structure

```
(define (domain Quantum)
  (:requirements :typing)
  (:types ...)
  (:predicates ...)
  (:action ...))
```

Listing 2. Problem file structure

```
(define (problem example)
  (:domain Quantum)
  (:objects ...)
  (:init ...)
  (:goal (and ...)))
```

III. LAYOUT SYNTHESIS AS CLASSICAL PLANNING

In this section, we describe two encodings of layout synthesis as a classical planning problem. Both encodings include the following actions:

- `apply_cnot`, to apply the CNOT-gate of two logical qubits on two physical qubits.
- `swap`, to insert a SWAP-gate. We allow swapping:
 - two mapped logical qubits in the circuit
 - a mapped logical qubit with an ancillary qubit

Both encodings include the following predicates, to model the state after a partial plan:

- `mapped(?l, ?p)`, to keep track on which physical qubit a logical qubit is currently mapped.
- `rcnot(...)`, keeping track which CNOT gates are still required (all CNOT gates are still required in the initial state, none should be required in the goal state).

The planning problem defines the following constraints on valid plans:

- **Initial Mapping:** The initial mapping from logical to physical qubits must be bijective.
- **Valid Gate Dependencies:** Gates must be applied to the correct qubits in proper order.
- **Valid CNOT and SWAP gates:** All CNOT and SWAP gates are only applied on neighboring physical qubits.

As a consequence, since all CNOT gates must be applied anyway, the shortest valid plan will correspond to the correct layout, with the minimal number of SWAP gates inserted.

Since the hardware platform only constrains 2-qubit gate connectivity, layout synthesis can focus only on the CNOT gates and their dependencies. The unary gates can be reinserted later. Ignoring the unary gates, every CNOT gate has at most

two direct dependencies. We illustrate this again on the DAG of the adder-circuit of Fig. 2. There, g_4 depends on the input gates g_2 and g_3 ; gate g_{10} only depends on g_4 ; and gate g_{11} depends on the CNOT gates g_9 and g_{10} . In general, a CNOT gate could also depend on one input qubit and one CNOT gate, but this does not happen in the example of Fig. 2.

We parse the circuit and extract only CNOT gates with their dependencies. After finding a solution, we reconstruct the circuit including single qubit gates. We first encode the logical qubits as objects $\{l_0, \dots, l_{n-1}\}$ with type `lqubit`, whereas m physical qubits using objects as $\{p_0, \dots, p_{m-1}\}$ with type `pqubit`.

In our experiments, we do not explicitly specify cost, so each additional SWAP gate increases the cost by 1. Alternatively, one can specify cost for SWAP gates explicitly; for example a cost of 3, representing 3 underlying CNOT gates.

The first encoding (Section III-A) is based on *global levels*, corresponding to the layers with CNOT gates in the dependency graph. This encoding uses two extra actions: `map_initial`, mapping a logical qubit to a physical qubit in the first time slice, and action `move_depth`, to advance to the next time slice. The second, more efficient encoding (Section III-B), avoids the explicit representation of time steps and is based on the relative order of *local dependencies* between CNOT gates (and logical input qubits).

A. Global Level Based Model

1) *Domain Specification:* In this section, we specify the predicates and actions required for the domain specification. Recall that in a domain file, predicates and actions are defined separately. The set of the predicates describe the state of the world, whereas actions describe the change from one state to another.

Valid Initial Mapping: For modelling the first constraint i.e., mapping logical qubits to physical qubits, we define four predicates and one action. The predicate `mapped` specifies that the logical qubit `?l` is mapped to the physical qubit `?p`. The two auxiliary predicates `mapped_pq/mapped_lq` describe if a physical/logical qubit is already mapped, since one needs a bijective mapping. In our encodings, we also allow swapping with ancillary qubits. After swapping, one needs to keep track of the physical qubits that are already used i.e. either mapped with some logical qubit or used as an ancillary qubit. We use the predicate `used` to indicate if a physical qubit is either mapped or used as an ancillary qubit. The parameter

?p (?l) in these predicates is of type pqubit (lqubit). To obtain propositional instances, one substitutes all objects with corresponding types in the predicates. This process is called grounding. It translates the PDDL description to a (potentially very large) propositional problem.

We use the `map_initial` action to map a logical qubit to a physical qubit. One can apply the action only if both logical and physical qubits are not mapped. Additionally, the physical qubit must not be *used* as an ancillary qubit earlier. Once the action is applied, both the qubits are mapped and physical qubit is considered as *used*.

Listing 3. predicates and action for initial mapping

```
(mapped_pq ?p - pqubit)
(mapped_lq ?l - lqubit)
(mapped ?l - lqubit ?p - pqubit)
(used ?p - pqubit)

(:action map_initial
:parameters (?l - lqubit ?p - pqubit)
:precondition (and(not(mapped_lq ?l)
(not(used ?p)))
:effect (and(mapped_lq ?l)(mapped ?l ?p)
(mapped_pq ?p)(used ?p)))
```

Valid Gate Dependencies: To enforce gate dependencies in this model, we use the layers as generated by Qiskit. As long as gates are executed layer by layer, their dependencies will be respected. When modelling layout synthesis as planning, we only consider the layers with CNOT gates. To simulate layers in our first planning model, we introduce objects of type `depth`, representing discrete depths, i.e., one object for each layer that contains a CNOT gate. We also add an initial depth level, to force the initial mapping before SWAP and CNOT gate execution.

Recall the DAG of the adder example in Section II-A, Figure 2. In this example, only the layers at depths $d_2, d_3, d_4, d_5, d_6, d_8, d_{10}$ contain CNOT gates. Additionally, we add the start depth d_0 . So for our adder example, the layer objects of type `depth` are defined as $\{d_0, d_2, d_3, d_4, d_5, d_6, d_8, d_{10}\}$.

To ensure the circuit is executed layer by layer, we maintain two predicates `current_depth` to specify the current layer, and `next_depth` to relate the current and the next layer. We use the action `move_depth` to move from one layer to another layer when executing a plan. Every valid plan has exactly k `move_depth` actions, where k is the number of layers in the DAG with at least one CNOT gate. Alternatively, instead of grouping based on independent gates, one could simply place each instruction in a single layer as in the OPENQASM input order. This would increase the number of layers required in such modelling, but the number of additional SWAP gates required does not change. Decreasing the number of layers, and consequently the number of actions in a valid plan, has a positive effect on the solving time.

Listing 4. predicates and action for valid gate dependencies

```
(current_depth ?d - depth)
(next_depth ?d1 - depth ?d2 - depth)
```

```
(:action move_depth
:parameters (?d1 - depth ?d2 - depth)
:precondition (and(current_depth ?d1)
(next_depth ?d1 ?d2))
:effect (and(not(current_depth ?d1)
(current_depth ?d2)))
```

Valid CNOT and SWAP gates: For the final constraint, we need to specify when a CNOT and SWAP gate can be applied. To model that a CNOT gate must be applied on specific qubits and at a certain depth, we use the predicate `rcnot` (required-cnot) in Listing 5. Predicate (`rcnot ?l1 - lqubit ?l2 - lqubit ?d - depth`) indicates that a CNOT gate must still be applied between two logical qubits $?l1, ?l2$ at the layer with depth $?d$. Note that the $?l1, ?l2, ?d$ are parameters and can be substituted with objects with corresponding types to generate (grounded) propositions.

To apply a CNOT gate, the corresponding logical qubits must be mapped to some physical qubits. The physical qubits must be connected, which is represented using the `connected` predicate. The action `apply_cnot` ensures that all the above conditions are satisfied when a required CNOT is applied. The effect of this action removes one required CNOT operation (`rcnot`).

Finally, we model the action `swap` to allow swapping of logical qubits when required. We allow two types of swaps:

- Swapping two mapped logical qubits.
- Swapping a mapped logical qubit with an ancillary qubit.

Note that PDDL allows two actions with the same name. Since both actions swap qubits, we call both actions ‘swap’ for consistency. However, the parameters and conditions of both types of swap actions are different. In the first case, similar to a CNOT gate both logical qubits must be mapped to connected physical qubits. The effect will update the mapping from logical to physical qubits. In the second case, first logical qubit $?l1$ must be mapped to a physical qubit $?p1$, which should be connected to an ancillary physical qubit $?p2$. Once swapped, the logical qubit $?l1$ is now mapped to $?p2$ and the physical qubit $?p1$ becomes ancillary. Since we do not allow initial mapping of logical qubits on ancillary qubits, we mark $?p2$ as *used*.

Listing 5. predicates and action for valid CNOT gates

```
(rcnot ?l1 - lqubit ?l2 - lqubit ?d - depth)
(connected ?p1 - pqubit ?p2 - pqubit)
```

```
(:action apply_cnot
:parameters (?l1 - lqubit ?l2 - lqubit
?p1 - pqubit ?p2 - pqubit ?d - depth)
:precondition (and(mapped ?l1 ?p1)
(mapped ?l2 ?p2)(connected ?p1 ?p2)
(rcnot ?l1 ?l2 ?d)(current_depth ?d))
:effect (and(not(rcnot ?l1 ?l2 ?d))))
```

```
; ; normal swap
```

```
(:action swap
:parameters (?l1 - lqubit ?l2 - lqubit
?p1 - pqubit ?p2 - pqubit ?d - depth)
:precondition (and(mapped ?l1 ?p1)
```

```

(mapped ?i2 ?p2)(connected ?p1 ?p2)
(current_depth ?d))
:effect (and(not(mapped ?i1 ?p1))
(not(mapped ?i2 ?p2))(mapped ?i1 ?p2)
(mapped ?i2 ?p1)))
;; ancillary swap
(:action swap
:parameters (?i1 - lqubit
?p1 - pqubit ?p2 - pqubit ?d - depth)
:precondition (and(mapped ?i1 ?p1)
(not(mapped_pq ?p2))(connected ?p1 ?p2)
(current_depth ?d))
:effect (and(not(mapped ?i1 ?p1))
(mapped ?i1 ?p2)(not(mapped_pq ?p1))
(mapped_pq ?p2)(used ?p2)))

```

2) *Problem Specification*: In the problem file, we need to specify the initial and goal states of the planning problem. For layout synthesis, the initial depth is d_0 . We specify the coupling map of the architecture using `connected` predicates. For CNOT mapping, we specify all the required CNOT gates at specific depths. Finally, the `next_depth` predicate is specified with ordering of layers. Note that the initial state specification is complete, i.e., all the propositions not specified are negated. In case of the goal specification, one only needs to specify the propositions that must be achieved. Propositions that are not specified are open, resulting in more than one goal state. In our model, we specify that all logical qubits are mapped and all required CNOT gates are performed (i.e., each `rcnot` is negated). Listings 6,7 present snippets of initial and goal specification of our adder example.

Listing 6. Adder initial state snippets

```

(:init
(current_depth d0)
(connected p1 p0)
...
(next_depth d0 d2)
...
(rcnot 12 13 d2)
...
)

```

Listing 7. Adder goal state snippets

```

(:goal
(and
(mapped_lq 10)
...
(mapped_lq 13)
(not (rcnot 12 13 d2))
...
(not (rcnot 13 10 d10))))
)

```

B. Local Dependency Based Model

In the Global model, using extra actions for moving to the next depth results in almost doubling the plan length in the worst case. At least, the plan length increases by the number of layers in the circuit with CNOT gates. Additionally, we need initial mapping actions for mapping logical qubits to physical qubits. This further increases the plan length. It is well known that increased plan length can result in increased solving

time. Moreover, since immediate dependencies of CNOT gates are not modelled directly, the early pruning of wrong partial solutions might not work properly.

To overcome these problems, we make two improvements to our Global encoding. First we drop the layers and model local dependencies directly when applying CNOT gates. Second, we integrate the initial mapping into the corresponding CNOT gates. Both these steps are easier when the CNOT actions are partially grounded with logical qubit parameters. We now describe these improvements in detail.

1) *Avoiding Layers*: In all our actions and predicates, we drop the depth parameters, and we drop the action `next_depth`. A CNOT gate C_1 can at most depend on two CNOT gates C_2, C_3 that act on at least one of the same qubits. As long as C_2, C_3 are executed before C_1 , we preserve the correctness. For example, consider the gate g_{11} in the adder circuit example in Figure 2. It depends on g_9, g_{10} , so those two CNOT gates must be performed before g_{11} .

To model local dependencies, we introduce new constants with type `gateid`, one for each CNOT gate. For example, we use constant g_{11} in `(rcnot g11)` to represent the CNOT gate corresponding to gate g_{11} . To generate locally dependent CNOT actions, we ground the parameters $?i1, ?i2, ?d$ in the `apply_cnot` action. Here each valid grounded action corresponds to one CNOT gate in the circuit. For each valid action, we extend the action name `apply_cnot` with its corresponding `gateid`. For example, the partially grounded action with logical qubits $l3, l0$ at depth d_{11} is `apply_cnot_g11`. The preconditions additionally specify that the dependent CNOT gates are already applied (i.e., not required). For CNOT gate g_{11} in the adder circuit we obtain the following action specification:

Listing 8. An example partially grounded CNOT action in adder circuit

```

(:action apply_cnot_g11
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(rcnot g9))
(not(rcnot g10))(rcnot g11)
(mapped 13 ?p1)(mapped 10 ?p2)
(connected ?p1 ?p2))
:effect (and(not(rcnot g11))))
)

```

2) *Improving Initial Mapping*: As the actions are already partially grounded, for each action the dependencies are known at compile time. Not all CNOT gates have two CNOT dependencies, for example gate g_4 in Figure 2 depends directly on (logical) input qubits. To avoid explicit initial mapping actions, we integrate the mapping of these input qubits into the CNOT action. Instead of checking if the corresponding physical qubit is already mapped, we check if it is not used. In that case, we immediately map the logical qubit to this physical qubit. We do no longer require the mapped-predicate on logical qubits. For example, the action applying the CNOT gate g_4 is:

Listing 9. CNOT gate with integrated initial mapping

```

(:action apply_cnot_g4
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(used ?p1))
(not(used ?p2))
)
)

```

```

    (rcnot g4)(connected ?p1 ?p2))
:effect (and(not(rcnot g4))
    (mapped 12 ?p1)(mapped_pq ?p1)(used ?p1)
    (mapped 13 ?p2)(mapped_pq ?p2)(used ?p2)))

```

A similar integration is also applied to CNOT gates which depend only on one other CNOT gate. We provide the full specification for the Adder example in Appendix A.

IV. EXPERIMENTAL EVALUATION

A. Experiment Design

We have implemented the translation of quantum circuits into PDDL instances in our tool Q-Synth (Quantum Synthesizer). For an experimental evaluation, we consider a standard set of benchmark circuits from [19] and we map them onto IBM platforms Tenerife (5 qubits) and Melbourne (14 qubits). For the first experiment, we use platform Tenerife (also called IBM-X2). We consider those 6 out of 13 circuits that use no more physical qubits than the 5 qubits available in Tenerife. For this experiment, we give a 300 seconds time limit and a 16-GB memory limit. In case of the second experiment with platform Melbourne, we use all 13 circuits. We give a 3-hour time limit and a 48-GB memory limit for all 13 instances. In both cases, we measure and report the CPU time taken by the whole tool chain (including parsing, encoding, solving, and extracting and validating the plans). Only the CPU time is reported, to avoid measuring disk I/O overhead in our cluster.

Q-synth requires a planning tool to solve the generated PDDL instances. We consider the Fast Downward planner (FD) with two planner configurations, the Big Joint Optimal Landmarks Planner (BJOLP) [25] and Merge-and-Shrink (MS) [26], and the SAT based planner Madagascar (M) [27]. For both experiments, we apply FD+BJOLP on the Global models (column G-bj). For the Local encoding, we report results from all three planners FD with BJOLP (L-bj), FD with MS (L-ms), and Madagascar (L-M). Note that Madagascar is a satisfying planner. We increment the plan length by 1 until we find a plan. This ensures optimality of the plans generated by Madagascar.

We compare our results with three existing tools. First with Qiskit’s heuristic approach SABRE [14]. We use the first 100 seeds for the SABRE Layout and take the minimum number of swaps produced by any seed. In every instance, the approach with 100 runs takes approximately 2 minutes.

Then we compare with two leading exact approaches QMAP [18], [29] and OLSQ [19]. Although there are heuristic versions of both tools, we only consider the exact versions of them. We use the latest version OLSQ 0.0.4.1 installed using pip. Note that OLSQ only uses bidirectional coupling graphs, so for sake of uniformity we change the coupling maps of Tenerife and Melbourne for all experiments. For QMAP, we use the latest version `mqt.qmap 2.1.3`. By default, it uses subset optimization (QMAP-S) as in [29]. However, QMAP-S was shown to be sub-optimal for certain architectures [18]. Essentially, QMAP-S maps a given circuit with k logical qubits to a subset of k physical qubits. Instead, QMAP-SA uses optimal subarchitectures that also allow ancillary qubits, thus allowing ancillary swaps. We compare Q-Synth with the exact

approaches QMAP (without subarchitectures) and QMAP-SA (with optimal subarchitectures) as described in [18]. We also experiment with QMAP-S on the Melbourne platform, but for a fair comparison, in this case we also disabled ancillary swaps in Q-Synth. We report results with planner FD+BJOLP (L-bj-no-anc).

B. Validation

Validating if our mapped circuits are optimal and correct is non-trivial. We use the following four measures to ensure correctness and optimality.

- When a circuit is mapped, we try to recover the original circuit by reversing the swaps and using the reverse initial mapping. The resultant circuit must be exactly the same as the original circuit, which we compare using Qiskit.
- We check if all the 2-qubit gates are applied on the connected qubits. One could alternatively use the checkmap function from qiskit.
- We compare the equivalence of the mapped circuit with the original circuit with at least 1 million simulations in Qiskit.
- Finally, for optimality we cross compare with the results obtained from other exact tools.

Note that with SAT based planners, one could extract certificates when refuting an instance. This provides provable lower bounds on the number of swaps.

C. Results

In Table I (on platform Tenerife), both our models with all planner configurations, and both existing tools QMAP and OLSQ, solve all the instances. Overall, for the benchmarks on this small platform, Q-Synth is slightly faster than QMAP, and OLSQ is considerably slower, especially on the larger instances. All exact approaches compute the minimum number of swaps required for `mod5mils_65` as 2. On the other hand, SABRE returns 3 swap insertions, which is non-optimal.

Table II presents the results on platform Melbourne with 14 qubits. Our Q-Synth with Local models performs much better than with Global models. Q-Synth with planner FD with MS (L-ms) solves most instances: 11 out of 13 within the time and memory limits; with BJOLP (L-bj), it solves 10 out of 13 instances; with Madagascar it solves 8 out of 13 instances (L-M); surprisingly it timeouts on one 5-qubit instance. Even our Global encoding with FD+BJOLP (G-bj) solves 4 out of 13 instances, which is more than previous exact methods. Other planning tools on our Global models did not perform that well (timings are not reported here). Of the previous exact approaches, OLSQ solves only 3 out of 13 instances in total, while QMAP-SA solves 2 out of 13. Q-Synth is 2 orders of magnitude faster than OLSQ on the `or` instance. On the other hand, QMAP (without subarchitectures) runs out of memory for all instances. In case of solving without ancillary qubits, QMAP-S solves 7 instances, including a 7-qubit instance. On the other hand, L-bj-no-anc solves 11 instances and performs better than our models with ancillary swaps.

We don't know the minimal number of SWAP gates required for the largest benchmarks, since none of the exact tools could solve them. On the other hand, with SABRE we could compute an upper bound on this number. One might also find such plans by using QMAP and OLSQ in satisfying mode, or running the planning tools on our encoding in satisfying mode, but this has not been the focus of the research reported here. Note that in 5 instances, one can observe that SABRE gives non-optimal swap insertions. For example, for the instance `4gt13_92`, SABRE gives 3 additional swaps, which can be implemented by 9 additional CNOT gates. Within 17 minutes, our approach L-ms computed the minimum number of swaps needed, which then also provides a guaranteed lower bound. This clearly shows the feasibility of classical planning for exact optimal layout synthesis of quantum circuits.

V. COMPARISON WITH RELATED WORK

Comparison to QMAP and OLSQ

Our tool Q-Synth with the Local model outperforms QMAP significantly: we solve 9 instances uniquely. The difference is clear when the number of qubits is more than 4: all the instances timed out for QMAP after 3 hours. Note that we solve all three 9-qubit instances (two even within 5 minutes). QMAP uses an exponential number of variables in the number of qubits to represent the permutations. We conjecture that is the reason for poor performance on the 14 qubit platform. Even with subarchitecture optimization, scaling to 14 qubit platform seems difficult, and we expect the same challenge for even larger platforms. A similar bottleneck for QMAP is reported in [20] with platform Tokyo (20 qubits). Furthermore, the number of swap insertions in QMAP depends on the order of the input quantum circuit, which can result in suboptimal solutions. For example, QMAP and QMAP-SA give 2 additional swaps for the `adder` instance, instead of 1 optimal swap (* in Table I).

Even our Global encoding outperforms QMAP and solves two 5 qubit instances. Since the number of layers increases the plan length, the difficulty of the problem increases as confirmed by the results. This shows the strength of planning based approaches, and the effect of modelling the problem (Global vs Local) on performance.

OLSQ (run in exact mode for optimal solutions) scales poorly with the number of qubits and CNOT gates compared to Q-Synth. Between OLSQ and QMAP-SA, QMAP-SA performs better on a 5-qubit platform whereas OLSQ performs better on a 14-qubit platform. These results are consistent with the exponential dependency of QMAP on the target platform. Note that other approaches could also benefit from the optimal subarchitectures computed by QMAP-SA. Further, when optimizing for the number of swaps, the solutions from OLSQ are not necessarily optimal. After some time limit, OLSQ searches for solutions with larger makespan, which can result in suboptimal solutions. In our experiments, the swap counts generated by both tools are optimal.

Both tools and also `satmap` by [20] provide heuristic approaches that produce near optimal solutions and scale much better. In this paper, we focus only on exact approaches

where the solutions are truly optimal in the count of swap insertions. Proving that there exists no other mapping with less SWAP gates is a much harder problem. One could easily use satisfying planners for finding near optimal solutions using our approach on even larger circuits. Given enough time, the near optimal solutions are on par with other tools in terms of swap insertions.

Without Ancillary Qubits: QMAP-S performs significantly better than QMAP-SA, consistent with the theoretical considerations in [18]. For example, consider the instance `qaoa5`, QMAP-S tries to map onto a 5-qubit subset of the physical qubits, while QMAP-SA tries to map onto a 7-qubit subset, i.e., it allows 2 additional ancillary qubits. Further, QMAP-S imposes a restriction on the number of swaps in front of each gate. In case of `qaoa5`, the swap limit is 3, which significantly reduces the solving time. However, it is not clear to us if this technique preserves the optimality. Note that, for the same instance, the swap limit with QMAP-SA is 7. We observed that QMAP-S returns 11 additional swaps for the instance `4gt13_92` (* in Table II), instead of 10 swaps as reported by Q-Synth. OLSQ in heuristic mode (OLSQ-TB) also gives 10 additional swaps for the same instance, confirming an upper bound of 10 swaps. Our approach without ancillary swaps still reports the correct minimal swap insertions in all instances. However, [18] provides an example where ancillary swaps are essential to obtain an optimal solution.

Comparison to Temporal Planning

[10] proposed to use temporal planners for Layout Synthesis on QAOA problems. In Section 4 of [10], classical planning is mentioned as a potential alternative for Temporal planning. However, they use time steps for gates to avoid dependencies, similar to our Global level-based encoding, but without grouping the CNOT gates in layers. This can almost double the plan lengths, and it blurs the look-ahead information due to lack of dependencies. In their paper, poor preliminary results were reported with the SAT based planner Madagascar (M/Mp) with parallel plans, which is consistent with our observations. Another key issue with using Temporal planning is the lack of optimality: one can only obtain plans optimal in makespan. This issue is similar to parallel plans in classical planning: the number of swaps added need not be optimal and can be worse in practice.

In [13], layout synthesis for the QAOA algorithm for graph coloring is split into two stages: Qubit Initialisation (QI) and Routing. Classical planning is considered for QI, where it is only used for initializing logical qubits on physical qubits. The addition of SWAP gates and generating actual plans is still handled by temporal planners. Compared to random initial allocation, using the classical planner FastDownward, improved the makespan in many instances.

From our experiments, we conclude that classical planning provides a strong alternative to temporal planning to solve the full Layout synthesis problem. Moreover, the model using Local dependencies is superior to the one using Global levels.

Circuit	Our tool Q-Synth (exact)			Previous Exact Tools			SABRE				
	q	c	+s	G-bj	L-ms	L-bj	L-M	QMAP	QMAP-SA	OLSQ	+s
or	3	6	0	2.4	2.6	2.2	2.2	4.0	3.9	6.7	0
adder	4	10	1	2.5	3.0	2.6	2.4	3.9*	4.1*	40.3	1
qaoa5	5	8	0	2.6	3.2	2.4	2.1	4.0	3.9	12.6	0
4mod5-v1_22	5	11	1	2.9	3.2	2.4	2.2	4.0	3.9	24.2	1
mod5mils_65	5	16	2	3.5	3.7	2.6	3.1	4.0	4.0	107	3
4gt13_92	5	30	0	3.8	5.5	3.0	2.8	4.1	4.4	136	0

TABLE I

PLATFORM TENERIFE OR IBM-QX2 (5 QUBITS), Q: NUMBER OF LOGICAL QUBITS, C: NUMBER OF CNOT GATES IN ORIGINAL CIRCUIT, +S: NUMBER OF SWAPS ADDED AFTER MAPPING. WE SPECIFY THE TIME TAKEN BY ALL EXACT TOOLS IN SECONDS.

Circuit	Our tool Q-Synth (exact)			Previous Exact Tools			Without ancillary qubits		SABRE				
	q	c	+s	G-bj	L-ms	L-bj	L-M	QMAP	QMAP-SA	OLSQ	L-bj-no-anc	QMAP-S	+s
or	3	6	2	3.7	7.8	2.8	2.6	MO	5.5	517	4.9	2.8	2
adder	4	10	0	4.6	17.2	2.6	2.4	MO	6.5	30.5	4.4	2.4	0
qaoa5	5	8	0	3.8	32.9	2.6	2.1	MO	TO	39.5	4.3	2.6	0
4mod5-v1_22	5	11	3	1047	34.3	3.8	3.6	MO	TO	TO	4.6	10.1	4
mod5mils_65	5	16	6	TO	49.1	18.5	8.0	MO	TO	TO	4.8	18.6	6
4gt13_92	5	30	10	TO	973	4275	TO	MO	TO	TO	11.6	183*	13
tof_4	7	22	1	TO	161	3.2	7.3	MO	TO	TO	5.1	6734	1
barenco_tof_4	7	34	5	TO	238	40.5	94.2	MO	TO	TO	8.5	TO	6
tof_5	9	30	1	TO	440	3.2	601	MO	MO	TO	4.9	TO	1
mod_mult_55	9	40	7	TO	10258	TO	TO	MO	MO	TO	767	TO	8
barenco_tof_5	9	50	6	TO	730	247	TO	MO	MO	TO	22.9	TO	7
vbe_adder_3	10	50	-	TO	TO	TO	TO	MO	MO	TO	TO	TO	8
rc_adder_6	14	71	-	TO	TO	TO	TO	MO	MO	TO	TO	MO	12
Total number of instances solved:	4	11	10	8	0	2	3	11	7	13			

TABLE II

PLATFORM MELBOURNE (14 QUBITS), Q: NUMBER OF LOGICAL QUBITS, C: NUMBER OF CNOT GATES IN ORIGINAL CIRCUIT, +S: NUMBER OF SWAPS ADDED AFTER MAPPING. WE SPECIFY THE TIME TAKEN BY ALL EXACT TOOLS IN SECONDS.

REFERENCES

- [1] P. W. Shor, "Algorithms for quantum computation: Discrete logarithms and factoring," in *35th Annual Symposium on Foundations of Computer Science, Santa Fe, New Mexico, USA, 20-22 November 1994*. IEEE Computer Society, 1994, pp. 124–134. [Online]. Available: <https://doi.org/10.1109/SFCS.1994.365700>
- [2] L. K. Grover, "A fast quantum mechanical algorithm for database search," in *Proceedings of the Twenty-Eighth Annual ACM Symposium on the Theory of Computing, Philadelphia, Pennsylvania, USA, May 22-24, 1996*, G. L. Miller, Ed. ACM, 1996, pp. 212–219. [Online]. Available: <https://doi.org/10.1145/237814.237866>
- [3] F. Arute, K. Arya, R. Babbush, D. Bacon, J. C. Bardin, R. Barends, R. Biswas, S. Boixo, F. G. Brandao, D. A. Buell *et al.*, "Quantum supremacy using a programmable superconducting processor," *Nature*, vol. 574, no. 7779, pp. 505–510, 2019.
- [4] B. Tan and J. Cong, "Optimality study of existing quantum computing layout synthesis tools," *IEEE Trans. Computers*, vol. 70, no. 9, pp. 1363–1373, 2021. [Online]. Available: <https://doi.org/10.1109/TC.2020.3009140>
- [5] M. Amy, D. Maslov, M. Mosca, and M. Roetteler, "A meet-in-the-middle algorithm for fast synthesis of depth-optimal quantum circuits," *IEEE Trans. Comput. Aided Des. Integr. Circuits Syst.*, vol. 32, no. 6, pp. 818–830, 2013. [Online]. Available: <https://doi.org/10.1109/TCAD.2013.2244643>
- [6] A. W. Cross, L. S. Bishop, J. A. Smolin, and J. M. Gambetta, "Open quantum assembly language," 2017.
- [7] D. M. Miller, R. Wille, and Z. Sasanian, "Elementary quantum gate realizations for multiple-control toffoli gates," in *2011 41st IEEE International Symposium on Multiple-Valued Logic*, 2011, pp. 288–293.
- [8] M. Y. Siraichi, V. F. dos Santos, C. Collange, and F. M. Q. Pereira, "Qubit allocation," in *Proceedings of the 2018 International Symposium on Code Generation and Optimization, CGO 2018, Vösendorf / Vienna, Austria, February 24-28, 2018*, J. Knoop, M. Schordan, T. Johnson, and M. F. P. O'Boyle, Eds. ACM, 2018, pp. 113–125. [Online]. Available: <https://doi.org/10.1145/3168822>
- [9] A. Zulehner, A. Paler, and R. Wille, "An efficient methodology for mapping quantum circuits to the IBM QX architectures," *IEEE Trans. Comput. Aided Des. Integr. Circuits Syst.*, vol. 38, no. 7, pp. 1226–1236, 2019. [Online]. Available: <https://doi.org/10.1109/TCAD.2018.2846658>
- [10] D. Venturelli, M. Do, E. G. Rieffel, and J. Frank, "Temporal planning for compilation of quantum approximate optimization circuits," in *Proceedings of the Twenty-Sixth International Joint Conference on Artificial Intelligence, IJCAI 2017, Melbourne, Australia, August 19-25, 2017*, C. Sierra, Ed. ijcai.org, 2017, pp. 4440–4446. [Online]. Available: <https://doi.org/10.24963/ijcai.2017/620>
- [11] K. E. C. Booth, M. Do, J. C. Beck, E. G. Rieffel, D. Venturelli, and J. Frank, "Comparing and integrating constraint programming and temporal planning for quantum circuit compilation," in *Proceedings of the Twenty-Eighth International Conference on Automated Planning and Scheduling, ICAPS 2018, Delft, The Netherlands, June 24-29, 2018*. AAAI Press, 2018, pp. 366–374. [Online]. Available: <https://aaai.org/ocs/index.php/ICAPS/ICAPS18/paper/view/17787>
- [12] D. Venturelli, M. Do, B. O'Gorman, J. Frank, E. Rieffel, K. Booth, T. Nguyen, P. Narayan, and S. Nanda, "Quantum circuit compilation: An emerging application for automated reasoning," in *Proceedings of the 12th International Scheduling and Planning Applications Workshop (SPARK 2019)*, 2019, pp. 95–103.
- [13] M. Do, Z. Wang, B. O'Gorman, D. Venturelli, E. G. Rieffel, and J. Frank, "Planning for compilation of a quantum algorithm for graph coloring," in *ECAI 2020 - 24th European Conference on Artificial Intelligence, 29 August-8 September 2020, Santiago de Compostela, Spain, August 29 - September 8, 2020 - Including 10th Conference on Prestigious Applications of Artificial Intelligence (PAIS 2020)*, ser. Frontiers in Artificial Intelligence and Applications, vol. 325. IOS Press, 2020, pp. 2338–2345. [Online]. Available: <https://doi.org/10.3233/FAIA200363>
- [14] G. Li, Y. Ding, and Y. Xie, "Tackling the qubit mapping problem for nisq-era quantum devices," in *Proceedings of the Twenty-Fourth International Conference on Architectural Support for Programming Languages and Operating Systems, ASPLOS 2019, Providence, RI, USA, April 13-17, 2019*, I. Bahar, M. Herlihy, E. Witchel, and A. R. Lebeck, Eds. ACM, 2019, pp. 1001–1014. [Online]. Available: <https://doi.org/10.1145/3297858.3304023>
- [15] S. Niu, A. Suau, G. Staffelbach, and A. Todri-Sanial, "A hardware-

- aware heuristic for the qubit mapping problem in the nisq era,” *IEEE Transactions on Quantum Engineering*, vol. 1, pp. 1–14, 2020.
- [16] R. Wille, L. Burgholzer, and A. Zulehner, “Mapping quantum circuits to IBM QX architectures using the minimal number of SWAP and H operations,” in *Proceedings of the 56th Annual Design Automation Conference 2019, DAC 2019, Las Vegas, NV, USA, June 02-06, 2019*. ACM, 2019, p. 142. [Online]. Available: <https://doi.org/10.1145/3316781.3317859>
- [17] T. Itoko, R. Raymond, T. Imamichi, A. Matsuo, and A. W. Cross, “Quantum circuit compilers using gate commutation rules,” in *Proceedings of the 24th Asia and South Pacific Design Automation Conference, ASPDAC 2019, Tokyo, Japan, January 21-24, 2019*. ACM, 2019, pp. 191–196. [Online]. Available: <https://doi.org/10.1145/3287624.3287701>
- [18] T. Peham, L. Burgholzer, and R. Wille, “On optimal subarchitectures for quantum circuit mapping,” *CoRR*, vol. abs/2210.09321, 2022. [Online]. Available: <https://doi.org/10.48550/arXiv.2210.09321>
- [19] B. Tan and J. Cong, “Optimal layout synthesis for quantum computing,” in *IEEE/ACM International Conference On Computer Aided Design, ICCAD 2020, San Diego, CA, USA, November 2-5, 2020*. IEEE, 2020, pp. 137:1–137:9. [Online]. Available: <https://doi.org/10.1145/3400302.3415620>
- [20] A. Molavi, A. Xu, M. Diges, L. Pick, S. S. Tannu, and A. Albarghouthi, “Qubit mapping and routing via maxsat,” in *55th IEEE/ACM International Symposium on Microarchitecture, MICRO 2022, Chicago, IL, USA, October 1-5, 2022*. IEEE, 2022, pp. 1078–1091. [Online]. Available: <https://doi.org/10.1109/MICRO56248.2022.00077>
- [21] A. Botea, A. Kishimoto, and R. Marinescu, “On the complexity of quantum circuit compilation,” in *Proceedings of the Eleventh International Symposium on Combinatorial Search, SOCS 2018, Stockholm, Sweden - 14-15 July 2018*, V. Bulitko and S. Storandt, Eds. AAAI Press, 2018, pp. 138–142. [Online]. Available: <https://aaai.org/ocs/index.php/SOCS/SOCS18/paper/view/17959>
- [22] Qiskit contributors, “Qiskit: An open-source framework for quantum computing,” 2023.
- [23] D. V. McDermott, “The 1998 AI planning systems competition,” *AI Mag.*, vol. 21, no. 2, pp. 35–55, 2000. [Online]. Available: <https://doi.org/10.1609/aimag.v21i2.1506>
- [24] M. Helmert, G. Röger, and E. Karpas, “Fast downward stone soup: A baseline for building planner portfolios,” in *ICAPS 2011 Workshop on Planning and Learning*, vol. 2835, 2011.
- [25] C. Domshlak, M. Helmert, E. Karpas, E. Keyder, S. Richter, G. Röger, J. Seipp, and M. Westphal, “Bjolv: The big joint optimal landmarks planner,” 2011.
- [26] S. Sievers, “Fast downward merge-and-shrink,” *IPC-9 planner abstracts*, pp. 85–90, 2018.
- [27] J. Rintanen, “Madagascar: Scalable planning with SAT,” in *8th International Planning Competition*, 2014. [Online]. Available: <https://research.ics.aalto.fi/software/sat/madagascar/>
- [28] I. Shaik and J. van de Pol, “Classical planning as QBF without grounding,” in *ICAPS*. AAAI Press, 2022, pp. 329–337.
- [29] L. Burgholzer, S. Schneider, and R. Wille, “Limiting the search base in optimal quantum circuit mapping,” in *27th Asia and South Pacific Design Automation Conference, ASP-DAC 2022, Taipei, Taiwan, January 17-20, 2022*. IEEE, 2022, pp. 466–471. [Online]. Available: <https://doi.org/10.1109/ASP-DAC52403.2022.9712555>
- [30] M. Ghallab, D. Nau, and P. Traverso, *Automated Planning: theory and practice*. Elsevier, 2004.

APPENDIX

Listing 10. Adder circuit – Local model; domain file

```
(define (domain Quantum)
(:requirements :typing)
(:types pqubit lqubit gateid - object)
(:constants g4 g9 g10 g11 g12
             g13 g14 g19 g20 g22 - gateid
             10 11 12 13 - lqubit)
(:predicates
 (mapped_pq ?p - pqubit)
 (used ?p - pqubit)
 (mapped ?l - lqubit ?p - pqubit))
```

```
(connected ?p1 - pqubit ?p2 - pqubit)
(rcnot ?g - gateid))

(:action swap
:parameters (?l1 - lqubit ?l2 - lqubit
             ?p1 - pqubit ?p2 - pqubit)
:precondition (and(mapped ?l1 ?p1)
                 (mapped ?l2 ?p2)
                 (connected ?p1 ?p2))
:effect (and(not(mapped ?l1 ?p1))
           (not(mapped ?l2 ?p2))
           (mapped ?l1 ?p2)(mapped ?l2 ?p1)))

; ancillary
(:action swap
:parameters (?l1 - lqubit
             ?p1 - pqubit ?p2 - pqubit)
:precondition (and(mapped ?l1 ?p1)
                 (not(mapped_pq ?p2))
                 (connected ?p1 ?p2))
:effect (and(not(mapped ?l1 ?p1))(mapped ?l1 ?p2)
           (not(mapped_pq ?p1))(mapped_pq ?p2)
           (used ?p2)))

(:action apply_cnot_g4
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(used ?p1))
                 (not(used ?p2))
                 (rcnot g4)(connected ?p1 ?p2))
:effect (and(not(rcnot g4))(mapped 12 ?p1)
           (mapped_pq ?p1)(used ?p1)
           (mapped 13 ?p2)(mapped_pq ?p2)
           (used ?p2)))

(:action apply_cnot_g9
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(used ?p1))
                 (not(used ?p2))
                 (rcnot g9)(connected ?p1 ?p2))
:effect (and(not(rcnot g9))(mapped 10 ?p1)
           (mapped_pq ?p1)(used ?p1)
           (mapped 11 ?p2)(mapped_pq ?p2)
           (used ?p2)))

(:action apply_cnot_g10
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(rcnot g4))(mapped 12 ?p1)
                 (not(rcnot g4))(mapped 13 ?p2)
                 (rcnot g10)
                 (connected ?p1 ?p2))
:effect (and(not(rcnot g10))))

(:action apply_cnot_g11
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(rcnot g9))(mapped 13 ?p1)
                 (not(rcnot g10))(mapped 10 ?p2)
                 (rcnot g11)
                 (connected ?p1 ?p2))
:effect (and(not(rcnot g11))))

(:action apply_cnot_g12
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(rcnot g9))(mapped 11 ?p1)
                 (not(rcnot g10))(mapped 12 ?p2)
                 (rcnot g12)
                 (connected ?p1 ?p2))
:effect (and(not(rcnot g12))))
```

```

(:action apply_cnot_g13                                     (rcnot g20)
:parameters (?p1 - pqubit ?p2 - pqubit)                   (rcnot g22))
:precondition (and(not(rcnot g11)) (:goal
    (mapped 10 ?p1)(not(rcnot g12)) (and
    (mapped 11 ?p2)(rcnot g13)      (not (rcnot g4))
    (connected ?p1 ?p2))           (not (rcnot g9))
:effect (and(not(rcnot g13))))                          (not (rcnot g10))
                                                    (not (rcnot g11))
                                                    (not (rcnot g12))
                                                    (not (rcnot g13))
                                                    (not (rcnot g14))
                                                    (not (rcnot g19))
                                                    (not (rcnot g20))
                                                    (not (rcnot g22))))

(:action apply_cnot_g14                                     (rcnot g20)
:parameters (?p1 - pqubit ?p2 - pqubit)                   (rcnot g22))
:precondition (and(not(rcnot g11))(mapped 12 ?p1) (not (rcnot g14))
    (not(rcnot g12))(mapped 13 ?p2) (not (rcnot g19))
    (rcnot g14)                       (not (rcnot g20))
    (connected ?p1 ?p2))               (not (rcnot g22))))
:effect (and(not(rcnot g14))))

(:action apply_cnot_g19
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(rcnot g13))(mapped 10 ?p1)
    (not(rcnot g13))(mapped 11 ?p2)
    (rcnot g19)
    (connected ?p1 ?p2))
:effect (and(not(rcnot g19))))

(:action apply_cnot_g20
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(rcnot g14))(mapped 12 ?p1)
    (not(rcnot g14))(mapped 13 ?p2)
    (rcnot g20)
    (connected ?p1 ?p2))
:effect (and(not(rcnot g20))))

(:action apply_cnot_g22
:parameters (?p1 - pqubit ?p2 - pqubit)
:precondition (and(not(rcnot g19))(mapped 13 ?p1)
    (not(rcnot g20))(mapped 10 ?p2)
    (rcnot g22)
    (connected ?p1 ?p2))
:effect (and(not(rcnot g22))))

```

Listing 11. Adder circuit – Local model; problem file

```

(define (problem test)
(:domain Quantum)
(:objects p0 p1 p2 p3 p4 - pqubit)
(:init
    (connected p1 p0)
    (connected p2 p0)
    (connected p2 p1)
    (connected p3 p2)
    (connected p3 p4)
    (connected p4 p2)
    (connected p0 p1)
    (connected p0 p2)
    (connected p1 p2)
    (connected p2 p3)
    (connected p4 p3)
    (connected p2 p4)
    (rcnot g4)
    (rcnot g9)
    (rcnot g10)
    (rcnot g11)
    (rcnot g12)
    (rcnot g13)
    (rcnot g14)
    (rcnot g19)

```