

Teaching Magnetism with Bivectors

Steward Jensen*

Department of Physics and Engineering, Alma College, Alma, MI 48801

(Dated: September 7, 2023)

Magnetic fields are traditionally presented as a (pseudo)vector quantity, tied closely to the cross product: familiar ideas to experts but full of challenges and subtleties for students. Building on earlier work in rotational physics, we present an alternative approach to teaching the subject in which magnetic fields are instead described using *bivectors*, which can be visualized as “tiles” with area and orientation whose components form an antisymmetric matrix. Bivectors have historically been considered mostly in specialized contexts like spacetime classification or geometric algebra, but they are no more complicated to understand than cross products. Teaching magnetism in this language addresses common student difficulties, opens the door to understanding the topic in relativity and extra dimensions, and can give fresh insight into these familiar ideas.

I. INTRODUCTION

Learning magnetism for the first time is challenging. The concept of a field is subtle, and students who have just started to understand electric fields are then presented with a second type of field that is illustrated almost identically but has very different behavior. They need to learn how and when to use multiple different right-hand rules, which are known to be challenging for new learners, and the use of right-hand rules means that there are no simple two-dimensional examples to start from: every magnetism problem requires three-dimensional reasoning. Even after overcoming those challenges, more advanced students may still stumble over the pseudovector behavior of the magnetic field or be puzzled by relativistic electromagnetism where the antisymmetric tensor form of the field arises without any clear motivation.

Much of this becomes less challenging if we present the magnetic field as a *bivector* quantity, instead of the traditional vector description. Figure 1 illustrates the bivector magnetic field of two bar magnets, visualized as oriented “tiles” that thread like beads along the traditional field lines: a clear visual distinction from the vector electric field. Each tile’s area represents the field’s magnitude; the orientation is counterclockwise when looking into a north pole and clockwise when looking into a south pole.

As will be explained, the bivector formalism itself does not involve any right-hand rules and avoids the subtleties of pseudovectors, but a simple right hand rule can relate each tile to the corresponding traditional vector. Purely two dimensional examples are natural, because magnetic forces act in the bivector’s plane, and the step from three dimensional magnetism to four dimensional space-time becomes entirely straightforward.

Just as traditional vector instruction in magnetism often builds on prior experience using cross products in the analysis of rotational motion, teaching magnetism with bivectors follows most naturally when students have previously studied rotations in that language. The author




FIG. 1. Two bar magnets whose north poles are marked with colored tape. The resulting magnetic field lines are illustrated in the magnets’ plane, along with bivector tiles representing the magnetic field. (The tiles might be imagined as beads threading along the field lines, each tile orthogonal to the line at its location.) Magnetic field bivectors are oriented counterclockwise when looking into a north pole and clockwise when looking into a south pole. Larger tiles represent stronger fields. (For visual clarity, the magnetic field tiles are labeled with their orientation and also shaded so the counterclockwise side is light orange and the clockwise side is darker blue.)

and a student discussed how to teach rotational physics using bivectors in previous work.¹ (The present article can stand alone, but readers may prefer to first familiarize themselves with bivectors in that simpler context.) One key conclusion for both rotational physics and magnetism is that even instructors who choose to retain the traditional focus on vector descriptions may benefit from incorporating some elements of the bivector picture.

Most physicists have never studied bivectors, and it may at first seem unwise to present students with these unfamiliar new geometrical and mathematical ideas. But to new learners, cross products are just as unfamiliar and the math is just as daunting. Even after instruction, Deprez et al. found that two thirds of second semester physics students score below 50% on tests of cross products in electromagnetism (or as pure math).² Students’ conceptual understanding is fragile enough that in a study

* jensens@alma.edu

by Kustusch, awkward arm positions for the right-hand rule significantly reduced their accuracy and they struggled with cross products of vectors that pointed out of the page.³ (This source includes an excellent review of literature on student difficulties with right-hand rules.)

Meanwhile, describing the magnetic field in the same vector language as the electric field has its own costs. Guisasola et al. found that students very often analyze magnetic field problems using an “electrical” model as if north and south poles act like positive and negative charges.⁴ Similar electric-like mental models of magnetism were reported by Maloney et al.⁵ and by Scaife and Heckler,⁶ the latter of whom also found that after studying magnetism, many students became confused about electric fields as well.⁷ A clear geometrical distinction between the descriptions of electric and magnetic fields can make these confusions less likely.

Mathematically, bivectors are rank-2 antisymmetric tensors closely related to differential 2-forms (in the same way that vectors are related to 1-forms). Many advanced treatments of electromagnetism model it as a 2-form field, but bivectors have a simpler geometrical interpretation and relate more directly to the familiar vector electric field. They arise in multiple contexts: for example, they are used in the Petrov classification of spacetimes,^{8,9} and the study of general relativity with torsion.¹⁰

Even though bivectors are rarely discussed in the traditional curriculum, they have broad applicability: any equation involving cross products or curls can be rewritten in bivector language. In fact, as discussed below the electromagnetic field tensor $F^{\mu\nu}$ is a (four-dimensional) bivector, though the term is rarely used.

A topic in mathematical physics where knowledge of bivectors is already essential is geometric algebra. The text by Doran and Lasenby provides a thorough pedagogical presentation along with a broad collection of applications.¹¹ Other introductions include a tutorial article by Gull, Lasenby, and Doran,¹² the Oersted medal lecture by Hestenes,¹³ and articles by Vold about rotations¹⁴ and electromagnetism.¹⁵ However, these sources put strong emphasis on the role of bivectors within the structure of geometric algebra, and readers can easily get the impression that bivectors are only meaningful in that context.¹⁶ The present work encourages the adoption of bivectors far beyond geometric algebra, but students of that subject may find this independent introduction to bivectors to be a helpful first step.

The organization of this paper is as follows. Section II uses the field of a current loop as context to introduce the bivector magnetic field. Section III calculates magnetic fields from moving source charges, and Section IV then computes the forces exerted by magnetic fields on particles and currents. Relativistic electromagnetism is discussed in Section V. Finally, Section VI presents conclusions and notes on pedagogy. Appendix A discusses magnetic moment and torque. Additionally, Appendix B sketches more advanced material including the vector potential, energy and momentum, and extra dimensions. Last of all,




FIG. 2. *Left:* A square current loop produces a bivector magnetic field whose orientation at points inside the loop matches the direction of current flow. Along the central axis the field weakens with distance, but its orientation is the same. *Right:* That total field at any point is the sum of contributions from all four straight wires. In the plane of the loop, each side contributes a field in that plane: parallel tiles add their areas. Elsewhere, each contributed tile is tilted: one edge points toward the source, and the other is parallel to the current. Along the axis, the field components in the plane of the loop add, while the components orthogonal to the loop cancel.

Appendix C provides a reference for bivector operations.

II. ESSENTIAL INTUITION: THE MAGNETIC FIELD OF A CURRENT LOOP

When introducing magnetism, instructors must always choose whether to begin with the *sources* of magnetic fields or with the *effects* of those fields. Just as with the traditional description based on cross products, either order can work in the bivector formalism. Here, we choose to begin with an intuitive description of magnetic fields produced by flowing currents.

Figure 2 shows a geometric visualization of bivector fields. The bivector magnetic field \overleftrightarrow{b} at a point is represented as a two-dimensional tile whose *area* is proportional to the bivector’s magnitude and which has a specific *attitude* (the angle of the plane in space) and *orientation* (clockwise or counterclockwise). The *shape* of the tile is not physically significant, and in fact it is sometimes helpful to change from one shape to another.

The example of a square current loop in Figure 2 displays an essential piece of intuition: the bivector magnetic field \overleftrightarrow{b} produced within an isolated (planar) current loop always has the same orientation as the flow of current around the loop. Not only that, but at points inside the loop each straight wire segment’s individual contribution to the field has that same orientation.

This second observation is enough to determine the attitude and orientation of a straight wire’s field contribution at *any* point: just picture that wire as if it were one edge of an imagined larger tilted (planar) loop encircling the measurement point. Then the field tile must be tilted to match. For example, on the right of Figure 2, the contribution of wire 4 at a point above the loop is represented as a tile tilted down toward its source wire.




FIG. 3. The tile representing \overleftrightarrow{b} is projected onto each of the three coordinate planes. Comparing the orientation of each projection to the plane's orientation (shown here in cyclic coordinate order), in this example we can see that b_{xy} and b_{yz} are positive while b_{zx} is negative. (If we instead considered the other orientation for the xz -plane, we would say b_{zx} was positive.) Also shown is the normal vector \vec{B} to the tile, which is equivalent to the usual magnetic field: its direction relates to the orientation of \overleftrightarrow{b} by the right hand rule.

We might imagine the flow of current “dragging” the near side of the tile to rotate in its plane.

Like vectors, bivectors can be quantitatively described by their coordinate components, as illustrated in Figure 3. Because tiles are two-dimensional those components correspond to coordinate *planes* (each specified by two coordinate labels). For example, the magnitude of the component b_{xy} is the tile's projected area on the xy plane, and that component is positive because the projection's orientation matches the direction that rotates x toward y . But since this is opposite the direction that rotates y into x , we say that $b_{yx} = -b_{xy}$: the component labels are antisymmetric. A component with a repeated label like b_{xx} does not specify a plane, so we treat these as zero.

Thus, specifying the three components b_{xy} , b_{yz} , and b_{zx} is enough to uniquely specify the bivector. (We have arbitrarily chosen to label the three coordinate pairs in cyclic order.) Even though they label areas rather than lengths, these components combine according to the Pythagorean theorem to give the bivector's overall magnitude:¹⁷

$$|\overleftrightarrow{b}| = b_{xy}^2 + b_{yz}^2 + b_{zx}^2 = \frac{1}{2} \sum_{i,j=\{x,y,z\}} b_{ij}^2 \quad (1)$$

The factor of $\frac{1}{2}$ corrects for double counting in the sum over all possible index pairs, since (e.g.) b_{xy} and b_{yx} are not independent. The components naturally form an antisymmetric matrix (or rather, second rank tensor):

$$\overleftrightarrow{b} = \begin{pmatrix} 0 & b_{xy} & b_{zx} \\ b_{yx} & 0 & b_{yz} \\ b_{zx} & b_{zy} & 0 \end{pmatrix} = \begin{pmatrix} 0 & b_{xy} & -b_{zx} \\ -b_{xy} & 0 & b_{yz} \\ b_{zx} & -b_{yz} & 0 \end{pmatrix} \quad (2)$$

where in the second form we have put all component indices into cyclic order.




FIG. 4. *Left*: The bivector magnetic field of a current loop, along with the normal vector \vec{B} that corresponds to it by the right-hand rule: the traditional magnetic field. *Right*: The same scenario, reflected horizontally. The bivector magnetic field has naturally reversed its orientation under reflection, but now the right-hand rule indicates that the corresponding traditional field \vec{B}' should point down, while the reflection of the original \vec{B} still points up. This reversal of \vec{B} under reflection is the defining characteristic of a *pseudovector*.

Figure 3 also illustrates that the traditional magnetic field vector \vec{B} is normal to the bivector \overleftrightarrow{b} in the direction given by a right-hand rule. In components:

$$\vec{B} = \begin{pmatrix} B_x \\ B_y \\ B_z \end{pmatrix} = \begin{pmatrix} b_{yz} \\ b_{zx} \\ b_{xy} \end{pmatrix} \quad (3)$$

Because this equation relies on cyclic coordinate order, a right handed coordinate system becomes necessary any time we work with \vec{B} .

As a final qualitative example of magnetic sources, Figure 1 showed the magnetic field of two permanent bar magnets. That image illustrates the field in two ways: as magnetic field lines that spread out from the north poles of the magnets and converge into the south poles, and as bivector “tiles” like beads strung along the field lines. The plane of each tile is orthogonal to the field line at its center (since field lines are parallel to the normal vector \vec{B}), and the tiles' orientations are related to the north and south poles of the magnets: the bivector field appears *counterclockwise* when looking into a north pole and *clockwise* when looking into a south pole. All the usual explanations for magnetized materials carry over smoothly to the bivector description.

Before moving on to quantitative calculations, we should pause to observe that the traditional magnetic field vector \vec{B} constructed by a right-hand rule is not a “true” vector (or *polar vector*) at all, but rather a *pseudovector* (or *axial vector*). It behaves like a vector under rotations, but under a reflection like $x \rightarrow -x$ its overall direction reverses (in addition to the reflection) as shown in Figure 4: $(B_x, B_y, B_z) \rightarrow (B_x, -B_y, -B_z)$. This awkward behavior of pseudovectors becomes entirely natural in bivector components, where the components whose sign changes are precisely the ones involving x : $(b_{yz}, b_{zx}, b_{xy}) \rightarrow (b_{yz}, -b_{zx}, -b_{xy})$. This corresponds to reversing the signs of the x -row and x -column of the \overleftrightarrow{b} matrix (matching the usual tensor transformation law).




FIG. 5. *A*: A point charge q moving to the right with velocity \vec{v} creates magnetic fields \vec{b}_1 and \vec{b}_2 at points above and below its line of motion, each illustrated by an oriented tile: counterclockwise above that line and clockwise below it. The rest of the figure illustrates the calculation of those two fields. *B*: The calculation of each wedge product $\vec{v} \wedge \hat{r}$. In each case, the two vectors define a parallelogram in the plane of the page with area $|\vec{v} \wedge \hat{r}| = |\vec{v}|h = |\vec{v}||\hat{r}|\sin\theta$. By placing the vectors tip to tail in product order (followed by their negatives to close the parallelogram), the arrows determine the orientation of the bivector tile. *C*: Each field is computed from Eq. (4): a scalar multiplication simply rescales the area of the tile. For clarity, in the last step both tiles have been reshaped to squares (while keeping each one's area and orientation the same).

III. MAGNETIC FIELDS FROM MOVING CHARGES AND THE WEDGE PRODUCT

Now that we have established the basic mathematics of bivectors, we are ready for quantitative calculations. The simplest magnetic field source equation is that for a point charge q moving at constant (nonrelativistic) velocity \vec{v} . This scenario is illustrated in Figure 5A, where the magnetic field bivector \vec{b} is considered at two points: one ahead of the charge at an angle θ from its direction of motion and one farther away directly to its side. The equation for computing this bivector field is

$$\vec{b} = \frac{\mu_0 q}{4\pi r^2} (\vec{v} \wedge \hat{r}) \quad , \quad (4)$$

where $\mu_0 \approx 4\pi \times 10^{-7} \text{ T s m/C}$, \vec{r} is the position of the measurement point relative to the source, $r \equiv |\vec{r}|$, and $\hat{r} \equiv \frac{\vec{r}}{r}$ is a unit vector in that direction.

In the final term, instead of the cross product from the traditional equation we see instead the *wedge product* of the vectors \vec{v} and \hat{r} . As illustrated in Figure 5B, the wedge product of two vectors defines a bivector represented by a parallelogram tile whose edges are the two vector arrows aligned tip to tail in product order (followed by the same two vectors in reverse): this loop of arrows defines the bivector's orientation. This matches our essential intuition about bivector magnetic fields: the tile will always lie in a plane that includes both the motion of the moving charge and the direction to it, oriented as if the moving charge is “dragging” the near edge.

The magnitude of the wedge product bivector is the area of the parallelogram,

$$|\vec{v} \wedge \hat{r}| \equiv |\vec{v}| |\hat{r}| \sin\theta = |\vec{v}| \sin\theta \quad . \quad (5)$$

In the cases shown here where the bivector tile lies in the plane of the page, we can write $\vec{v} \wedge \hat{r}_1 = |\vec{v}| \sin\theta \begin{smallmatrix} \circlearrowleft \\ \square \end{smallmatrix}$ and $\vec{v} \wedge \hat{r}_2 = |\vec{v}| \sin 90^\circ \begin{smallmatrix} \circlearrowright \\ \square \end{smallmatrix} = |\vec{v}| \begin{smallmatrix} \circlearrowright \\ \square \end{smallmatrix}$. (The symbol $\begin{smallmatrix} \circlearrowleft \\ \square \end{smallmatrix}$ indicates a counterclockwise tile in the plane of the page, just as

\odot indicates a vector out of the page. We can interpret these symbols as “unit bivectors”. Unit bivectors in other planes will be illustrated in Figure 6.)

This geometric definition makes it clear that the wedge product of vectors is antisymmetric, $\vec{u} \wedge \vec{v} = -\vec{v} \wedge \vec{u}$: reversing the order in which the two vectors are placed tip to tail reverses the tile's orientation. Consistent with that, the wedge product of a vector with itself has zero area: $\vec{v} \wedge \vec{v} = 0$. It is also linear: $(a\vec{u}) \wedge \vec{v} = a(\vec{u} \wedge \vec{v}) = \vec{u} \wedge (a\vec{v})$ and $\vec{u} \wedge (\vec{v} + \vec{w}) = \vec{u} \wedge \vec{v} + \vec{u} \wedge \vec{w}$.

These results are also evident from the equation for the wedge product in components:

$$\vec{\ell} = \vec{u} \wedge \vec{v} \quad \implies \quad \ell_{ij} = u_i v_j - u_j v_i \quad , \quad (6)$$

where $i, j = \{x, y, z\}$. Expressing this in matrix form,

$$\vec{\ell} = \begin{pmatrix} 0 & u_x v_y - u_y v_x & u_x v_z - u_z v_x \\ u_y v_x - u_x v_y & 0 & u_y v_z - u_z v_y \\ u_z v_x - u_x v_z & u_z v_y - u_y v_z & 0 \end{pmatrix} \quad (7)$$

$$= \begin{pmatrix} 0 & L_z & -L_y \\ -L_z & 0 & L_x \\ L_y & -L_x & 0 \end{pmatrix} \quad .$$

In the second line, we have replaced the components of $\vec{\ell}$ with the components of its corresponding normal (pseudo)vector \vec{L} according to Eq. (3). These component equations precisely match those for the cross product $\vec{L} = \vec{u} \times \vec{v}$, and in the matrix form of Eq. (7) they are easy to remember: the subscripts of each positive term simply label the row and column (in that order), with no need to puzzle through cyclic coordinate patterns. (This can be taken as the *definition* of the cross product.)

Rather than listing components, we can also express quantities in terms of the coordinate unit vectors by using the wedge product as illustrated in the top row of Figure 6: “ $\hat{x} \wedge \hat{y}$ ” means “a unit tile in the xy -plane, oriented in the direction that rotates \hat{x} toward \hat{y} .” For our




FIG. 6. *Top*: Labeled representations of coordinate unit bivectors based on the three dimensional coordinate system shown: e.g. $\hat{x} \wedge \hat{y}$ is a unit bivector in the xy -plane oriented in the direction that rotates \hat{x} toward \hat{y} . *Bottom*: “Decorated” vectors representing the same three bivector orientations together with their corresponding normal vectors, related by the right hand rule.

examples, $\vec{v} \wedge \hat{r}_1 = |\vec{v}| \sin \theta \hat{x} \wedge \hat{y}$ and $\vec{v} \wedge \hat{r}_2 = |\vec{v}| \hat{x} \wedge (-\hat{y}) = -|\vec{v}| \hat{x} \wedge \hat{y} = |\vec{v}| \hat{y} \wedge \hat{x}$ (using the antisymmetry of \wedge).

As the final step in computing the field, as shown in Figure 5C the actual magnetic field bivector is a scalar multiple of the wedge product $\vec{v} \wedge \hat{r}$. This simply scales the magnitude of the bivector, and correspondingly, the area of the tile drawn. In the final step at the far right, we have reshaped both tiles to squares for easier comparison of their magnitudes (while keeping their areas and orientations the same). We can express the result in any of the usual ways. In explicit components, $b_{1,xy} = \frac{\mu_0 q}{4\pi r_1^2} |\vec{v}| \sin \theta$ and $b_{2,xy} = -\frac{\mu_0 q}{4\pi r_2^2} |\vec{v}|$.

Now that we can compute fields due to point sources, we can apply the same reasoning to magnetostatics problems. For a steady current through a thin continuous wire composed of infinitesimal segments $d\vec{l}$, the magnetic field is computed as a sum using the Biot-Savart law:

$$\overleftrightarrow{b} = \frac{\mu_0 I}{4\pi} \int \frac{1}{r^2} (d\vec{l} \wedge \hat{r}) \quad . \quad (8)$$

Sums and integrals of bivectors can be computed component by component just as for vectors. (Understanding bivector sums geometrically without resorting to components can be subtle: see Sec. IV of Ref. [1].)

For example, as illustrated in Figure 7, consider a current I flowing through an infinite wire along the x -axis: $\vec{I} = I\hat{x}$. We seek to measure the magnetic field at position $\vec{\rho} = (0, y, z)$, a distance $\rho = \sqrt{y^2 + z^2} > 0$ from the wire. Then $d\vec{l} \wedge \hat{r} = dx\hat{x} \wedge (\frac{x}{r}\hat{x} + \frac{y}{r}\hat{y} + \frac{z}{r}\hat{z})$, so

$$\begin{aligned} \overleftrightarrow{b} &= \frac{\mu_0 I}{4\pi} (y\hat{x} \wedge \hat{y} + z\hat{x} \wedge \hat{z}) \int_{-\infty}^{\infty} dx \frac{1}{(x^2 + \rho^2)^{3/2}} \\ &= \frac{\mu_0 I}{4\pi} (\hat{x} \wedge \vec{\rho}) \frac{2}{\rho^2} = \frac{\mu_0 I}{2\pi\rho} \hat{x} \wedge \hat{\rho} \quad . \end{aligned} \quad (9)$$

This agrees with the familiar vector result for the magnitude, and as usual each tile lies in a plane that extends both along the wire’s direction and radially away from it. (To apply our essential intuition, we might imagine the wire bending far away into a loop around any given




FIG. 7. An infinite straight wire carrying current I along the x -axis produces a bivector magnetic field whose orientation fans around the wire: in keeping with the Biot-Savart law’s $I d\vec{l} \wedge \hat{r}$ term, each tile has an edge parallel to the wire source and another that extends radially away from it. Also shown are magnetic field lines circling around the wire.

measurement point.) Naturally, we could instead have taken separate integrals for b_{xy} and b_{xz} .

At last, we can return to our initial example illustrated in Figure 2: the magnetic field along the (z -)axis of a square wire loop of side length $2L$ carrying steady current I . A calculation similar to Eq. (9) for the field along the central plane of a finite straight wire leads to

$$\begin{aligned} \overleftrightarrow{b} &= \frac{\mu_0 I}{2\pi\rho} \frac{L}{\sqrt{\rho^2 + L^2}} \hat{x} \wedge \hat{\rho} \quad , \text{ and thus} \quad (10) \\ \overleftrightarrow{b}_1 &= \frac{\mu_0 I}{2\pi(z^2 + L^2)} \frac{L}{\sqrt{z^2 + 2L^2}} \hat{x} \wedge (L\hat{y} + z\hat{z}) \quad , \end{aligned}$$

where the second line is specific to wire 1’s field along the z -axis as shown (for which $\vec{\rho} = L\hat{y} + z\hat{z}$). The contributions of the other three wires give the same fraction terms and differ only in the wedge products: those are

$$\begin{aligned} \overleftrightarrow{b}_1 &= \dots \hat{x} \wedge (L\hat{y} + z\hat{z}) & \overleftrightarrow{b}_3 &= \dots (-\hat{x}) \wedge (-L\hat{y} + z\hat{z}) \\ \overleftrightarrow{b}_2 &= \dots \hat{y} \wedge (-L\hat{x} + z\hat{z}) & \overleftrightarrow{b}_4 &= \dots (-\hat{y}) \wedge (L\hat{x} + z\hat{z}) \end{aligned} \quad (11)$$

Rearranging the wedge products to a common order and summing the fields, the $\hat{x} \wedge \hat{y}$ components all reinforce each other, and the others cancel out. Overall,

$$b_{\text{loop}} = \frac{\mu_0 I}{2\pi(z^2 + L^2)} \frac{4L^2}{\sqrt{z^2 + 2L^2}} \hat{x} \wedge \hat{y} \quad . \quad (12)$$

This establishes our central result and intuition.

IV. MAGNETIC FORCES AND THE MATRIX PRODUCT

Now that we understand the sources of magnetic fields in bivector language, we can study their effect on moving charges. We first consider the example illustrated in Figure 8: a particle of charge $q = +1 \mu\text{C}$ moving at




FIG. 8. A positively charged particle q moving with velocity \vec{v} in a uniform magnetic field \overleftrightarrow{b} oriented counterclockwise in the plane. The direction of the magnetic force is found by rotating the velocity vector by 90° *opposite* the field's orientation (here, a clockwise rotation). This leads the particle to follow a clockwise circular path: also opposite the field's orientation.

1 m/s upward (in the $+y$ direction) through a region of uniform magnetic field $\overleftrightarrow{b} = 6 \text{ mT} \overleftrightarrow{\square}$. We could also write the bivector field as a single non-vanishing component: $b_{xy} = 6 \text{ mT}$ (or equivalently, $b_{yx} = -6 \text{ mT}$).

The bivector equation for the magnetic force on this particle involves a “dot product” of the magnetic field and the velocity:

$$\vec{F}_m = q \overleftrightarrow{b} \cdot \vec{v} \quad (13)$$

$$|\vec{F}_m| = |q| |\overleftrightarrow{b}| |\vec{v}| \cos \theta \quad (14)$$

The second line gives the force's magnitude for general directions of motion, where θ is the angle between the velocity and the bivector plane. Because our velocity is in the plane of the bivector ($\theta = 0$), the magnitude is $|\vec{F}_m| = |q| |\overleftrightarrow{b}| |\vec{v}| = 6 \text{ nN}$. To find force's direction, start from the velocity vector and rotate 90° *opposite* the orientation of the bivector field. In our case, this results in a force to the right (in the $+x$ direction), and the particle eventually follows a clockwise circular path (which is likewise opposite the field's orientation).

The antisymmetry of \overleftrightarrow{b} means that we could equally well have written Eq. (13) as $\vec{F}_m = -q \vec{v} \cdot \overleftrightarrow{b}$. Although this equation is less elegant, it is more explicit geometrically: in this other order, the product $\vec{v} \cdot \overleftrightarrow{b}$ rotates the vector in the *same* direction as the bivector's orientation, and then the minus sign provides an explicit reminder to reverse it.

For those familiar with matrix math, the dot product in Eq. (13) can be interpreted as a matrix product with \vec{v} as a column vector:

$$\vec{F}_m = 1 \mu\text{C} \begin{pmatrix} 0 & 6 \text{ mT} \\ -6 \text{ mT} & 0 \end{pmatrix} \begin{pmatrix} 0 \\ 1 \text{ m/s} \end{pmatrix} = \begin{pmatrix} 6 \text{ nN} \\ 0 \end{pmatrix} \quad (15)$$

(If antisymmetry is used to write the product in the other order, we must instead interpret \vec{v} and \vec{F}_m as row matrices.) One benefit of bivector language is already evident: to describe motion in a plane we can work entirely in two dimensions! The only nonzero component of the magnetic field is b_{xy} , unlike the traditional formulation of this scenario where $B_z \neq 0$.

For students who are not comfortable with matrix multiplication, one can simply list formulas for each component

(as is often done for the cross product). Including all three dimensions for future reference,

$$\begin{aligned} F_{m,x} &= q(b_{xx}v_x + b_{xy}v_y + b_{xz}v_z) = q(b_{xy}v_y - b_{zx}v_z), \\ F_{m,y} &= q(b_{yx}v_x + b_{yy}v_y + b_{yz}v_z) = q(b_{yz}v_z - b_{xy}v_x), \\ F_{m,z} &= q(b_{zx}v_x + b_{zy}v_y + b_{zz}v_z) = q(b_{zx}v_x - b_{yz}v_y). \end{aligned} \quad (16)$$

In the last step of each line, we have used the antisymmetry of \overleftrightarrow{b} to eliminate components with repeated indices and (purely for ease of comparison to the usual cross product) to standardize its components in cyclic order. The pattern of matching index labels in each component equation is straightforward to explain, and may be easier to remember than the cyclic pattern for cross products. (Expressed in index notation, $F_{m,i} = q \sum_{j=\{x,y,z\}} b_{ij}v_j$.)

We could also write our example in the language of coordinate unit bivectors, where the velocity is $\vec{v} = 1 \text{ m/s} \hat{y}$ and the magnetic field is $\overleftrightarrow{b} = 6 \text{ mT} \hat{x} \wedge \hat{y}$. (We do not need a separate $-6 \text{ mT} \hat{y} \wedge \hat{x}$ term: by antisymmetry, it would be redundant.) Then from Eq. (13),

$$\begin{aligned} \vec{F}_m &= 1 \mu\text{C} (6 \text{ mT} \hat{x} \wedge \hat{y}) \cdot 1 \text{ m/s} \hat{y} \\ &= 6 \text{ nN} (\hat{x} \wedge \hat{y} \cdot \hat{y}) = 6 \text{ nN} \hat{x} \quad , \end{aligned} \quad (17)$$

where in the last step we have used the fact that $\hat{y} \cdot \hat{y} = 1$ to simplify the products of unit vectors.

To expand on that last point, if we had used the force equation in the other order, $\vec{F}_m = -q \vec{v} \cdot \overleftrightarrow{b}$, we would have needed to use antisymmetry to reverse the wedge product to bring the two \hat{y} s adjacent before evaluating the dot product:

$$\begin{aligned} \vec{F}_m &= -6 \text{ nN} (\hat{y} \cdot \hat{x} \wedge \hat{y}) = -6 \text{ nN} (\hat{y} \cdot (-\hat{y} \wedge \hat{x})) \\ &= -6 \text{ nN} (\hat{y} \cdot \hat{y} \wedge (-\hat{x})) = -6 \text{ nN} (-\hat{x}) = 6 \text{ nN} \hat{x} \quad , \end{aligned} \quad (18)$$

with the same final result.¹⁸ These steps can give insight into our original geometric explanation of bivector dot products: in the form of Eq. (17) the dot product removed the second unit vector (\hat{y}), rotating the result “backward” toward the first (\hat{x}), while in the form of Eq. (18) (line 2) the dot product removed the first unit vector (\hat{y}), rotating the result “forward” toward the second ($-\hat{x}$).

More generally, the particle's velocity may not lie in the magnetic field's bivector plane. Consider the case illustrated in Figure 9, where our particle of charge $q = 1 \mu\text{C}$ is moving with velocity $\vec{v} = (4\hat{x} + 3\hat{z}) \text{ m/s}$ (an angle of $\theta \approx 37^\circ$ above the xy -plane). At its location there is a magnetic field $\overleftrightarrow{b} = 6 \text{ mT} \hat{x} \wedge \hat{y}$. Using Eq. (14), we can compute the magnitude of the resulting magnetic force:

$$|\vec{F}_m| = 1 \times 10^{-6} \text{ C} \cdot 6 \times 10^{-3} \text{ T} \cdot 5 \text{ m/s} \cdot \frac{4}{5} = 24 \text{ nN} \quad (19)$$

The direction is found by first projecting the velocity vector to the plane of the bivector ($4 \text{ m/s} \hat{x}$) and then rotating it 90° opposite the bivector's orientation, as before: the $-\hat{y}$ direction. It is worth explicitly observing




FIG. 9. A positively charged particle q moving with velocity \vec{v} at an angle θ from \hat{x} toward \hat{z} feels a force due to a magnetic field \vec{b} in the xy -plane. The direction of the magnetic force is found by first projecting the velocity vector into the plane of \vec{b} (reducing its length by a factor of $\cos\theta$) and then rotating it by 90° opposite the field's orientation. The resulting magnitude is then $|\vec{F}_m| = |q| |\vec{b}| |\vec{v}| \cos\theta$. If \vec{B} is the traditional magnetic field vector corresponding to \vec{b} , then the angle between \vec{B} and \vec{v} is $90^\circ - \theta$ and the trig function becomes $\cos\theta = \sin(90^\circ - \theta)$: magnitude and direction agree with the usual cross product.

that Eq. (14) agrees with the familiar formula for cross product magnitude. As shown, the traditional magnetic field vector \vec{B} is normal to the bivector tile so the angle between \vec{B} and \vec{v} is $90^\circ - \theta$, and $\cos\theta = \sin(90^\circ - \theta)$.

Once again this can be expressed in matrix language:

$$\vec{F}_m = 1 \mu\text{C} \begin{pmatrix} 0 & 6 \text{ mT} & 0 \\ -6 \text{ mT} & 0 & 0 \\ 0 & 0 & 0 \end{pmatrix} \begin{pmatrix} 4 \text{ m/s} \\ 0 \\ 3 \text{ m/s} \end{pmatrix} = \begin{pmatrix} 0 \\ -24 \text{ nN} \\ 0 \end{pmatrix}. \quad (20)$$

The explicit component expressions of Eq. (16) lead to the same result. In terms of coordinate unit vectors,

$$\begin{aligned} \vec{F}_m &= 1 \mu\text{C} \ 6 \text{ mT} \ \hat{x} \wedge \hat{y} \cdot (4\hat{x} + 3\hat{z}) \text{ m/s} \\ &= 24 \text{ nN} (\hat{x} \wedge \hat{y} \cdot \hat{x}) + 18 \text{ nN} (\hat{x} \wedge \hat{y} \cdot \hat{z}) = -24 \text{ nN} \hat{y}, \end{aligned} \quad (21)$$

where in the second line we have distributed the dot product (and combined scalar terms), and then re-ordered the first wedge product to bring the \hat{x} s adjacent. In the second term, \hat{z} is orthogonal to both \hat{x} and \hat{y} , and thus contributes a dot product of zero.

Other standard results for magnetic forces translate naturally into bivector language. For example, the conclusion that magnetic forces do no work follows directly from the antisymmetry of \vec{b} :

$$W = \int \vec{F} \cdot d\vec{l} = \int (-q\vec{v} \cdot \vec{b}) \cdot (\vec{v} dt) = -q \int (\vec{v} \cdot \vec{b} \cdot \vec{v}) dt = 0. \quad (22)$$

Similarly, the magnetic force on a thin wire carrying current I along a path given by infinitesimal segments $d\vec{l}$ is given by the vector integral

$$\vec{F}_m = \int I \vec{b} \cdot d\vec{l}. \quad (23)$$

For a straight wire of directed length \vec{L} , this leads to the result $\vec{F}_m = I \vec{b} \cdot \vec{L}$.

V. ELECTROMAGNETISM AND RELATIVITY

In special relativity, we extend our usual three-dimensional vectors by incorporating an additional time component to create a four-vector. For example, position (x, y, z) combines with time t as the spacetime position $\mathbf{X} = (ct, x, y, z)$, and momentum \vec{p} becomes four-momentum by adding energy as its time component: $\mathbf{P} = (E/c, p_x, p_y, p_z) = m\mathbf{U}$. This last form uses the relativistic four-velocity $\mathbf{U} = \frac{d\mathbf{X}}{d\tau} = (c \frac{dt}{d\tau}, \frac{dx}{d\tau}, \frac{dy}{d\tau}, \frac{dz}{d\tau}) = \gamma(c, v_x, v_y, v_z)$, where τ is proper time and $\gamma = \frac{dt}{d\tau} = 1/\sqrt{1 - v^2/c^2}$.

Electric and magnetic fields do not extend to four-vectors in the same way. Instead, careful arguments show that relativistic transformation laws mix their components together. Imagine, though, that we had treated magnetic fields as bivectors from the start. Then the natural generalization of the 3×3 matrix for \vec{b} in (2) would be a 4×4 matrix, adding a new t -row and t -column at the top and left (superscripts denote contravariant indices):

$$\vec{b}^{\mu\nu} = \begin{pmatrix} 0 & b^{tx} & b^{ty} & b^{tz} \\ -b^{tx} & 0 & b^{xy} & -b^{zx} \\ -b^{ty} & -b^{xy} & 0 & b^{yz} \\ -b^{tz} & b^{zx} & -b^{yz} & 0 \end{pmatrix}. \quad (24)$$

Under Lorentz transformations, the new time-space components mix with the familiar space-space components,¹⁹ while under ordinary rotations the three time-space components remain entirely distinct from the space-space components and instead simply transform as a three-dimensional vector. This corresponds precisely to the familiar electromagnetic field tensor:

$$\vec{F}^{\mu\nu} = \begin{pmatrix} 0 & E_x/c & E_y/c & E_z/c \\ -E_x/c & 0 & B_z & -B_y \\ -E_y/c & -B_z & 0 & B_x \\ -E_z/c & B_y & -B_x & 0 \end{pmatrix}. \quad (25)$$

The correspondence between the \vec{B} and \vec{b} components is familiar, and now we see that the electric field emerges naturally from the four-bivector's timelike components.²⁰

The rules we have seen for effects and sources of magnetic fields generalize directly to this relativistic form. We saw in Eq. (13) that the force on a moving particle was $\vec{F}_m = q\vec{b} \cdot \vec{v}$, or using index notation, $F_{m,i} = q \sum_j b_{ij} v_j$. For relativistic four-vectors, this becomes

$$\begin{aligned} F_{\text{em}}^\mu &= \frac{dP^\mu}{d\tau} = q \sum_\nu b^{\mu\nu} U_\nu = q \sum_{\nu,\rho} b^{\mu\nu} \eta_{\nu\rho} U^\rho, \text{ so} \\ F_{\text{em}}^x &= \frac{dP^x}{dt} = \frac{dP^x}{d\tau} \frac{d\tau}{dt} = \frac{dP^x}{d\tau} \frac{1}{\gamma} = \frac{1}{\gamma} F_{\text{em}}^x \\ &= \frac{1}{\gamma} q \left(\frac{E_x}{c} (\gamma c) + \sum_j b_{xj} (\gamma v_j) \right) = q (E_x + \sum_j b_{xj} v_j), \end{aligned} \quad (26)$$

and similarly for the other components, exactly matching the usual Lorentz force law. Here, $\eta_{\mu\nu} = \text{diag}(-1, 1, 1, 1)$ is the flat metric that defines the spacetime inner product.

Even the formula for the (approximate) magnetic field of a non-relativistic point charge ($\gamma \approx 1$) gives sensible results for its new time components. Taking $\hat{\mathbf{R}} = (0, \hat{r})$, the natural generalization of Eq. (4) is

$$\overleftrightarrow{\mathbf{b}} = \frac{\mu_0 q}{4\pi r^2} (\mathbf{U} \wedge \hat{\mathbf{R}}) \quad . \quad (27)$$

The space-space components are exactly as before. The time-space components give $\overleftrightarrow{\mathbf{b}}^{ti} = (\frac{\mu_0 c}{4\pi}) \frac{q}{r^2} \hat{r}^i$, or since $\epsilon_0 \mu_0 = 1/c^2$, $\vec{E} = \frac{q}{4\pi \epsilon_0 r^2} \hat{r}$: Coulomb's law.

It is enlightening to consider the geometric significance of $\overleftrightarrow{\mathbf{F}}$ as a bivector in four dimensions. As discussed further in Appendix B 3, in d dimensions it is possible to represent any bivector as a sum of $d/2$ or fewer tiles (rounded down). In our context of four-dimensional spacetime, one natural geometric interpretation of $\overleftrightarrow{\mathbf{F}}$ is to consider it as a sum of the usual spatial magnetic field tile (extended to a four-bivector with zero time components) plus an “electric tile” $\hat{\mathbf{t}} \wedge \mathbf{E}/c$, where $\hat{\mathbf{t}} = (1, 0, 0, 0)$ and $\mathbf{E} = (0, E_x, E_y, E_z)$. (In keeping with our intuition for magnetic fields, one might imagine that as charges move through time they also drag the field with them, so electric fields in space show it “rotating away” from the timelike flow of charge.)

That simple electric/magnetic division is always possible, but more careful attention to the bivector's structure can yield deeper insight: under some circumstances, the two pieces of that sum can be simplified into a single tile. The details of algebraic classification of bivectors are beyond the scope of this article, but in brief: if $\overleftrightarrow{\mathbf{F}}$ can be represented by a single tile that contains a timelike four-vector, then there exists a reference frame where the field is entirely electric ($\overleftrightarrow{\mathbf{F}}$ has no space-space components). If it can be represented by a single tile that contains only spacelike four-vectors, there is a reference frame where the field is entirely magnetic. And if it can be represented by a single tile containing exactly one null direction, then the fields are typical of a plane wave propagating in that null direction. Otherwise, $\overleftrightarrow{\mathbf{F}}$ can be written as a sum of two mutually orthogonal tiles (one timelike, one spacelike).

VI. CONCLUSIONS

As we have seen, the bivector description of magnetic fields and their effects is mathematically equivalent to the traditional (pseudo)vector approach. Component by component, the equations are the same: only the labels change. But the geometric interpretation is entirely different: it trades away the familiarity of vector operations (and the subtlety of the cross product) in favor of a picture that is less familiar but has more direct relationships to the sources and effects of the field.

In the classroom, the primary goal of teaching magnetism as a bivector is to help students avoid the known pitfalls of the (pseudo)vector approach, but that has to be balanced against the costs of introducing the new formalism. Every instructor will have to judge how much of the

new picture to incorporate. Instructional time is always at a premium, so the best adjustments will be “revisions” rather than “additions” to the standard curriculum.

A pure bivector treatment would entirely eliminate the need to teach right-hand rules and the cross product (along with worries about left-handed coordinate systems), but that is not practical: students will need to engage with the traditional approach in other courses and contexts for the foreseeable future. But in the author's experience, students appreciate seeing the cross product as “first construct the wedge product tile, and then curl your right-hand fingers so your thumb points along the cross product result.” It doesn't cost much class time to comment that the parallelogram tile is the “true” magnetic field, and that we are just converting it to a vector with the right-hand rule for computational convenience.

The other major pedagogical stumbling block addressed by bivectors is students' tendency to confuse electric and magnetic field vectors and their behaviors. Presenting magnetic fields primarily as tiles rather than arrows would make the distinction clear. But if that is too big a leap, instructors could draw magnetic fields as illustrated in the second row of Fig. 6: draw the traditional (pseudo)vector along with a curved arrow around it indicating the right-hand rule orientation of the corresponding bivector. (A similar convention is sometimes used by engineers to illustrate torque, another pseudovector quantity.)

These “decorated” vectors look at least somewhat distinct from electric field vectors, and they retain the bivector tiles' benefit of a direct visual relationship to the orientation of current loop sources. (Also, like bivector tiles, they may give a helpful reminder that finding the force direction involves rotating in the curved arrow's plane.) With the right pedagogical framing, decorated vectors into or out of the plane in two-dimensional systems might even be close enough to the bivector tile notation to make those problems approachable without the need for much three-dimensional reasoning. This could have real benefits, possibly even at the high school level.

Of course, adopting a new formalism even in part comes with its own challenges. The cross product may be confusing for students, but that one operation applies to any combination of vectors and pseudovectors being multiplied. (When using the cross product with decorated vectors, students would need to keep track of when the result was a pseudovector and when it wasn't.) With bivectors, it is necessary to distinguish between the product of two vectors in Eq. (6), the product of a bivector and a vector in Eq. (13), and the product of two bivectors in Eq. (A4). The geometric differences make it easy to distinguish each from the others, but this is still a lot for students to keep track of: every instructor must judge which works better for their own students.

A final challenge for instructors considering teaching with bivectors today is the lack of direct support in existing textbooks and supplementary resources. In the author's experience, it works best to present a single clear story in class rather than explaining the vector language

first and then presenting bivectors as an alternative (or vice versa): the latter comes across as repetitive and confusing. Without textbooks or other sources that describe the magnetic field as a bivector, it is hard to present that as the primary description to use. Similarly, computational tools like Mathematica and Maple provide built-in support for vectors and vector fields, but handling bivectors requires more effort.²¹

Clearly, there is a tension between these two approaches. The bivector description may have moderate pedagogical advantages, while the pseudovector description has the benefit of over a century of development and tradition. It is natural to ask, if the two are mathematically equivalent, why go to the trouble to switch?

Magnetic field bivectors are true tensors rather than awkward pseudotensors. Relativistic electromagnetism has always required a bivector formulation, but traditionally students are given no geometric insight for that structure. Only the bivector formalism for magnetism can describe a purely two-dimensional problem, or describe magnetic effects in theories of higher dimensions at all. For all these reasons, it is reasonable to conclude that bivectors are a more fundamentally *true* description of magnetic fields, and we owe it to our students to share that with them. Just as significant, understanding magnetic fields as bivectors can give fresh insight into this familiar topic, not least by emphasizing the field's relationship as both cause and effect of rotating charges.

Sharing this insight with students is important and exciting. As we have seen, even if it is not feasible to fully embrace the bivector description right away, there are steps we can take to at least open the door to these deeper ideas, and even those limited steps may have pedagogical benefits. There is more development to be done: most notably, a presentation of Maxwell's equations in bivector language is important, but requires a careful development of bivector calculus.²² But the core ideas stand strongly on their own, and already address the substantial majority of topics in magnetism at the introductory level.

ACKNOWLEDGMENTS

Thanks to Jack Poling for help developing these ideas in the context of rotational physics and for a careful literature search. Figures 1, 2, 4, and 7 were produced with Mathematica. Figures 3 and 6 by the author and most of the reference information in Appendix C previously appeared in Ref. [1].

Appendix A: Current loops in external fields

A current loop in a uniform magnetic field \overleftrightarrow{b} experiences a torque, which is properly understood as a bivector quantity.¹ To calculate this, we must first define the magnetic moment bivector of a current flowing along the closed curve C : $\overleftrightarrow{\mu} \equiv I\overleftrightarrow{a}$. Here \overleftrightarrow{a} is the curve's directed

area: for a planar loop, this is just a bivector whose magnitude is the area and whose orientation matches the flow of current around the curve. More generally, \overleftrightarrow{a} is computed as a sum of infinitesimal bivector areas $d\overleftrightarrow{a}$ that form a surface \mathcal{S} bounded by closed curve C :²³

$$\overleftrightarrow{a} = \int_{\mathcal{S}} d\overleftrightarrow{a} = \frac{1}{2} \oint_C \vec{r} \wedge d\vec{\ell} \quad , \text{ or in components,} \quad (\text{A1})$$

$$a_{ij} = \frac{1}{2} \oint_C (r_i dl_j - r_j dl_i) = \oint_C r_i dl_j \quad . \quad (\text{A2})$$

Any surface \mathcal{S} bounded by C will yield the same \overleftrightarrow{a} . The final equality in Eq. (A2) uses integration by parts, where $d\vec{\ell}$ is just $d\vec{r}$ restricted to lie along the curve.

We now consider the torque $d\overleftrightarrow{\tau}$ acting on each segment $d\vec{\ell}$ of the wire. Infinitesimally, $d\overleftrightarrow{\tau} = \vec{r} \wedge d\vec{F}$, where the force is given by Eq. (23). Then

$$\overleftrightarrow{\tau} = \oint_C \vec{r} \wedge (I\overleftrightarrow{b} \cdot d\vec{\ell}) = I \oint_C \vec{r} \wedge (\overleftrightarrow{b} \cdot d\vec{\ell}) \quad , \quad (\text{A3})$$

or after a few lines of straightforward index notation,²⁴

$$\overleftrightarrow{\tau} = \overleftrightarrow{b} \cdot \overleftrightarrow{\mu} - \overleftrightarrow{\mu} \cdot \overleftrightarrow{b} \equiv \overleftrightarrow{b} \boxtimes \overleftrightarrow{\mu} \quad . \quad (\text{A4})$$

In this last step we have defined the notation \boxtimes for the *bivector cross product* or *commutator product* of two bivectors producing a bivector.²⁵ (Note the reversed order compared with $\vec{\tau} = \vec{\mu} \times \vec{B}$.)

This bivector cross product shares many features with the familiar vector cross product, including antisymmetry: $\overleftrightarrow{m} \boxtimes \overleftrightarrow{\ell} = -\overleftrightarrow{\ell} \boxtimes \overleftrightarrow{m}$. Its geometric meaning is interesting (essentially a wedge product extended into a third dimension: creating a parallelogram tube by placing bivector tiles edge to edge: see Fig. 12 in Appendix C) but sufficiently complicated that it's probably not worth sharing it with students. For calculations, an identity²⁶ allows us to simplify commutator products of unit bivectors:

$$\begin{aligned} (\hat{x} \wedge \hat{y}) \boxtimes (\hat{y} \wedge \hat{z}) &= \hat{x} \wedge \hat{z} & (\hat{x} \wedge \hat{y}) \boxtimes (\hat{z} \wedge \hat{y}) &= -\hat{x} \wedge \hat{z} \\ (\hat{x} \wedge \hat{y}) \boxtimes (\hat{z} \wedge \hat{x}) &= \hat{y} \wedge \hat{z} & (\hat{y} \wedge \hat{z}) \boxtimes (\hat{x} \wedge \hat{z}) &= -\hat{y} \wedge \hat{x} \\ (\hat{x} \wedge \hat{y}) \boxtimes (\hat{x} \wedge \hat{y}) &= 0 & & \text{etc.} \end{aligned} \quad (\text{A5})$$

The pattern is straightforward: reverse the wedge products as necessary to put the matching coordinate unit vectors next to each other, adding a minus sign for each reversal, and the result is the wedge product of the remaining two unit vectors.

Finally, the energy of a magnetic dipole $\overleftrightarrow{\mu}$ (like a current loop) in a magnetic field \overleftrightarrow{b} can be expressed as

$$\begin{aligned} U &= -\frac{1}{2} \overleftrightarrow{\mu} : \overleftrightarrow{b} \equiv -\frac{1}{2} \sum_{i,j} \mu_{ij} b_{ij} = -|\overleftrightarrow{\mu}| |\overleftrightarrow{b}| \cos \theta \quad (\text{A6}) \\ &= -(\mu_{xy} b_{xy} + \mu_{yz} b_{yz} + \mu_{zx} b_{zx}) \quad . \end{aligned}$$

This is the "double dot product" of bivectors, often denoted by a colon, where θ is the angle between the two bivector planes.

Appendix B: More advanced material

1. The vector potential

Although the topic goes beyond the introductory material that has been the focus above, it is worth briefly noting how the magnetic vector potential \vec{A} fits into the bivector formalism. The answer is straightforward: the vector potential remains an ordinary vector, and all of its usual properties and relationships remain unchanged.

The one necessary adjustment is its relationship to the magnetic field. Rather than the traditional curl $\vec{B} = \nabla \times \vec{A}$ we use the *bivector curl* (or *exterior derivative*):

$$\overleftrightarrow{b} = \nabla \wedge \vec{A} \quad \text{or in components,} \quad (\text{B1})$$

$$b_{ij} = \partial_i A_j - \partial_j A_i \quad , \quad (\text{B2})$$

where ∂_i is a shorthand for $\frac{\partial}{\partial x_i}$. Under the relationship defined in Eq. (3) these are precisely the components of the curl of \vec{A} , structured as a bivector.

The proper intuition for this bivector curl is precisely the same as for the usual curl, except that the resulting bivector orientation directly reflects the rotational quality of the vector field (rather than requiring a right-hand rule step to transform it to an axis of rotation). In that regard, the standard vector potential relationship $\vec{A} = \frac{\mu_0 I}{4\pi} \int (\frac{d\vec{\ell}}{r})$ (for currents that vanish at infinity) may give insight into the form of the bivector field due to moving charges. Roughly speaking, a moving charge drags \vec{A} along with it, diminishing with distance. Thus, the charge produces a bivector curl \overleftrightarrow{b} in the current-distance plane, with its orientation paralleling the current on the nearer side.

2. Energy and momentum of the field

The expression for the energy density of the magnetic field is essentially the same in bivector language as for vectors:

$$u_m = \frac{1}{2\mu_0} |\overleftrightarrow{b}|^2 \quad . \quad (\text{B3})$$

But the Poynting vector that represents the flow of energy in an electromagnetic field (and equivalently, the field's momentum) requires modification:

$$\vec{S} = \frac{1}{\mu_0} \overleftrightarrow{b} \cdot \vec{E} \quad . \quad (\text{B4})$$

This has the same form as Eq. (14) ($\vec{F}_m = q \overleftrightarrow{b} \cdot \vec{v}$), so we can base our intuition on Figure 9. Electromagnetic fields transport energy only when the electric field has a component in the bivector plane. When that is true, the flow of energy is also in the bivector plane, perpendicular to the electric field.

Naturally, in relativistic language there is nothing new to say at all: relativistic treatments of electromagnetic

energy and momentum are already formulated in terms of $F^{\mu\nu}$. The key result is that the stress-energy-momentum tensor is given by $T^{\mu\nu} = \frac{1}{\mu_0} (F^{\mu\rho} F^\nu{}_\rho - \frac{1}{4} \eta^{\mu\nu} F^{\rho\lambda} F_{\rho\lambda})$.

3. Extra dimensions

As we have seen, the traditional pseudovector approach to magnetism is only defined in three dimensions (where a right-hand rule is meaningful), while the bivector formalism remains natural in two-dimensional examples and in four-dimensional space-time. In fact, if we imagine a world with d dimensions of space (as inspired for example by string theory), the bivector description and equations that we have seen continue to provide a meaningful and intuitive description of magnetic phenomena.

Taking 4-dimensional space as an example, the electric field is described by a 4-component vector $\vec{E} = (E_x, E_y, E_z, E_w)$. But as a bivector, the magnetic field requires a 4×4 antisymmetric matrix:

$$\overleftrightarrow{b} = \begin{pmatrix} 0 & b_{xy} & b_{xz} & b_{xw} \\ -b_{xy} & 0 & b_{yz} & b_{yw} \\ -b_{xz} & -b_{yz} & 0 & b_{zw} \\ -b_{xw} & -b_{yw} & -b_{zw} & 0 \end{pmatrix} \quad . \quad (\text{B5})$$

Because of the antisymmetry, this has $\binom{d}{2} = \frac{d(d-1)}{2} = 6$ independent components: too many to map into a 4-dimensional vector.

Understanding bivectors geometrically in four or more dimensions requires some care. In d dimensions, it is possible to represent any bivector as a sum of not more than $d/2$ tiles (rounded down), each corresponding to a wedge product of two vectors. (A proof is sketched in Appendix C of Ref. [1].) This means that every bivector in three dimensions can be represented as a single tile (for example, a sum like $\hat{x} \wedge \hat{y} + \hat{y} \wedge \hat{z}$ can be written as $(\hat{x} - \hat{z}) \wedge \hat{y}$), but in four dimensions most require two tiles (e.g. $\hat{x} \wedge \hat{y} + \hat{z} \wedge \hat{w}$ cannot be simplified). If all the dimensions are spacelike, we can even require that all of the vectors in those wedge products be mutually orthogonal, so the tiles are fully orthogonal as well.

As an explicit example, consider a point particle of charge $q = 1 \mu\text{C}$ with velocity $\vec{v} = (9, 0, 20, -12) \text{ m/s}$ moving in a uniform magnetic field $\overleftrightarrow{b} = [4\hat{x} \wedge (\hat{y} + \hat{z}) - 3(\hat{z} - \hat{y}) \wedge \hat{w}] \text{ mT}$. (All four vectors in these two wedge products happen to be orthogonal.) Then according to Eq. (13), the force on the particle is

$$\vec{F} = \begin{pmatrix} 0 & 4 & 4 & 0 \\ -4 & 0 & 0 & 3 \\ -4 & 0 & 0 & -3 \\ 0 & -3 & 3 & 0 \end{pmatrix} \begin{pmatrix} 9 \\ 0 \\ 20 \\ -12 \end{pmatrix} \text{ nN} = \begin{pmatrix} 80 \\ -72 \\ 0 \\ 60 \end{pmatrix} \text{ nN} \quad . \quad (\text{B6})$$

This resulting force is perpendicular to the velocity, as usual: the particle will change direction but not speed, and we can expect that it will follow a path that traces simultaneous circles (at different rates) in the planes of the two tiles that constitute \overleftrightarrow{b} .

This may be easier to visualize if we first split the velocity into two pieces, each orthogonal to one of the two planes: $\vec{v} = \vec{v}_1 + \vec{v}_2 = (9, 10, 10) \text{ m/s} + (0, -10, 10, -12) \text{ m/s}$. Then \vec{v}_1 contributes a force of $\vec{F}_1 = (80, -36, -36, 0) \text{ nN}$ (in the plane of the first tile, as visualized in Fig. 9), and \vec{v}_2 contributes a force of $\vec{F}_2 = (0, -36, 36, 60) \text{ nN}$ (in the plane of the second tile). If we group the two resulting accelerations with their corresponding velocities, each piece of the overall velocity will remain in its corresponding plane as the system evolves in time.

Extending these results to $(d+1)$ -dimensional spacetime follows exactly the pattern established in Sec. V. The electric and magnetic fields combine into a $(d+1)$ -dimensional bivector. Its components form a $(d+1) \times (d+1)$ antisymmetric matrix whose top row (after $b^{tt} = 0$) corresponds to the electric field.

Appendix C: Bivector math reference

We collect here a number of formal results in bivector mathematics, with both algebraic and geometric interpretations. (A geometric interpretation of bivector addition can be found in Ref. [1].) For clarity, in this reference we will use the symbols \vec{U} , \vec{V} , and \vec{W} to refer to generic ordinary vectors (“polar vectors”), while the symbols \vec{L} , \vec{M} , and \vec{N} will refer to generic pseudovectors (“axial vectors”) whose bivector equivalents are $\overleftrightarrow{\ell}$, \overleftrightarrow{m} , and \overleftrightarrow{n} , respectively.

Here, we will relate pseudovector product equations to their bivector equivalents. The results are presented in index notation and involve the totally antisymmetric Levi-Civita symbol ϵ_{ijk} , where $\epsilon_{xyz} = +1$, $\epsilon_{yxz} = -1$, etc. As we will see, the final bivector forms do not involve ϵ_{ijk} at all. Although the derivations here are entirely in Cartesian three dimensional space for clarity, the final bivector results in index notation generalize directly to curved space in any dimension (where bivectors are antisymmetric rank-2 contravariant tensors).

In most cases, the equivalences can be derived using the identity

$$\sum_{i=1}^3 \epsilon_{ijk} \epsilon_{ibc} = \delta_{jb} \delta_{kc} - \delta_{jc} \delta_{kb} \quad , \quad (\text{C1})$$

though at times a more general identity is needed:

$$\begin{aligned} \epsilon_{ijk} \epsilon_{abc} &= \delta_{ia} \delta_{jb} \delta_{kc} + \delta_{ib} \delta_{jc} \delta_{ka} + \delta_{ic} \delta_{ja} \delta_{kb} \\ &\quad - \delta_{ia} \delta_{jc} \delta_{kb} - \delta_{ib} \delta_{ja} \delta_{kc} - \delta_{ic} \delta_{jb} \delta_{ka} \quad . \end{aligned} \quad (\text{C2})$$

For any pseudovector \vec{L} (in three dimensions), we can define a unique “dual” bivector $\overleftrightarrow{\ell}$ whose plane is normal to \vec{L} , whose magnitude (“area”: $|\overleftrightarrow{\ell}|$) is equal to the vector’s magnitude (“length”: $|\vec{L}|$), and whose orientation relates to the direction of \vec{L} by the right hand rule. The

matrix components ℓ_{ij} that describe this dual bivector are:

$$\ell_{ij} = \sum_{k=1}^3 \epsilon_{ijk} L_k \equiv \epsilon_{ijk} L_k \quad . \quad (\text{C3})$$

This second form illustrates the use of Einstein summation notation (used implicitly through the rest of this section) where repeated indices within a single term are assumed to be summed over all coordinates.²⁷ Explicitly in terms of components, this reads

$$\ell_{ij} = \begin{pmatrix} 0 & \ell_{xy} & -\ell_{zx} \\ -\ell_{xy} & 0 & \ell_{yz} \\ \ell_{zx} & -\ell_{yz} & 0 \end{pmatrix} = \begin{pmatrix} 0 & L_z & -L_y \\ -L_z & 0 & L_x \\ L_y & -L_x & 0 \end{pmatrix} \quad . \quad (\text{C4})$$

We can see that $\ell_{ji} = -\ell_{ij}$, because of the antisymmetry of ϵ_{ijk} . Comparing components between the two matrices makes the geometric significance clear: for example, the bivector component ℓ_{xy} in the xy -plane is perpendicular to the vector component L_z , with the same magnitude.

The relationship also works in the other direction, with a factor of a half to compensate for double counting (since each independent bivector component appears twice in the matrix):

$$L_i = \frac{1}{2} \epsilon_{ijk} \ell_{jk} = \begin{pmatrix} \ell_{yz} \\ \ell_{zx} \\ \ell_{xy} \end{pmatrix} \quad . \quad (\text{C5})$$

We begin with cross products, since that is where pseudovectors arise. The cross product of two ordinary vectors $\vec{L} = \vec{U} \times \vec{V}$ is expressed in index notation as

$$L_i = \epsilon_{ijk} U_j V_k \quad . \quad (\text{C6})$$

(One familiar example of this is the angular momentum of a point particle: $\vec{L} = \vec{r} \times \vec{p}$.) Using the definition in Eq. (C3) (after suitably relabeling summed indices), the symmetries of ϵ_{ijk} , and the identity (C1), we find

$$\begin{aligned} \ell_{ij} &= \epsilon_{ijk} L_k = \epsilon_{ijk} (\epsilon_{kbc} U_b V_c) = (\epsilon_{kij} \epsilon_{kbc}) U_b V_c \\ &= (\delta_{ib} \delta_{jc} - \delta_{ic} \delta_{jb}) U_b V_c = U_i V_j - U_j V_i \quad . \end{aligned} \quad (\text{C7})$$

This is the definition of the wedge product:

$$\boxed{\vec{L} = \vec{U} \times \vec{V} \quad \longleftrightarrow \quad \overleftrightarrow{\ell} = \vec{U} \wedge \vec{V}} \quad . \quad (\text{C8})$$

This can be visualized as explained in Figure 10. Like the cross product, this is antisymmetric: $\vec{U} \wedge \vec{V} = -\vec{V} \wedge \vec{U}$.

If vectors are expressed in a basis of coordinate unit vectors, $\vec{U} = U_x \hat{x} + U_y \hat{y} + U_z \hat{z}$, then bivectors will be naturally expressed in a basis of coordinate unit bivectors: $\overleftrightarrow{\ell} = \ell_{xy} \hat{x} \wedge \hat{y} + \ell_{yz} \hat{y} \wedge \hat{z} + \ell_{zx} \hat{z} \wedge \hat{x}$. It’s important to recognize that an expression like this should include *either* an $\hat{x} \wedge \hat{y}$ term or a $\hat{y} \wedge \hat{x}$ term but not both: because $\hat{y} \wedge \hat{x} = -\hat{x} \wedge \hat{y}$, including both terms would be redundant.




FIG. 10. In the wedge product $\vec{\ell} = \vec{U} \wedge \vec{V}$, the two vectors define a parallelogram of area $|\vec{\ell}| = |\vec{U}|h = |\vec{U}||\vec{V}|\sin\theta$ with a fixed attitude in space. This figure illustrates two ways to visualize its orientation: either as the direction that rotates the first vector toward the second tail-to-tail, or by following the first vector tip-to-tail with the second around the edges.




FIG. 11. Finding the (dot) product of a vector \vec{U} with a bivector $\vec{\ell}$ is a two-step process. First, project the vector into the plane of the bivector, and then rotate it 90° in the tile's orientation direction. The resulting magnitude is $|\vec{U}||\vec{\ell}|\cos\theta$, where θ is the angle between the vector and the bivector plane, and the $\cos\theta$ comes from the projection. (This matches the formula for cross product magnitude: if \vec{L} is the pseudovector corresponding to $\vec{\ell}$, then its angle from \vec{U} is $90^\circ - \theta$ and thus $|\vec{L} \times \vec{U}| = |\vec{L}||\vec{U}|\sin(90^\circ - \theta) = |\vec{L}||\vec{U}|\cos\theta$.)

Meanwhile, the cross product of a pseudovector and an ordinary vector is an ordinary vector, $\vec{V} = \vec{L} \times \vec{U}$, and can be expressed in index notation as

$$V_i = \epsilon_{ijk} L_j U_k = U_k (\epsilon_{kij} L_j) = U_k \ell_{ki} \quad . \quad (\text{C9})$$

(A familiar physical example of this is the magnetic force on a charged particle: $\vec{F} = q\vec{v} \times \vec{B}$, where the magnetic field \vec{B} is a pseudovector.) We can immediately recognize this as matrix multiplication of a row vector times a square matrix, which we will represent symbolically as a dot product:

$$\boxed{\vec{V} = \vec{L} \times \vec{U} \quad \longleftrightarrow \quad \vec{V} = \vec{U} \cdot \vec{\ell}} \quad . \quad (\text{C10})$$

This can be visualized as explained in Figure 11.²⁸ (Note that the order of the two terms has reversed.) Given the antisymmetry of $\vec{\ell}$, if we reinterpret \vec{U} as a column vector we can instead write the matrix product in the opposite order: $\vec{V} = -\vec{\ell} \cdot \vec{U}$. Performing the matrix multiplication often feels more familiar in this order.

For expressions written in terms of coordinate unit vectors, expanding this product will lead to terms of the form $\hat{x} \cdot (\hat{x} \wedge \hat{y})$. Using the triple product identity from




FIG. 12. The commutator product $\vec{m} \boxtimes \vec{\ell}$ of two tiles is non-zero if and only if their planes intersect along a line (with angle θ between them): geometrically, it is essentially a wedge product of tiles. Reshape the tiles as rectangles with unit length along the shared line (\vec{W}), so $\vec{m} = \vec{U} \wedge \vec{W}$ and $\vec{\ell} = \vec{W} \wedge \vec{V}$. Then form a “pipe” out of two copies of each as shown. The cross section of the pipe (e.g. the “end cap”) is the tile representing the commutator and is equal to $\vec{U} \wedge \vec{V}$: a parallelogram of area $|\vec{m}||\vec{\ell}|\sin\theta$ whose orientation follows from \vec{U} through the shared \vec{W} edge to \vec{V} and back around.

note **C**, $\vec{U} \cdot (\vec{V} \wedge \vec{W}) = (\vec{U} \cdot \vec{V})\vec{W} - (\vec{U} \cdot \vec{W})\vec{V}$, we find:

$$\begin{aligned} \hat{x} \cdot (\hat{x} \wedge \hat{y}) &= \hat{y} & \hat{y} \cdot (\hat{x} \wedge \hat{y}) &= -\hat{x} & \hat{z} \cdot (\hat{y} \wedge \hat{x}) &= 0 \\ (\hat{x} \wedge \hat{y}) \cdot \hat{x} &= -\hat{y} & (\hat{x} \wedge \hat{y}) \cdot \hat{y} &= \hat{x} & (\hat{y} \wedge \hat{x}) \cdot \hat{z} &= 0 \\ \hat{x} \cdot (\hat{y} \wedge \hat{z}) &= 0 & \hat{y} \cdot (\hat{y} \wedge \hat{z}) &= \hat{z} & \hat{z} \cdot (\hat{y} \wedge \hat{z}) &= -\hat{y} \\ & & & & & \vdots \end{aligned} \quad (\text{C11})$$

The pattern is easy to remember: the unit vector dot product will “cancel out” a matching unit vector in the wedge product, with a minus sign if the wedge product needs to be reversed to bring them side by side.

(In the remainder of this section, we will omit the derivations of each bivector expression: the methods are similar to those above, but the details can get tedious.)

Finally, we consider the cross product of two pseudovectors, whose result is another pseudovector: $\vec{N} = \vec{L} \times \vec{M}$. (One example of this is the torque on a magnetic moment in an external magnetic field: $\vec{\tau} = \vec{\mu} \times \vec{B}$.) Converting this to bivector language is messy: it starts like Eq. (C7) and uses Eqs. (C5) and (C2), with the result

$$n_{ij} = m_{ik} \ell_{kj} - \ell_{ik} m_{kj} \quad . \quad (\text{C12})$$

The result is recognizable as the matrix product of the two bivectors, antisymmetrized (again in opposite order):

$$\boxed{\vec{N} = \vec{L} \times \vec{M} \quad \longleftrightarrow \quad \vec{n} = \vec{m} \cdot \vec{\ell} - \vec{\ell} \cdot \vec{m} \equiv \vec{m} \boxtimes \vec{\ell}} \quad . \quad (\text{C13})$$

We can call this the *commutator product* (or the *bivector cross product*), since this operation is formally called the *commutator* of the two matrices. (The usual notation for a commutator is $[A, B] = AB - BA$.) Its definition implies that it is antisymmetric: $\vec{m} \boxtimes \vec{\ell} = -\vec{\ell} \boxtimes \vec{m}$. For “simple” bivectors that can each be represented by a single tile, this can be visualized as described in Figure 12.

If $\vec{m} = \vec{A} \wedge \vec{B}$ and $\vec{\ell} = \vec{U} \wedge \vec{V}$, then

$$\vec{m} \boxtimes \vec{\ell} = (\vec{A} \wedge \vec{B})(\vec{B} \cdot \vec{U}) - (\vec{A} \wedge \vec{U})(\vec{B} \cdot \vec{V}) \\ - (\vec{B} \wedge \vec{V})(\vec{A} \cdot \vec{U}) + (\vec{B} \wedge \vec{U})(\vec{A} \cdot \vec{V})$$

This allows us to simplify coordinate unit vector expressions like $(\hat{x} \wedge \hat{y}) \boxtimes (\hat{y} \wedge \hat{z})$:

$$\begin{aligned} (\hat{x} \wedge \hat{y}) \boxtimes (\hat{y} \wedge \hat{z}) &= \hat{x} \wedge \hat{z} & (\hat{x} \wedge \hat{y}) \boxtimes (\hat{z} \wedge \hat{x}) &= \hat{y} \wedge \hat{z} \\ (\hat{x} \wedge \hat{y}) \boxtimes (\hat{z} \wedge \hat{y}) &= -\hat{x} \wedge \hat{z} & (\hat{x} \wedge \hat{y}) \boxtimes (\hat{x} \wedge \hat{z}) &= -\hat{y} \wedge \hat{z} \\ (\hat{z} \wedge \hat{y}) \boxtimes (\hat{x} \wedge \hat{y}) &= -\hat{z} \wedge \hat{x} & (\hat{x} \wedge \hat{y}) \boxtimes (\hat{x} \wedge \hat{y}) &= 0 \\ & & & \vdots \end{aligned} \quad (C14)$$

Again the pattern is straightforward: reverse the wedge products as necessary to put the matching coordinate unit vectors next to each other, multiplying by -1 for each reversal, and the result is the wedge product of the remaining two unit vectors.

Having established the formulas for cross products involving pseudovectors, we next consider dot products. The dot product of two pseudovectors $\alpha = \vec{L} \cdot \vec{M}$ is a scalar; one example is the energy of a magnetic dipole in an external magnetic field. It can be written as

$$\alpha = L_i M_i = \frac{1}{2} \ell_{jk} m_{jk} \quad . \quad (C15)$$

As in previous equations, the factor of $\frac{1}{2}$ compensates for the duplication of entries in the two antisymmetric matrices. This sum over products of all matrix components is sometimes called the “double dot product” and is denoted by a colon:²⁹

$$\boxed{\alpha = \vec{L} \cdot \vec{M} \quad \longleftrightarrow \quad \alpha = \frac{1}{2} \vec{\ell} : \vec{m}} \quad . \quad (C16)$$

As with the vector dot product, we can interpret this as a measure of whether two bivectors are oriented in the same direction: orthogonal tiles have double dot product zero. We can use this to define the magnitude of a bivector: $|\vec{\ell}|^2 \equiv \frac{1}{2} \sum_{i,j=1}^3 \ell_{ij}^2$. If we use the antisymmetry of the bivector matrices, we can also interpret this in terms of the trace of the matrix product: $\alpha = -\frac{1}{2} \text{tr}(\vec{\ell} \cdot \vec{m})$. And if we express $\vec{m} = \vec{U} \wedge \vec{V}$, then $\alpha = \vec{U} \cdot \vec{\ell} \cdot \vec{V}$.

For expressions in terms of coordinate unit bivectors such as $\vec{\ell} = \ell_{xy} \hat{x} \wedge \hat{y} + \ell_{yz} \hat{y} \wedge \hat{z} + \ell_{zx} \hat{z} \wedge \hat{x}$ and similarly for \vec{m} , this boils down to $\alpha = \ell_{xy} m_{xy} + \ell_{yz} m_{yz} + \ell_{zx} m_{zx}$, exactly like the dot product of two (pseudo)vectors. (By writing the three terms explicitly and only including a single order for each coordinate pair, we have avoided the need for the factor of $\frac{1}{2}$.)

Geometrically, this is a measure of the degree to which the two planes have the same attitude and orientation in space. For two tiles whose planes overlap along a line (which includes any two tiles in three dimensions) the double dot product matches the dot product of their normal vectors: $\frac{1}{2} \vec{\ell} : \vec{m} = |\vec{\ell}| |\vec{m}| \cos \theta$, where θ is the angle




FIG. 13. The wedge product of a vector with a bivector, $\vec{U} \wedge \vec{\ell}$ (shown at left), can be visualized as an oriented three-dimensional volume formed by extruding the bivector tile along the vector’s direction. If the bivector is a wedge product $\vec{\ell} = \vec{V} \wedge \vec{W}$, this defines the triple product $\vec{U} \wedge \vec{V} \wedge \vec{W}$. If we choose right-handed coordinates, the component $\phi \equiv \Phi_{xyz}$ is positive if the bivector tile’s orientation appears counterclockwise from inside the region (as shown at left) and negative if it appears clockwise from inside (as with $-\vec{U} \wedge \vec{\ell}$ at right).

between the planes. More generally in higher dimensions (where two planes may only overlap at a point), the double dot product equals zero if *any* vector in one tile is perpendicular to the other tile. The precise geometric meaning in higher dimensions seems complicated: considering the form $\vec{U} \cdot \vec{\ell} \cdot \vec{V}$ in light of Figure 11, we are projecting \vec{U} into the plane of $\vec{\ell}$, multiplying it by the bivector magnitude, rotating it 90° , and then taking the dot product with \vec{V} .

Finally, the dot product of an ordinary vector and a pseudovector $\phi = \vec{U} \cdot \vec{L}$ is more subtle to understand, because the result ϕ is a “pseudoscalar” rather than an ordinary scalar:

$$\begin{aligned} \phi &= U_i L_i = \frac{1}{2} \epsilon_{ijk} U_i \ell_{jk} \\ &= U_x \ell_{yz} + U_y \ell_{zx} + U_z \ell_{xy} \quad . \end{aligned} \quad (C17)$$

Every term contains all three spatial coordinates: there are no free indices, just like a scalar quantity. But like a pseudovector, under a reflection like $x \rightarrow -x$ all three terms change sign, which a true scalar would not. (An example of this is the electromagnetic invariant $\vec{E} \cdot \vec{B}$.)

The appropriate interpretation (which correctly generalizes to higher dimensions) is not a scalar, but the wedge product of \vec{U} with $\vec{\ell}$:

$$\boxed{\phi = \vec{U} \cdot \vec{L} \quad \longleftrightarrow \quad \Phi_{(3)} = \vec{U} \wedge \vec{\ell}} \quad (C18a)$$

$$\Phi_{ijk} = U_i \ell_{jk} + U_j \ell_{ki} + U_k \ell_{ij} \quad . \quad (C18b)$$

(This is symmetric: $\vec{U} \wedge \vec{\ell} = \vec{\ell} \wedge \vec{U}$.) This is a *trivector*: a totally antisymmetric rank-3 tensor. As shown in Figure 13, this can be visualized as an (oriented) region of 3D space, with the bivector tile $\vec{\ell}$ as its base and the vector \vec{U} showing how it “extrudes” into the third dimension.

If the bivector is a wedge product $\vec{\ell} = \vec{V} \wedge \vec{W}$, this defines the “triple product” of (true) vectors: $\vec{U} \wedge \vec{V} \wedge \vec{W}$. By convention, the pseudoscalar is defined to equal the specific component $\phi \equiv \Phi_{xyz}$ of the trivector: the coefficient of $\hat{x} \wedge \hat{y} \wedge \hat{z}$. (In a right-handed coordinate system, the sign

of ϕ is positive if the bivector's orientation looks counter-clockwise when viewed from inside the parallelepiped.)

Because Equation (C18b) is totally antisymmetric in i , j , and k , it is zero unless the three indices are different. In three dimensions, this means that Eq. (C17) is the only independent term: that's why it looks like a scalar. But in d dimensions, there are $\binom{d}{3} = \frac{1}{3!}d(d-1)(d-2)$ independent ways of choosing three coordinate labels out of d , so that is the number of components.

Replacing pseudovectors with bivectors opens one more possible type of product that is not relevant in three dimensions: the wedge product of two bivectors $\overleftrightarrow{\ell} \wedge \overleftrightarrow{m}$. This is a totally antisymmetric rank-4 tensor (a “quadvec-

tor”?), and with four antisymmetrized coordinate indices it is guaranteed to be zero in three dimensions. The explicit coordinate form can be written:

$$\overleftrightarrow{\ell} \wedge \overleftrightarrow{m} \rightarrow \ell_{ij}m_{kl} + \ell_{ik}m_{lj} + \ell_{il}m_{jk} + \ell_{jk}m_{il} + \ell_{jl}m_{ki} + \ell_{kl}m_{ij}. \quad (\text{C19})$$

This could be imagined as an oriented chunk of 4D space. This does arise in physics: as noted earlier, the electromagnetic invariant $\vec{E} \cdot \vec{B}$ is a pseudoscalar, and in relativistic 4D spacetime a pseudoscalar corresponds to a quadvector. In this case, it arises from the wedge product of the electromagnetic field tensor (a four-bivector) with itself: $\overleftrightarrow{F} \wedge \overleftrightarrow{F}$. This zero if \overleftrightarrow{F} is a “simple” bivector (i.e. if it can be represented as a single tile).

-
- [1] S. Jensen and J. Poling, “Teaching rotational physics with bivectors,” [arXiv:2207.03560](https://arxiv.org/abs/2207.03560). (To appear in the American Journal of Physics).
- [2] T. Deprez, S. E. Gijzen, J. Deprez, and M. De Cock, “Investigating student understanding of cross products in a mathematical and two electromagnetism contexts,” *Phys. Rev. Phys. Educ. Res.* **15** (Sep, 2019) 020132.
- [3] M. B. Kustusch, “Assessing the impact of representational and contextual problem features on student use of right-hand rules,” *Phys. Rev. Phys. Educ. Res.* **12** (Jan, 2016) 010102, [arXiv:1507.02364](https://arxiv.org/abs/1507.02364).
- [4] J. Guisasola, J. M. Almudí, and J. L. Zubimendi, “Difficulties in learning the introductory magnetic field theory in the first years of university,” *Science Education* **88** no. 3, (2004) 443–464.
- [5] D. P. Maloney, T. L. O’Kuma, C. J. Hieggelke, and A. Van Heuvelen, “Surveying students’ conceptual knowledge of electricity and magnetism,” *American Journal of Physics* **69** no. S1, (07, 2001) S12–S23.
- [6] T. M. Scaife and A. F. Heckler, “Student understanding of the direction of the magnetic force on a charged particle,” *American Journal of Physics* **78** no. 8, (08, 2010) 869–876.
- [7] T. M. Scaife and A. F. Heckler, “Interference between electric and magnetic concepts in introductory physics,” *Phys. Rev. ST Phys. Educ. Res.* **7** (Mar, 2011) 010104.
- [8] A. Z. Petrov, “Klassifikatsiya prostranstv opredelyayushchikh polya tyagoteniya,” *Uch. Zapiski Kazan. Gos. Univ.* **114** no. 8, (1954) 55–69.
- [9] A. Z. Petrov, “The classification of spaces defining gravitational fields,” *Gen. Rel. Grav.* **32** no. 8, (2000) 1665–1685. (English translation of Petrov’s 1954 paper.).
- [10] A. Trautman, “Einstein-Cartan theory,” in *Encyclopedia of Mathematical Physics*, J.-P. Francoise, G. Naber, and Tsou S.T., eds., vol. 2, pp. 189–195. Elsevier, 6, 2006. [arXiv:gr-qc/0606062](https://arxiv.org/abs/gr-qc/0606062).
- [11] C. Doran and A. Lasenby, *Geometric Algebra for Physicists*. Cambridge University Press, Cambridge, 2003.
- [12] S. F. Gull, A. N. Lasenby, and C. J. L. Doran., “Imaginary numbers are not real - the geometric algebra of spacetime,” *Found. Phys.* **23** no. 9, (1993) 1175–1201.
- [13] D. Hestenes, “Oersted medal lecture 2002: Reforming the mathematical language of physics,” *American Journal of Physics* **71** no. 2, (2003) 104–121.
- [14] T. G. Vold, “An introduction to geometric algebra with an application in rigid body mechanics,” *American Journal of Physics* **61** no. 6, (1993) 491–504.
- [15] T. G. Vold, “An introduction to geometric calculus and its application to electrodynamics,” *American Journal of Physics* **61** no. 6, (1993) 505–513.
- [16] The Wikipedia entry for bivectors is well-written (<https://en.wikipedia.org/wiki/Bivector>), but even it focuses almost exclusively on geometric algebra.
- [17] D. R. Conant and W. A. Beyer, “Generalized pythagorean theorem,” *The American Mathematical Monthly* **81** no. 3, (1974) 262–265.
- [18] The general principle echos the “BAC-CAB” identity: $(\vec{u} \wedge \vec{v}) \cdot \vec{w} = \vec{u}(\vec{v} \cdot \vec{w}) - \vec{v}(\vec{u} \cdot \vec{w})$ and $\vec{w} \cdot (\vec{u} \wedge \vec{v}) = (\vec{w} \cdot \vec{u})\vec{v} - (\vec{w} \cdot \vec{v})\vec{u}$.
- [19] Lorentz transformations of four-vectors can be written as a matrix product: $U' = \Lambda U$. In that language, a four-bivector transforms as $\overleftrightarrow{b}' = \Lambda \overleftrightarrow{b} \Lambda^T$. These transformations precisely reproduce the Lorentz transformations of \vec{E} and \vec{B} .
- [20] This process of “dimensional reduction” in which an antisymmetric tensor in d dimensions splits into an antisymmetric tensor plus a vector when one dimension is singled out and the system is described in $d - 1$ dimensions arises routinely in theories of physics in extra dimensions.
- [21] The author is happy to share the Mathematica code used to generate figures in this article, but it is not (yet) clean or robust enough for public consumption.
- [22] S. Jensen, “Maxwell’s equations and bivector calculus.” (In preparation).
- [23] The formula at the end of Eq. (A1) results from choosing S as the cone with tip at the origin and C as its base. Each segment $d\vec{\ell}$ is the base of a triangle whose tip is at the origin and is exactly half of the bivector tile $\vec{r} \wedge d\vec{\ell}$.
- [24] Each dot product is a matrix multiplication, or more precisely, tensor index contraction on one index. In this work, we will always denote this with a (single) dot product like $\overleftrightarrow{b} \cdot \overleftrightarrow{\mu}$. In geometric algebra the convention is different: there, roughly speaking, a (single) dot product denotes contraction on as many indices as possible. Here, when we need to contract both bivector indices as in

Eq. (A6), our notation will be the “double dot product”.

- [25] The symbol \boxtimes is meant to evoke a cross product applied to bivector tiles. The traditional notation for the commutator of two matrices is $\overleftrightarrow{\tau} = [\overleftrightarrow{b}, \overleftrightarrow{\mu}]$, but a notation that looks like a product seems helpful.
- [26] If $\overleftrightarrow{m} = \vec{A} \wedge \vec{B}$ and $\overleftrightarrow{\ell} = \vec{U} \wedge \vec{V}$, then $\overleftrightarrow{m} \boxtimes \overleftrightarrow{\ell} = (\vec{A} \wedge \vec{V})(\vec{B} \cdot \vec{U}) - (\vec{A} \wedge \vec{U})(\vec{B} \cdot \vec{V}) - (\vec{B} \wedge \vec{V})(\vec{A} \cdot \vec{U}) + (\vec{B} \wedge \vec{U})(\vec{A} \cdot \vec{V})$.
- [27] For simplicity, we assume spacelike Cartesian orthonormal coordinates: the distinction between covariant and contravariant indices can be ignored.
- [28] One way of understanding the process of projection and rotation in Figure 11 begins by expressing the bivector as a wedge product of two vectors: $\overleftrightarrow{\ell} = \vec{F} \wedge \vec{G}$, so $\ell_{ij} = F_i G_j - G_i F_j$. Then $\vec{U} \cdot \overleftrightarrow{\ell} = (U_i F_i) G_j - (U_i G_i) F_j$: any component of \vec{U} in the direction of \vec{F} gets rotated to point along \vec{G} , and any component along \vec{G} gets rotated

to point along $-\vec{F}$. This rotates the projection in the same sense that rotates \vec{F} toward \vec{G} .

- [29] In this work, the (single) dot product always represents matrix multiplication, or more precisely, tensor index contraction on one index. The double dot product notation used here for contraction on two indices is more common in engineering than in physics: in the traditional physics curriculum, students see second rank tensors only rarely before they learn index notation, at which point these shorthands become unnecessary. In geometric algebra the convention is different: there, roughly speaking, a (single) dot product denotes contraction on as many indices as possible, so the double index contraction of two bivectors would be represented by a single dot product.