

# Comparison of Methods for Rotating a Point in $\mathbb{R}^3$ : A Case Study

Tom Verhoeff

Dept. Math. & CS, Eindhoven University of Technology, The Netherlands  
[T.Verhoeff@tue.nl](mailto:T.Verhoeff@tue.nl)

11 Feb 2025; updated 05 Apr 2025

## Abstract

This article presents and compares four approaches for computing the rotation of a point about an axis by an angle in  $\mathbb{R}^3$ . We illustrate these methods by computing, by hand, the rotation of point  $P = (1, 0, 1)^T$  about axis  $\mathbf{a} = (1, 1, 1)^T$  by angle  $\theta = 60^\circ$  (following the right-hand rule). The four methods considered are:

1. An *ad hoc* geometric method exploiting a symmetry in the situation.
2. A projection method that sets up a new coordinate system using the dot and cross products.
3. A matrix method which rotates the standard basis and uses matrix-vector multiplication.
4. A Geometric (Clifford) Algebra method that represents the rotation as a double reflection via a rotor.

All methods yield the same exact result:  $P' = \left(\frac{4}{3}, \frac{1}{3}, \frac{1}{3}\right)^T$ .

## Introduction

This article was written for the *LinkedIn* group *Pre-University Geometric Algebra* [5], to compare various methods to rotate a vector in  $\mathbb{R}^3$ , including via Geometric (Clifford) Algebra. We assume some prior familiarity with vectors in  $\mathbb{R}^3$ , in particular, the dot product and cross product, but all definitions will be given.

Rotations in three-dimensional space occur in many areas of science and engineering. In this document we examine four methods for performing such a rotation “by hand”. We shall use as our running example (see Fig. 1) the rotation of

$$P = (1, 0, 1)^T$$

about the line in the direction

$$\mathbf{a} = (1, 1, 1)^T$$

by an angle  $\theta = 60^\circ$  (using the right-hand rule).

Although the particular configuration allows some shortcuts, our aim is to compare the underlying concepts and the amount of work involved in each approach.




Figure 1: Rotation problem: Rotate given point  $P$  about given axis  $\mathbf{a}$  by given angle  $\theta$ .

## Method 1: *Ad Hoc* Approach Exploiting Symmetry

Observe (see Fig. 2) that the plane perpendicular to the axis  $\mathbf{a} = (1, 1, 1)^T$  and containing  $P = (1, 0, 1)^T$  is given by

$$x + y + z = 2,$$

since

$$1 + 0 + 1 = 2.$$

It turns out that the points

$$P = (1, 0, 1)^T, \quad P_2 = (1, 1, 0)^T, \quad P_3 = (0, 1, 1)^T$$

all lie in this plane and, moreover, one may verify that

$$\|P - P_2\| = \|P_2 - P_3\| = \|P_3 - P\| = \sqrt{2}.$$

Thus these three points form an *equilateral triangle*. Its centroid (which, for an equilateral triangle, is also the circumcenter) is

$$Q = \left( \frac{1+0+1}{3}, \frac{1+1+0}{3}, \frac{0+1+1}{3} \right)^T = \left( \frac{2}{3}, \frac{2}{3}, \frac{2}{3} \right)^T.$$

Since  $Q$  lies on axis  $\mathbf{a}$ , this point  $Q$  is also the projection of  $P$  onto  $\mathbf{a}$  (also see Method 2 below). Since the vertices of the triangle are separated by central angles of  $120^\circ$ , the symmetric configuration can be exploited to “read off” a  $60^\circ$  rotation about the axis. Namely,  $P'$  ends up on the line from  $Q$  to the midpoint  $M$  of  $PP_2$ , such that  $\|P' - Q\| = \|P - Q\| = \sqrt{\frac{2}{3}}$ . A short calculation shows that

$$M = \left( \frac{1+1}{2} + \frac{0+1}{2} + \frac{1+0}{2} \right)^T = \left( 1, \frac{1}{2}, \frac{1}{2} \right)^T$$

and hence

$$P' = Q + (M - Q) \frac{\|P - Q\|}{\|M - Q\|} = \left(\frac{4}{3}, \frac{1}{3}, \frac{1}{3}\right)^T.$$




Figure 2: Method 2: *Ad hoc* approach exploiting symmetry.

For further discussion of symmetric configurations in space, see, for example, [1].

## Method 2: Projection and a New Coordinate System

This method works for arbitrary rotation axes, rotation angles, and points. See Fig. 3.




Figure 3: Method 2: Projection and new coordinate system (the latter is not to scale).

### Step 1. Projecting $P$ onto $\mathbf{a}$

The projection of  $P$  onto  $\mathbf{a}$  is given by

$$Q = \frac{P \cdot \mathbf{a}}{\mathbf{a} \cdot \mathbf{a}} \mathbf{a}.$$

Recall that the *dot product* for vectors  $\mathbf{v} = (v_x, v_y, v_z)$  and  $\mathbf{w} = (w_x, w_y, w_z)$  is

$$\mathbf{v} \cdot \mathbf{w} = v_x w_x + v_y w_y + v_z w_z,$$

and geometrically

$$\mathbf{v} \cdot \mathbf{w} = \|\mathbf{v}\| \|\mathbf{w}\| \cos \psi,$$

where  $\psi$  is the angle between  $\mathbf{v}$  and  $\mathbf{w}$ . For

$$P = (1, 0, 1)^T \quad \text{and} \quad \mathbf{a} = (1, 1, 1)^T$$

we have

$$P \cdot \mathbf{a} = 1 + 0 + 1 = 2, \quad \mathbf{a} \cdot \mathbf{a} = 1 + 1 + 1 = 3,$$

so that

$$Q = \frac{2}{3}(1, 1, 1)^T = \left(\frac{2}{3}, \frac{2}{3}, \frac{2}{3}\right)^T.$$

### Step 2. Setting up a New Coordinate System in the Plane

The vector

$$P - Q = \left(1 - \frac{2}{3}, 0 - \frac{2}{3}, 1 - \frac{2}{3}\right)^T = \left(\frac{1}{3}, -\frac{2}{3}, \frac{1}{3}\right)^T$$

lies in a plane perpendicular to axis  $\mathbf{a}$ . We choose this direction as our new  $X$ -axis:

$$\mathbf{b} = \frac{(P - Q)^T}{\|P - Q\|} = \sqrt{\frac{2}{3}} \left(\frac{1}{3}, -\frac{2}{3}, \frac{1}{3}\right)^T.$$

Next, we take the new  $Z$ -axis to be in the direction of  $\mathbf{a}$ , i.e.,

$$\mathbf{n} = \frac{\mathbf{a}}{\|\mathbf{a}\|} = \frac{1}{\sqrt{3}}(1, 1, 1)^T,$$

and define the  $Y$ -axis via the *cross product*:

$$\mathbf{c} = \mathbf{n} \times \mathbf{b}.$$

For vectors  $\mathbf{v} = (v_x, v_y, v_z)$  and  $\mathbf{w} = (w_x, w_y, w_z)$  the cross product is defined as

$$\mathbf{v} \times \mathbf{w} = (v_y w_z - v_z w_y, v_z w_x - v_x w_z, v_x w_y - v_y w_x),$$

and geometrically by  $\mathbf{v} \times \mathbf{w}$  is perpendicular to both  $\mathbf{v}$  and  $\mathbf{w}$ , using the right-hand rule for direction, and  $\|\mathbf{v} \times \mathbf{w}\| = \|\mathbf{v}\| \|\mathbf{w}\| \sin \phi$  where  $\phi$  is the angle between  $\mathbf{v}$  and  $\mathbf{w}$ .

A short calculation shows

$$\mathbf{n} \times \mathbf{b} = \frac{1}{\sqrt{3}}(1, 1, 1)^T \times \sqrt{\frac{2}{3}} \left(\frac{1}{3}, -\frac{2}{3}, \frac{1}{3}\right)^T = \left(\frac{\sqrt{2}}{3}, 0, -\frac{\sqrt{2}}{3}\right)^T.$$

### Step 3. Rotating in the New Coordinates

Express the rotated vector (with respect to the center  $Q$ ) as

$$P' - Q = \cos 60^\circ \mathbf{b} + \sin 60^\circ \mathbf{c}.$$

With  $\cos 60^\circ = \frac{1}{2}$  and  $\sin 60^\circ = \frac{\sqrt{3}}{2}$ , we get

$$P' - Q = \frac{1}{2} \left( \frac{1}{3}, -\frac{2}{3}, \frac{1}{3} \right)^T + \frac{\sqrt{3}}{2} \left( \frac{1}{\sqrt{3}}, 0, -\frac{1}{\sqrt{3}} \right)^T.$$

A short computation gives

$$P' - Q = \left( \frac{1}{6} + \frac{1}{2}, -\frac{1}{3} + 0, \frac{1}{6} - \frac{1}{2} \right)^T = \left( \frac{2}{3}, -\frac{1}{3}, -\frac{1}{3} \right)^T.$$

Thus,

$$P' = Q + (P' - Q) = \left( \frac{2}{3}, \frac{2}{3}, \frac{2}{3} \right)^T + \left( \frac{2}{3}, -\frac{1}{3}, -\frac{1}{3} \right)^T = \left( \frac{4}{3}, \frac{1}{3}, \frac{1}{3} \right)^T.$$

This method is also easy to apply for other rotation angles  $\theta$ :

$$P' = Q + \cos \theta \mathbf{b} + \sin \theta \mathbf{c}.$$

### Method 3: The Matrix Approach

When one needs to rotate various points  $P = (x, y, z)^T$ , one can write each such point as a linear combination of the basis vectors  $\mathbf{e}_1, \mathbf{e}_2, \mathbf{e}_3 = (1, 0, 0)^T, (0, 1, 0)^T, (0, 0, 1)^T$ :

$$P = x \mathbf{e}_1 + y \mathbf{e}_2 + z \mathbf{e}_3$$

Using Method 2, each basis vector can be rotated to yield vectors  $\mathbf{e}'_1, \mathbf{e}'_2, \mathbf{e}'_3$  (see Fig. 4). Since rotation about an axis through the origin is a linear operation, we now have

$$P' = x \mathbf{e}'_1 + y \mathbf{e}'_2 + z \mathbf{e}'_3$$

The latter is often written as a matrix-vector multiplication:

$$P' = (\mathbf{e}'_1 \ \mathbf{e}'_2 \ \mathbf{e}'_3) \begin{pmatrix} x \\ y \\ z \end{pmatrix}$$

where the rotated basis vectors are written as columns.

Any rotation about a fixed axis through the origin can be written as a matrix. One standard formula for the rotation matrix about a unit vector

$$\mathbf{n} = (n_x, n_y, n_z)$$

by an angle  $\theta$  is

$$R_{\text{mat}} = \cos \theta I + (1 - \cos \theta) \mathbf{n} \mathbf{n}^T + \sin \theta [\mathbf{n}]_{\times},$$




Figure 4: Method 3: Using a rotation matrix based on rotated basis vectors.

where  $I$  is the identity matrix,  $\mathbf{n}\mathbf{n}^T$  is the *outer product*, and

$$[\mathbf{n}]_{\times} = \begin{pmatrix} 0 & -n_z & n_y \\ n_z & 0 & -n_x \\ -n_y & n_x & 0 \end{pmatrix}$$

is the skew-symmetric matrix corresponding to the cross product (see, e.g., [4] for further details on the derivation of this formula).

For our case, since  $\mathbf{a} = (1, 1, 1)^T$  we have

$$\mathbf{n} = \frac{1}{\sqrt{3}}(1, 1, 1)^T,$$

and with  $\theta = 60^\circ$  (so that  $\cos 60^\circ = \frac{1}{2}$  and  $\sin 60^\circ = \frac{\sqrt{3}}{2}$ ) the entries can be computed to yield

$$R_{\text{mat}} = \frac{1}{2} \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{pmatrix} + \frac{1}{6} \begin{pmatrix} 1 & 1 & 1 \\ 1 & 1 & 1 \\ 1 & 1 & 1 \end{pmatrix} + \frac{1}{2} \begin{pmatrix} 0 & -1 & 1 \\ 1 & 0 & -1 \\ -1 & 1 & 0 \end{pmatrix} = \begin{pmatrix} \frac{2}{3} & -\frac{1}{3} & \frac{2}{3} \\ \frac{2}{3} & \frac{2}{3} & -\frac{1}{3} \\ -\frac{1}{3} & \frac{2}{3} & \frac{2}{3} \end{pmatrix}.$$

Then the rotated point is

$$P' = R_{\text{mat}} P = \begin{pmatrix} \frac{2}{3} \cdot 1 + (-\frac{1}{3}) \cdot 0 + \frac{2}{3} \cdot 1 \\ \frac{2}{3} \cdot 1 + \frac{2}{3} \cdot 0 + (-\frac{1}{3}) \cdot 1 \\ -\frac{1}{3} \cdot 1 + \frac{2}{3} \cdot 0 + \frac{2}{3} \cdot 1 \end{pmatrix} = \begin{pmatrix} \frac{4}{3} \\ \frac{1}{3} \\ \frac{1}{3} \end{pmatrix}.$$

Note that a rotation matrix is an operator on points and that rotation operations can be composed, without having to apply them to a point, via *matrix-matrix multiplication* of their rotation matrices. Storing a rotation matrix requires nine real numbers. Since there are only three rotational Degrees of Freedom in 3D, those nine numbers must be in a delicate relationship, which is expensive to maintain numerically under composition.

## Method 4: The Geometric (Clifford) Algebra Approach

In Geometric Algebra for  $\mathbb{R}^3$ , *geometric objects* are obtained as linear combinations of products of the basis vectors  $\mathbf{e}_1, \mathbf{e}_2, \mathbf{e}_3$ . The empty product corresponds to a scalar:

$$c_0 + c_1 \mathbf{e}_1 + c_2 \mathbf{e}_2 + c_3 \mathbf{e}_3 + c_4 \mathbf{e}_{12} + c_5 \mathbf{e}_{23} + c_6 \mathbf{e}_{31} + c_7 \mathbf{e}_{123}$$

where  $\mathbf{e}_{ij}$  is short for  $\mathbf{e}_i \mathbf{e}_j$ . The scalar component  $c_0$  can be viewed as a sized and oriented 0-dimensional subspace and the  $c_i \mathbf{e}_i$  components are sized and oriented 1-dimensional subspaces (size is vector length). Similarly, the  $c_k \mathbf{e}_{ij}$  components are sized and oriented (but unshaped) 2-dimensional subspaces (size is area; oriented also means that the plane segment has distinct front and back sides). Finally,  $c_7 \mathbf{e}_{123}$  is a sized and oriented 3-dimensional subspace (size is volume; there is only one orientation modulo its sign; hence,  $\mathbf{e}_{123}$  is also known as the space's *pseudoscalar*). Any vector corresponds to a linear combination of the three  $\mathbf{e}_i$  basis vectors. Similarly, any oriented plane segment in  $\mathbb{R}^3$  corresponds to a linear combination of the three basis *bivectors*  $\mathbf{e}_{ij}$ .

Products of basis vectors satisfy the following relations:

$$\begin{aligned} \mathbf{e}_i \mathbf{e}_i &= 1 \\ \mathbf{e}_i \mathbf{e}_j &= -\mathbf{e}_j \mathbf{e}_i \text{ if } i \neq j \end{aligned}$$

Note that addition and multiplication are associative, that addition is commutative, but that multiplication is not. Moreover, multiplication distributes over addition. Multiplication of geometric objects is known as the *geometric product*. For example, we have

$$(\mathbf{e}_{12})^2 = \mathbf{e}_1 \mathbf{e}_2 \mathbf{e}_1 \mathbf{e}_2 = -\mathbf{e}_1 \mathbf{e}_1 \mathbf{e}_2 \mathbf{e}_2 = -1$$

and thus the bivector  $\mathbf{e}_{12}$  behaves like the complex unit  $i$  with  $i^2 = -1$ . Also see Appendix A for a few more examples.

For our rotation problem, we can write

$$\begin{aligned} \mathbf{a} &= \mathbf{e}_1 + \mathbf{e}_2 + \mathbf{e}_3 \\ P &= \mathbf{e}_1 + \mathbf{e}_3 \end{aligned}$$

A rotation can be done by two successive *reflections*. The reflection of  $\mathbf{v}$  in the line<sup>1</sup> along unit vector  $\mathbf{b}$  is given by the geometric product  $-\mathbf{b}\mathbf{v}\mathbf{b}$ , a.k.a. a *sandwich product*, where  $\mathbf{v}$  is sandwiched between two  $\mathbf{b}$ 's (see Appendix A for an explanation). Thus, reflecting in two lines  $\mathbf{b}$  and  $\mathbf{c}$  in succession, where  $\theta/2$  is the angle between them, yields a rotation by  $\theta$ :  $\mathbf{c}\mathbf{b}\mathbf{v}\mathbf{b}\mathbf{c}$  (the minus signs canceled). Here,  $\mathbf{c}\mathbf{b}$  is a bivector known as a *rotor* (for rotating from  $\mathbf{b}$  to  $\mathbf{c}$ , by convention), and  $\mathbf{b}\mathbf{c}$  is its *reverse*.

Introducing the rotor (also see Appendix A)

$$R = e^{-\frac{\mathbf{B}}{\|\mathbf{B}\|} \frac{\theta}{2}} = \cos \frac{\theta}{2} - \frac{\mathbf{B}}{\|\mathbf{B}\|} \sin \frac{\theta}{2},$$

---

<sup>1</sup>Actually, in the hyperplane dual to the line.

where  $\mathbf{B}$  is the bivector representing the plane of rotation, one then obtains the rotated vector by

$$P' = R P R^\dagger,$$

with  $R^\dagger$  the *reverse* of  $R$ .

For a rotation about  $\mathbf{a} = \mathbf{e}_1 + \mathbf{e}_2 + \mathbf{e}_3$ , the plane of rotation is perpendicular to  $\mathbf{a}$ . One may take the unit bivector (see Fig. 5)

$$\mathbf{U} = \mathbf{I} \frac{\mathbf{a}}{\|\mathbf{a}\|} = \frac{1}{\sqrt{3}} \mathbf{I}(\mathbf{e}_1 + \mathbf{e}_2 + \mathbf{e}_3),$$

where  $\mathbf{I} = \mathbf{e}_1 \mathbf{e}_2 \mathbf{e}_3 = \mathbf{e}_{123}$  is the pseudoscalar (with  $\mathbf{I}^2 = -1$ ). The product  $\mathbf{I}(\mathbf{e}_1 + \mathbf{e}_2 + \mathbf{e}_3)$  can be simplified as follows:

$$\mathbf{I}(\mathbf{e}_1 + \mathbf{e}_2 + \mathbf{e}_3) = \mathbf{e}_{123}(\mathbf{e}_1 + \mathbf{e}_2 + \mathbf{e}_3) = \mathbf{e}_{1231} + \mathbf{e}_{1232} + \mathbf{e}_{1233} = \mathbf{e}_{1123} - \mathbf{e}_{1223} + \mathbf{e}_{1233} = \mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12}$$




Figure 5: Method 4: Geometric (Clifford) Algebra (unit bivector  $\mathbf{U}$  is not to scale).

With  $\theta = 60^\circ$ , so that  $\theta/2 = 30^\circ$ , the rotor becomes

$$R = \cos 30^\circ - \sin 30^\circ \mathbf{U} = \frac{\sqrt{3}}{2} - \frac{1}{2} \mathbf{U} \quad \text{and} \quad R^\dagger = \frac{\sqrt{3}}{2} + \frac{1}{2} \mathbf{U}.$$

A (careful but elementary) calculation using the sandwich product then shows that

$$P' = R P R^\dagger = \frac{4}{3} \mathbf{e}_1 + \frac{1}{3} \mathbf{e}_2 + \frac{1}{3} \mathbf{e}_3.$$

Note that a rotor is an operator on points and that rotation operations can be composed, without having to apply them to a point, via the geometric product of the rotors. Storing a rotor requires four natural numbers. Since there are only three rotational Degrees of Freedom in 3D, there is a relationship between these numbers, viz. that the magnitude of the rotor is 1, and this is easy to maintain under composition. Note that 3D rotors are equivalent to *unit quaternions*. For more on this approach see, e.g., [3] and [2].



## Conclusion

We have described four different methods for computing the rotation of

$$P = (1, 0, 1)^T$$

about the axis

$$\mathbf{a} = (1, 1, 1)^T$$

by  $60^\circ$ . The first method uses a symmetry unique to the situation (namely, the fact that  $P$  lies in an equilateral triangle together with  $(0, 1, 1)^T$  and  $(1, 1, 0)^T$ ). The second method sets up a new coordinate system using the projection of  $P$  onto  $a$  and uses the dot and cross products (whose definitions we recalled) to “rotate” the vector. The third method derives the rotation matrix by “rotating” the standard basis; this approach is particularly useful if many points must be rotated about the same axis. Finally, the fourth method, based on Geometric Algebra, interprets the rotation as the product of two reflections (or equivalently via the rotor  $R = \exp(-\mathbf{U}\theta/2)$ ), unifying the treatment of rotations and reflections.

Though each approach has its own conceptual overhead and computational flavor, all yield the same final result:

$$P' = \left(\frac{4}{3}, \frac{1}{3}, \frac{1}{3}\right)^T.$$

The choice of method depends on the context and the user’s familiarity with the underlying mathematical tools.

Some notes:

1. The *ad hoc* approach works only in very specific situations (axis  $\mathbf{a}$ , angle  $\theta$ , point  $P$ ). Conceptually, it requires the use of Cartesian coordinates, vectors, computing midpoints, vector length, and scaling.
2. The projection method is fully general, and varying angle  $\theta$  is easy, whereas varying axis  $\mathbf{a}$  or point  $P$  is more involved. Conceptually, it additionally requires the dot product and cross product of vectors, and trigonometry for the rotation.
3. The matrix method is also fully general, and it is very easy to vary point  $P$ , whereas varying axis  $\mathbf{a}$  or angle  $\theta$  requires the computation of a new rotation matrix.

Conceptually, this requires additionally the use of matrices and matrix-vector multiplication. The rotation matrix can be obtained by applying the projection method for each of the basis vectors, or by applying a (rather complicated) formula.

Matrices are nice because rotations can be composed by multiplying their matrices, using matrix-matrix multiplication (something new to be learned). Numerically, the composition of rotation matrices requires (expensive) re-orthonormalization.

4. The Geometric (Clifford) Algebra (GA) method is fully general and works in spaces of arbitrary dimension. The key insight is that, in general, a rotation takes place in a plane and not ‘about an axis’. The latter is only the case in 3D. The rotation

plane can be captured by a unit bivector, from which a rotor can be derived. The rotor is used in an exponential and applied as a sandwich product.

Conceptually, this requires basic understanding of GA concepts, such as geometric objects, their algebra with addition and the geometric product. To understand why the method works, one also needs to study reflection and how products of vectors are composed of a scalar and a bivector, involving the angle between the vectors. Understanding the dot product can be useful, but the cross product and matrices are not needed. The geometric product serves as linear operator.

The manual calculation with a rotor in a sandwich product is lengthy but elementary, and easy to automate.

Rotors are nice because rotations can be composed by multiplying their rotors using the geometric product (which is already familiar). Numerically, the composition of rotors is easy to re-normalize. For the special case of  $\mathbb{R}^3$ , the GA method is equivalent to the use of quaternions.

**Acknowledgments** I used Mathematica for verification (see Appendix B) and for creating the illustrations. I had some helpful conversations with ChatGPT 4o and o3-mini.

## References

- [1] H.S.M. Coxeter, *Introduction to Geometry*, Wiley, 1969.
- [2] L. Dorst, D. Fontijne, and S. Mann, *Geometric Algebra for Computer Science*, Morgan Kaufmann, 2007.
- [3] D. Hestenes, *New Foundations for Classical Mechanics*, Springer, 1986.
- [4] J. Marsden and A. Tromba, *Vector Calculus*, 5th ed., W. H. Freeman, 2003.
- [5] J. Smith (Admin). *Pre-University Geometric Algebra* group on *LinkedIn*.  
<https://www.linkedin.com/groups/8278281/>

## A Geometric Algebra details

The geometric product of two vectors  $\mathbf{v} = v_x \mathbf{e}_1 + v_y \mathbf{e}_2 + v_z \mathbf{e}_3$  and  $\mathbf{w} = w_x \mathbf{e}_1 + w_y \mathbf{e}_2 + w_z \mathbf{e}_3$  is calculated as

$$\begin{aligned}
 \mathbf{vw} &= (v_x \mathbf{e}_1 + v_y \mathbf{e}_2 + v_z \mathbf{e}_3) (w_x \mathbf{e}_1 + w_y \mathbf{e}_2 + w_z \mathbf{e}_3) \\
 &= v_x \mathbf{e}_1 (w_x \mathbf{e}_1 + w_y \mathbf{e}_2 + w_z \mathbf{e}_3) + \\
 &\quad v_y \mathbf{e}_2 (w_x \mathbf{e}_1 + w_y \mathbf{e}_2 + w_z \mathbf{e}_3) + \\
 &\quad v_z \mathbf{e}_3 (w_x \mathbf{e}_1 + w_y \mathbf{e}_2 + w_z \mathbf{e}_3)
 \end{aligned}$$

$$\begin{aligned}
&= v_x w_x \mathbf{e}_{11} + v_x w_y \mathbf{e}_{12} + v_x w_z \mathbf{e}_{13} + \\
&\quad v_y w_x \mathbf{e}_{21} + v_y w_y \mathbf{e}_{22} + v_y w_z \mathbf{e}_{23} + \\
&\quad v_z w_x \mathbf{e}_{31} + v_z w_y \mathbf{e}_{32} + v_z w_z \mathbf{e}_{33} \\
&= \quad v_x w_x \quad + v_x w_y \mathbf{e}_{12} - v_x w_z \mathbf{e}_{31} + \\
&\quad - v_y w_x \mathbf{e}_{12} + v_y w_y \quad + v_y w_z \mathbf{e}_{23} + \\
&\quad \quad v_z w_x \mathbf{e}_{31} - v_z w_y \mathbf{e}_{23} + v_z w_z \\
&= v_x w_x + v_y w_y + v_z w_z + \\
&\quad (v_y w_z - v_z w_y) \mathbf{e}_{23} + (v_z w_x - v_x w_z) \mathbf{e}_{31} + (v_x w_y - v_y w_x) \mathbf{e}_{12} \\
&= \mathbf{v} \cdot \mathbf{w} + \mathbf{v} \wedge \mathbf{w}
\end{aligned}$$

which defines  $\mathbf{v} \wedge \mathbf{w} = \mathbf{vw} - \mathbf{v} \cdot \mathbf{w}$ , called the *wedge product*. Note the resemblance and difference to  $\mathbf{v} \times \mathbf{w}$ : the coefficients are the same, but  $\mathbf{v} \wedge \mathbf{w}$  uses the dual bivectors as basis compared to the regular basis vectors used in  $\mathbf{v} \times \mathbf{w}$ . We do have

$$\|\mathbf{v} \wedge \mathbf{w}\| = \|\mathbf{v} \times \mathbf{w}\| = \|\mathbf{v}\| \|\mathbf{w}\| \sin \theta$$

where  $\theta$  is the angle between  $\mathbf{v}$  and  $\mathbf{w}$ .

Also note that in general the geometric product of two vectors is the sum of a scalar and a bivector. In fact, products of vectors are like complex numbers in the plane spanned by those vectors, since such a product is a linear combination of the scalar unit 1 and a unit bivector, which squares to  $-1$ . To see the latter, consider bivector  $x \mathbf{e}_{23} + y \mathbf{e}_{31} + z \mathbf{e}_{12}$  and calculate its square. This comes to  $-(x^2 + y^2 + z^2)$ .

The scalar part  $\mathbf{v} \cdot \mathbf{w}$  equals zero if and only if  $\mathbf{v} \perp \mathbf{w}$  and the bivector part  $\mathbf{v} \wedge \mathbf{w}$  vanishes if and only if  $\mathbf{v} \parallel \mathbf{w}$ . We also see that if  $\mathbf{v} \perp \mathbf{w}$ , then  $\mathbf{vw} = \mathbf{v} \wedge \mathbf{w} = -\mathbf{w} \wedge \mathbf{v} = -\mathbf{wv}$ . Moreover, if  $\mathbf{v} \parallel \mathbf{w}$ , then  $\mathbf{vw} = \mathbf{v} \cdot \mathbf{w} = \mathbf{w} \cdot \mathbf{v} = \mathbf{wv}$ .

The formula for reflecting vector  $\mathbf{v}$  in the line along unit vector  $\mathbf{b}$  (meaning in the dual hyperplane of  $\mathbf{b}$ ) was given as  $-\mathbf{bvb}$ . This can be explained as follows:

$$\begin{aligned}
-\mathbf{bvb} &= -\mathbf{b}(\mathbf{v}_{\perp \mathbf{b}} + \mathbf{v}_{\parallel \mathbf{b}})\mathbf{b} && \text{distribution} \\
&= -\mathbf{b}\mathbf{v}_{\perp \mathbf{b}}\mathbf{b} - \mathbf{b}\mathbf{v}_{\parallel \mathbf{b}}\mathbf{b} && \mathbf{v}_{\perp \mathbf{b}} \perp \mathbf{b} \text{ and } \mathbf{v}_{\parallel \mathbf{b}} \parallel \mathbf{b} \\
&= \mathbf{b}^2 \mathbf{v}_{\perp \mathbf{b}} - \mathbf{b}^2 \mathbf{v}_{\parallel \mathbf{b}} && \mathbf{b} \text{ is unit vector} \\
&= \mathbf{v}_{\perp \mathbf{b}} - \mathbf{v}_{\parallel \mathbf{b}}
\end{aligned}$$

So, indeed  $-\mathbf{bvb}$  flips the component of  $\mathbf{v}$  parallel to  $\mathbf{b}$ . (Similarly,  $\mathbf{bvb}$  flips the component of  $\mathbf{v}$  perpendicular to  $\mathbf{b}$ .)

To understand the rotor  $R = e^{-\frac{\mathbf{B}}{\|\mathbf{B}\|} \frac{\theta}{2}}$ , suppose we have unit vectors  $\mathbf{b}, \mathbf{c}$  spanning angle  $\theta/2$ . Then we can calculate:

$$\begin{aligned}
\mathbf{cb} &= \mathbf{c} \cdot \mathbf{b} + \mathbf{c} \wedge \mathbf{b} \\
&= \mathbf{b} \cdot \mathbf{c} - \mathbf{b} \wedge \mathbf{c} \\
&= \|\mathbf{b}\| \|\mathbf{c}\| \cos \frac{\theta}{2} - \|\mathbf{b}\| \|\mathbf{c}\| \frac{\mathbf{b} \wedge \mathbf{c}}{\|\mathbf{b} \wedge \mathbf{c}\|} \sin \frac{\theta}{2}
\end{aligned}$$

$$\begin{aligned}
&= \cos \frac{\theta}{2} - \mathbf{B} \sin \frac{\theta}{2} \quad \text{where } \mathbf{B} = \frac{\mathbf{b} \wedge \mathbf{c}}{\|\mathbf{b} \wedge \mathbf{c}\|} \\
&= e^{-\mathbf{B} \frac{\theta}{2}}
\end{aligned}$$

Keep in mind that  $\mathbf{B}$  is a unit bivector (hence,  $\mathbf{B}^2 = -1$ ) in the plane formed by  $\mathbf{b}$  and  $\mathbf{c}$ , which is used for rotating from  $\mathbf{b}$  to  $\mathbf{c}$ . To rotate from  $\mathbf{b}$  to  $\mathbf{c}$  by angle  $\theta$ , any pair  $\mathbf{b}, \mathbf{c}$  with angle  $\theta$  will do. Thus, the unit bivector in the plane spanned by  $\mathbf{v}$  and  $\mathbf{w}$  will do, as long as it is scaled to the right size by  $\sin \frac{\theta}{2}$ . In particular, we don't need concrete vectors  $\mathbf{v}$  and  $\mathbf{w}$ .

Finally, let's do this 'careful but elementary' calculation alluded to earlier.

$$\begin{aligned}
RPR^\dagger &= \left( \frac{\sqrt{3}}{2} - \frac{1}{2} \mathbf{U} \right) (\mathbf{e}_1 + \mathbf{e}_3) \left( \frac{\sqrt{3}}{2} + \frac{1}{2} \mathbf{U} \right) \\
&= (s - t(\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12}))(\mathbf{e}_1 + \mathbf{e}_3)(s + t(\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12})) \quad \text{where } s, t = \frac{\sqrt{3}}{2}, \frac{1}{2\sqrt{3}} \\
&= s^2(\mathbf{e}_1 + \mathbf{e}_3) + \\
&\quad st((\mathbf{e}_1 + \mathbf{e}_3)(\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12}) - (\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12})(\mathbf{e}_1 + \mathbf{e}_3)) + \\
&\quad t^2(\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12})(\mathbf{e}_1 + \mathbf{e}_3)(\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12}) \\
&= s^2(\mathbf{e}_1 + \mathbf{e}_3) + \\
&\quad st(\mathbf{e}_{123} + \mathbf{e}_{131} + \mathbf{e}_{112} + \mathbf{e}_{323} + \mathbf{e}_{331} + \mathbf{e}_{312} + \\
&\quad \quad - \mathbf{e}_{231} - \mathbf{e}_{311} - \mathbf{e}_{121} - \mathbf{e}_{233} - \mathbf{e}_{313} - \mathbf{e}_{123}) - \\
&\quad t^2(\mathbf{e}_{23}(\mathbf{e}_1 + \mathbf{e}_3)(\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12}) + \\
&\quad \quad \mathbf{e}_{31}(\mathbf{e}_1 + \mathbf{e}_3)(\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12}) + \\
&\quad \quad \mathbf{e}_{12}(\mathbf{e}_1 + \mathbf{e}_3)(\mathbf{e}_{23} + \mathbf{e}_{31} + \mathbf{e}_{12})) \\
&= s^2(\mathbf{e}_1 + \mathbf{e}_3) + \\
&\quad st(\mathbf{e}_{123} - \mathbf{e}_3 + \mathbf{e}_2 - \mathbf{e}_2 + \mathbf{e}_1 + \mathbf{e}_{123} - \mathbf{e}_{123} - \mathbf{e}_3 + \mathbf{e}_2 - \mathbf{e}_2 + \mathbf{e}_1 - \mathbf{e}_{123}) - \\
&\quad t^2(\mathbf{e}_{23123} + \mathbf{e}_{23131} + \mathbf{e}_{23112} + \mathbf{e}_{23323} + \mathbf{e}_{23331} + \mathbf{e}_{23312} + \\
&\quad \quad \mathbf{e}_{31123} + \mathbf{e}_{31131} + \mathbf{e}_{31112} + \mathbf{e}_{31323} + \mathbf{e}_{31331} + \mathbf{e}_{31312} + \\
&\quad \quad \mathbf{e}_{12123} + \mathbf{e}_{12131} + \mathbf{e}_{12112} + \mathbf{e}_{12323} + \mathbf{e}_{12331} + \mathbf{e}_{12312}) \\
&= s^2(\mathbf{e}_1 + \mathbf{e}_3) + 2st(\mathbf{e}_1 - \mathbf{e}_3) - \\
&\quad t^2(-\mathbf{e}_1 - \mathbf{e}_2 - \mathbf{e}_3 + \mathbf{e}_3 + \mathbf{e}_{123} - \mathbf{e}_1 + \\
&\quad \quad - \mathbf{e}_2 + \mathbf{e}_1 + \mathbf{e}_{123} - \mathbf{e}_{123} + \mathbf{e}_3 - \mathbf{e}_2 + \\
&\quad \quad - \mathbf{e}_3 - \mathbf{e}_{123} + \mathbf{e}_1 - \mathbf{e}_1 - \mathbf{e}_2 - \mathbf{e}_3) \\
&= s^2(\mathbf{e}_1 + \mathbf{e}_3) + 2st(\mathbf{e}_1 - \mathbf{e}_3) + t^2(\mathbf{e}_1 + 4\mathbf{e}_2 + \mathbf{e}_3) \\
&= (s^2 + 2st + t^2)\mathbf{e}_1 + 4t^2\mathbf{e}_2 + (s^2 - 2st + t^2)\mathbf{e}_3 \\
&= (s + t)^2\mathbf{e}_1 + 4t^2\mathbf{e}_2 + (s - t)^2\mathbf{e}_3 \\
&= \frac{4}{3}\mathbf{e}_1 + \frac{1}{3}\mathbf{e}_2 + \frac{1}{3}\mathbf{e}_3
\end{aligned}$$

This is a good exercise in algebra and sign bookkeeping, which is ideal for automation.

## B Mathematica code

The general set up of our rotation problem:

---

```
1 origin = {0, 0, 0}
2 axis = {1, 1, 1}
3 theta = 60 Degrees (* just an angle; we should also do it for an arbitrary angle *)
4 pointP = {1, 0, 1}
```

---

Method 1:

---

```
5 pointP2 = {1, 1, 0};
6 pointP3 = {0, 1, 1};
7 pointQ = Mean[{pointP, pointP2, pointP3}];
8 pointM = Mean[{pointP, pointP2}];
9 pointPdash = pointQ + (pointM - pointQ) Norm[pointP - pointQ] / Norm[pointM - pointQ]
```

---

Method 2:

---

```
10 zAxis = Normalize[axis];
11 pointQ = (pointP . zAxis) zAxis; (* using dot product of vectors *)
12 xAxis = Normalize[pointP - pointQ];
13 yAxis = Cross[zAxis, xAxis];
14 pointPdash = pointQ + (Cos[theta] xAxis + Sin[theta] yAxis) Norm[pointP - pointQ]
```

---

Method 3:

---

```
15 R = RotationMatrix[theta, axis];
16 pointPdash = R . pointP (* using matrix-vector product *)
```

---

Method 4:

---

```
17 << CliffordBasic' (* installed from https://github.com/jlaragonvera/Geometric-Algebra *)
18 a = ToBasis[axis] (* axis: e[1] + e[2] + e[3] *)
19 p = ToBasis[pointP] (* point to be rotated: e[1] + e[3] *)
20 B = -Dual[a, 3] (* bivector for rotation plane: e[2,3] + e[3,1] + e[1,2] *)
21 rotor[B_, theta_] := Cos[theta/2] - B Sin[theta/2] / Magnitude[B];
22 GeometricRotate[v_, R_] := GeometricProduct[R, v, Turn[R]]; (* Turn[R] = reverse of R *)
23 pdash = GeometricRotate[p, rotor[B, theta]];
24 pointPdash = ToVector[pdash]
```

---