

How to calculate the Wigner angle

C. J. McKinstrie

Independent Photonics Consultant, Manalapan, NJ 07726

M. V. Kozlov

Center for Preparatory Studies, Nazarbayev University, Astana 010000, Kazakhstan

Abstract

Lorentz transformations in time and two space dimensions consist of boosts and rotations, and combinations thereof. In general, the combination of two boosts is not another boost: It is a boost followed by a rotation. The rotation angle is called the Wigner angle. Although it is straightforward to determine the energy and direction of the combined boost, it is difficult to determine the Wigner angle. In this article, the vector, matrix and spinor derivations of formulas for the Wigner angle are reviewed, and the underlying mathematics and physics are discussed briefly. Although the derivations are different, the results they produce are equivalent, as they should be. Like many physics problems, if one looks at the problem in the right way, it is not difficult to solve.

1. Introduction

The theory of special relativity is an important part of the undergraduate and graduate physics curricula [1, 2, 3, 4], and is required to analyze many phenomena of current interest. In time and one space dimension, every Lorentz transformation is a boost, transformations always act in the same (or opposite) direction and their composition rules are simple. However, in two (and three) dimensions, transformations are combinations of boosts and rotations, boosts can act in different directions and their composition rules are complicated.

It is well known that the combination of two parallel (or antiparallel) boosts is another boost (as it is in one dimension), but the combination of two nonparallel boosts is not: It is a boost followed by a rotation. Although it is straightforward to calculate the energy and direction of the combined boost, it is difficult to calculate the rotation angle, which is called the Wigner angle. In this article, we discuss three ways to determine the Wigner angle.

In Sec. 2, the standard vector (tensor) formalism is used to represent a boost and analyze the composition of two boosts. A boost is specified by its (dimensionless) velocity $\vec{v}$, in which case its energy $\gamma = 1/(1 - v^2)^{1/2}$, or its momentum $\vec{u} = \gamma\vec{v}$, in which case $\gamma = (1 + u^2)^{1/2}$. (Time and distance are measured in the same units, so time is really ct and velocity is really $\vec{v}/c$.) Two equivalent formulas for the product tensor are derived. The first formula involves the momenta $\vec{u}_1$ and $\vec{u}_2$ that define the boosts, whereas the second involves the momenta $\vec{u}_{12}$ and $\vec{u}_{21}$ that appear in the product tensor. We explain why the angle between the latter momenta is the Wigner angle and derive a formula for it.

The special orthogonal group $SO(1,2)$ consists of real 3×3 matrices L that satisfy the indefinite orthogonality (Lorentz) condition $L^t S L = S$, where $S = \text{diag}(1, -1, -1)$ is the structure (metric) matrix. This condition ensures that Lorentz transformations of the coordinate vector $T = [t, x, y]^t$ preserve the squared interval $T^t S T = t^2 - x^2 - y^2$. Lorentz matrices represent boosts in the x and y directions, rotations about the t axis (in the xy plane) and combinations of these transformations. The Lorentz condition imposes significant constraints on Lorentz matrices, which ensure that each matrix has the decomposition $L(\gamma, \theta_1, \theta_2) = R(\theta_2)B(\gamma)R^t(\theta_1)$, where $B(\gamma)$ represents a boost in the x direction with energy γ , and $R(\theta_i)$ represents a rotation through the (input or output) angle θ_i . This decomposition can be rewritten in the form $L(\gamma, \theta_1, \theta_2) = R(\theta_{21})B(\gamma, \theta_1)$, where $B(\gamma, \theta_1) = R(\theta_1)B(\gamma)R^t(\theta_1)$

represents a boost with direction angle θ_1 and $R(\theta_{21})$ represents a rotation through the difference (Wigner) angle $\theta_{21} = \theta_2 - \theta_1$. (The second decomposition was mentioned above.) In Sec. 3, we use the decomposition formula to efficiently derive equivalent formulas for the Wigner angle.

The special unitary group $SU(1,1)$ consists of complex 2×2 matrices M that satisfy the indefinite unitarity condition $M^\dagger S M = S$, where $S = \text{diag}(1, -1)$ is the metric matrix. It is well known that $SU(1,1)$ is locally isomorphic to (has the same local structure as) $SO(1,2)$. Each fundamental indefinite-unitary transformation (a real boost, a complex boost and a differential phase shift) corresponds to a Lorentz transformation (a boost in the x direction, a boost in the y direction and a rotation in the xy plane). One can use these relations to derive matrix-product rules for $SU(1,1)$ and deduce the corresponding rules for $SO(1,2)$. In principle, this indirect method (which is often called the spinor method) is simpler than the direct methods, because it involves 2×2 matrices, rather than 3×3 matrices (tensors). In Sec. 4, we use it to derive formulas for the Wigner half- and full-angles.

Finally, in Sec. 5, the main results of this article are summarized, and the advantages and disadvantages of each approach are discussed briefly. For completeness, the composition of two arbitrary transformations is discussed in the appendix.

2. Vector formalism

A Lorentz boost is specified by its (dimensionless) momentum $\vec{u}$ and energy $\gamma = (1 + u^2)^{1/2}$. Let t and $\vec{r}$ represent time and position, respectively. Then the boost equations are

$$t' = \gamma t + \vec{u} \cdot \vec{r}, \quad (1)$$

$$\begin{aligned} \vec{r}' &= \vec{u}t + [1 + (\gamma - 1)\vec{u}\vec{u} \cdot /u^2]\vec{r} \\ &= \vec{u}t + (1 + \epsilon\vec{u}\vec{u} \cdot)\vec{r}, \end{aligned} \quad (2)$$

where the unprimed (primed) variables are inputs (outputs) and $\epsilon = 1/(\gamma + 1)$ [2, 3]. These equations represent a transformation from the laboratory frame to a frame that is moving with momentum $-\vec{u}$. In Eq. (1), time is mixed with the component of $\vec{r}$ that is parallel to $\vec{u}$. In Eq. (2), the parallel part $\vec{r}_{\parallel} = \vec{u}\vec{u} \cdot \vec{r}/u^2$ is mixed with time, whereas the perpendicular part $\vec{r}_{\perp} = (1 - \vec{u}\vec{u} \cdot /u^2)\vec{r}$ is preserved.

One can rewrite Eqs. (1) and (2) in the tensor (matrix-like) form

$$T' = BT, \quad (3)$$

where $T = (t, \vec{r})$ and $T' = (t', \vec{r}')$ are coordinate three-vectors and the boost operator

$$B(\vec{u}) = \left[\begin{array}{c|c} \gamma & \vec{u} \cdot \\ \hline \vec{u} & 1 + \epsilon\vec{u}\vec{u} \cdot \end{array} \right]. \quad (4)$$

The lines on the right side of Eq. (4) divide the operator into blocks. The top-left entry acts on a scalar to produce another scalar, the top-right entry acts on a vector to produce a scalar, the bottom-left entry acts on a scalar to produce a vector and the bottom-right entry acts on a vector to produce another vector. Notice that the boost operator is symmetric.

Now let $E_p = (\gamma_p, \vec{u}_p)$ be the energy-momentum three-vector of a particle of unit mass, where $\gamma_p^2 - u_p^2 = 1$. This vector transforms in the same way as the coordinate vector ($E'_p = BE_p$). If the particle is at rest before the boost, then $\gamma_p = 1$ and $\vec{u}_p = 0$. After the boost,

$$\gamma'_p = \gamma, \quad \vec{u}'_p = \vec{u}. \quad (5)$$

Thus, the energy and momentum of a particle boosted from rest equal the energy and momentum that defined the boost, respectively (whence the name boost).

Now consider the boosting of a particle that is already moving. It follows from Eqs. (3) and (4), with $(\gamma, \vec{u}) = (\gamma_2, \vec{u}_2)$ and $(t, \vec{r}) = (\gamma_1, \vec{u}_1)$, that

$$\gamma_{21} = \gamma_2 \gamma_1 + \vec{u}_2 \cdot \vec{u}_1, \quad (6)$$

$$\begin{aligned} \vec{u}_{21} &= \vec{u}_2 \gamma_1 + [1 + \epsilon_2 \vec{u}_2 \cdot \vec{u}_1] \vec{u}_1 \\ &= \vec{u}_1 + (\gamma_1 + \epsilon_2 \vec{u}_2 \cdot \vec{u}_1) \vec{u}_2. \end{aligned} \quad (7)$$

It is tedious, but straightforward, to show that $\gamma_{21}^2 - u_{21}^2 = 1$. Thus, $(\gamma_{21}, \vec{u}_{21})$ is also an energy-momentum three-vector.

If we had used $(\gamma_1, \vec{u}_1)$ to transform $(\gamma_2, \vec{u}_2)$, we would have found that

$$\gamma_{12} = \gamma_1 \gamma_2 + \vec{u}_1 \cdot \vec{u}_2, \quad (8)$$

$$\vec{u}_{12} = \vec{u}_2 + (\gamma_2 + \epsilon_1 \vec{u}_1 \cdot \vec{u}_2) \vec{u}_1, \quad (9)$$

where $\gamma_{12}^2 - u_{12}^2 = 1$. Although $\vec{u}_{12}$ and $\vec{u}_{21}$ are different vectors (and the formulas for them in terms of $\vec{u}_1$ and $\vec{u}_2$ are complicated), their lengths are equal because their associated energies are equal ($\gamma_{12} = \gamma_{21} = \gamma$). Only their directions are different, which means that one vector is a rotated version of the other (in the plane defined by $\vec{u}_1$ and $\vec{u}_2$).

Now consider two successive transformations, specified by the three-vectors $(\gamma_1, \vec{u}_1)$ and $(\gamma_2, \vec{u}_2)$. Then, by applying Eqs. (3) and (4) twice, one finds that $T'' = B_2 B_1 T$, where the product operator

$$B_2(\vec{u}_2) B_1(\vec{u}_1) = \left[\begin{array}{c|c} \gamma & \vec{u}_{12} \\ \hline \vec{u}_{21} & \vec{\sigma}_{21} \end{array} \right]. \quad (10)$$

The constituents of this operator are

$$\gamma = \gamma_2 \gamma_1 + \vec{u}_2 \cdot \vec{u}_1, \quad (11)$$

$$\vec{u}_{12} = \vec{u}_2 + (\gamma_2 + \epsilon_1 \vec{u}_2 \cdot \vec{u}_1) \vec{u}_1, \quad (12)$$

$$\vec{u}_{21} = \vec{u}_1 + (\gamma_1 + \epsilon_2 \vec{u}_2 \cdot \vec{u}_1) \vec{u}_2, \quad (13)$$

$$\vec{\sigma}_{21} = 1 + \epsilon_2 \vec{u}_2 \cdot \vec{u}_2 + \epsilon_1 \vec{u}_1 \cdot \vec{u}_1 + (1 + \epsilon_2 \epsilon_1 \vec{u}_2 \cdot \vec{u}_1) \vec{u}_2 \cdot \vec{u}_1. \quad (14)$$

If the operator $B_2 B_1$ were to act on the three-vector $(1, 0)$, it would produce the three-vector $(\gamma_{21}, \vec{u}_{21})$, and if the operator $B_1 B_2$ were to act on the three-vector $(1, 0)$, it would produce

the three-vector $(\gamma_{12}, \vec{u}_{12})$, where $\gamma_{12} = \gamma_{21} = \gamma$. This observation establishes the physical significances of the scalar in Eq. (11), and the vectors in Eqs. (12) and (13). However, the physical significance of the dyadic in Eq. (14) is not obvious. Notice that this dyadic depends quadratically on $\vec{u}_2$ and $\vec{u}_1$, and is almost symmetric: The only term that depends on the order of the subscripts (boosts) is the last one, which is proportional to $\vec{u}_2 \vec{u}_1$. Because of this asymmetry, the composition of two boosts is not another boost (unless $\vec{u}_2$ is parallel or antiparallel to $\vec{u}_1$).

Evidently, Lorentz transformations are not limited to boosts. To ascertain what else they are, consider two pairs of coordinate axes, one in the laboratory frame (LF) and the other in a first moving frame (MF1), which moves with momentum $\vec{u}_1$ relative to the LF. At some reference time, the two origins coincide. How does one transform the LF axes so that they always coincide with the MF1 axes? First, one boosts the LF axes so that their origin coincides (keeps up) with the origin of the MF1 axes. Second (if necessary), one rotates the LF axes so that they align with the MF1 axes. Thus, the most general transformation between the frames consists of a boost followed by a rotation [5, 6]. Now consider another set of axes in a second moving frame (MF2), which moves with momentum $\vec{u}_2$ relative to MF1. Then one can transform the MF1 axes so that they coincide with the MF2 axes by boosting and rotating them. But the MF2 axes also move relative to the LF axes, so one can also transform the LF axes to the MF2 axes by boosting and rotating them (in ways that remain to be determined). Thus, Lorentz transformations, and combinations of them, consist of boosts followed by rotations.

The product operator (10) is asymmetric, so it must represent a boost followed by a rotation, but which ones? Let $\vec{\omega}_{21}$ be the rotation operator that converts $\vec{u}_{12}$ to $\vec{u}_{21}$ and consider the ansatz

$$\begin{aligned} L_{21} &= \left[\begin{array}{c|c} 1 & 0 \\ \hline 0 & \vec{\omega}_{21} \end{array} \right] \left[\begin{array}{c|c} \gamma & \vec{u}_{12} \\ \hline \vec{u}_{12} & 1 + \epsilon \vec{u}_{12} \vec{u}_{12} \cdot \end{array} \right] \\ &= \left[\begin{array}{c|c} \gamma & \vec{u}_{12} \\ \hline \vec{u}_{21} & \vec{\omega}_{21} + \epsilon \vec{u}_{21} \vec{u}_{12} \cdot \end{array} \right]. \end{aligned} \quad (15)$$

Notice that the rotation operator only modifies the bottom entries of the boost operator on which it acts. The requirement that the top entries in operator (15) equal the top entries

in operator (10) forces the boost operator to be the one specified by $\vec{u}_{12}$. The bottom left entry equals $\vec{u}_{21}$ by construction. By comparing the bottom right entries, one finds that

$$\vec{\sigma}_{21} = \vec{\omega}_{21} + \epsilon \vec{u}_{21} \vec{u}_{12} \cdot . \quad (16)$$

This entry contains the rotation operator itself, and the dyadic $\vec{u}_{21} \vec{u}_{12}$, both of which are asymmetric.

It only remains to write the rotation operator in terms of vectors. Let $\vec{n}_1$ and $\vec{n}_2$ be arbitrary unit vectors, let θ_{21} be the angle between them and consider the ansatz

$$\vec{\omega}_{21} = (\vec{n}_1 \cdot \vec{n}_2) + (\vec{n}_1 \times \vec{n}_2) \times , \quad (17)$$

where the dot product has magnitude $\cos(\theta_{21})$ and the cross product has magnitude $\sin(\theta_{21})$. It is easy to verify that $\vec{\omega}_{21} \vec{n}_1 = \vec{n}_2$. The dot product shortens $\vec{n}_1$ and the cross product adds the perpendicular part required to convert it to $\vec{n}_2$. In the context of transformation (15),

$$\vec{\omega}_{21} = \frac{\vec{u}_{12} \cdot \vec{u}_{21} + (\vec{u}_{12} \times \vec{u}_{21}) \times}{\gamma^2 - 1}, \quad (18)$$

because $|\vec{u}_{12}| = |\vec{u}_{21}| = (\gamma^2 - 1)^{1/2}$. By combining Eqs. (16) and (18), one obtains the operator

$$\vec{\sigma}_{21} = \frac{\vec{u}_{12} \cdot \vec{u}_{21} + (\vec{u}_{12} \times \vec{u}_{21}) \times}{\gamma^2 - 1} + \frac{\vec{u}_{21} \vec{u}_{12} \cdot}{\gamma + 1}. \quad (19)$$

Formula (14) involves the momenta $\vec{u}_1$ and $\vec{u}_2$ that define the constituent boosts, whereas formula (19) involves the momenta $\vec{u}_{12}$ and $\vec{u}_{21}$ that appear in the product operator. We demonstrated their equivalence in [8].

It follows from the first line of Eq. (15) that the rotation angle, which is called the Wigner angle, is the angle between $\vec{u}_{12}$ and $\vec{u}_{21}$. By combining Eqs. (7) and (9), one finds that

$$\vec{u}_{12} \times \vec{u}_{21} = (b_{12} b_{21} - 1) \vec{u}_1 \times \vec{u}_2, \quad (20)$$

where $b_{12} = \gamma_2 + \epsilon_1 \vec{u}_1 \cdot \vec{u}_2$ and $b_{21} = \gamma_1 + \epsilon_2 \vec{u}_1 \cdot \vec{u}_2$. Notice that the right side of Eq. (20) is proportional to the sine of the angle between $\vec{u}_1$ and $\vec{u}_2$ (θ_{21}), whereas the left side is proportional to the sine of the angle between $\vec{u}_{12}$ and $\vec{u}_{21}$ (θ_w). If the former vectors are not parallel, then neither are the latter vectors. It follows from Eq. (20) that

$$\sin(\theta_w) = \frac{(b_{12} b_{21} - 1) u_2 u_1 s_{21}}{\gamma^2 - 1}, \quad (21)$$

where $s_{21} = \sin(\theta_{21})$. Although Eq. (21) looks complicated, the numerator and denominator are both divisible by $\gamma - 1$ [Eq. (11)]. The numerator is proportional to

$$\begin{aligned}
& (b_{12}b_{21} - 1)u_2u_1 \\
&= (\gamma_2u_1 + u_2\delta_1c_{21})(u_2\gamma_1 + \delta_2u_1c_{21}) - u_2u_1 \\
&= (\gamma_2\gamma_1 - 1)u_2u_1 + (\gamma_2\delta_2u_1^2 + u_2^2\gamma_1\delta_1)c_{21} + \delta_2\delta_1u_2u_1c_{21}^2,
\end{aligned} \tag{22}$$

where $c_{21} = \cos(\theta_{21})$ and $\delta_i = \gamma_i - 1$. The first term in Eq. (22) is the product of $\gamma_2\gamma_1 - 1$ and u_2u_1 , and the last term is the product of $u_2u_1c_{21}$ and $\delta_2\delta_1c_{21}$, so consider the ansatz

$$\begin{aligned}
& (\gamma_2\gamma_1 - 1 + u_2u_1c_{21})(u_2u_1 + \delta_2\delta_1c_{21}) \\
&= (\gamma_2\gamma_1 - 1)u_2u_1 + [(\gamma_2\gamma_1 - 1)\delta_2\delta_1 + u_2^2u_1^2]c_{21} + \delta_2\delta_1u_2u_1c_{21}^2.
\end{aligned} \tag{23}$$

In Eqs. (22) and (23), the coefficients of c_{21} both equal $(2\gamma_2\gamma_1 + \gamma_2 + \gamma_1)\delta_2\delta_1$, so the latter equation is the required factorization of the former. By combining the preceding results, one finds that the Wigner angle is specified implicitly by the equation

$$\sin(\theta_w) = \frac{(u_2u_1 + \delta_2\delta_1c_{21})s_{21}}{\gamma_2\gamma_1 + 1 + u_2u_1c_{21}}. \tag{24}$$

Notice that θ_w only depends on the difference angle θ_{21} .

The derivation of Eq. (24) was based on the cross product of $\vec{u}_{12}$ and $\vec{u}_{21}$. In [8], we used the dot product to derive the alternative equation

$$\cos(\theta_w) = \frac{\gamma_2 + \gamma_1 + (u_2u_1 + \delta_2\delta_1c_{21})c_{21}}{\gamma_2\gamma_1 + 1 + u_2u_1c_{21}}. \tag{25}$$

We also checked that formulas (24) and (25) are consistent ($c_w^2 + s_w^2 = 1$). Notice that their common denominator is $\gamma + 1$ [Eq. (11)].

It is convenient to define the transformation parameter

$$\tau = u_2u_1/\delta_2\delta_1 = [(\gamma_2 + 1)(\gamma_1 + 1)/(\gamma_2 - 1)(\gamma_1 - 1)]^{1/2}, \tag{26}$$

which should not be confused with the proper time. By multiplying the numerators and denominators of Eqs. (24) and (25) by $2/\delta_2\delta_1$, and using the identities

$$\tau^2 + 1 = 2(\gamma_2\gamma_1 + 1)/\delta_2\delta_1, \tag{27}$$

$$\tau^2 - 1 = 2(\gamma_2 + \gamma_1)/\delta_2\delta_1, \tag{28}$$

one finds that

$$\begin{aligned}
s_w &= \frac{2(u_2 u_1 / \delta_2 \delta_1 + c)s}{2(\gamma_2 \gamma_1 + 1) / \delta_2 \delta_1 + 2(u_2 u_1 / \delta_2 \delta_1)c} \\
&= \frac{2(\tau + c)s}{\tau^2 + 1 + 2\tau c} = \frac{2(\tau + c)s}{(\tau + c)^2 + s^2}, \tag{29}
\end{aligned}$$

$$\begin{aligned}
c_w &= \frac{2(\gamma_2 + \gamma_1) / \delta_2 \delta_1 + 2(u_2 u_1 / \delta_2 \delta_1 + c)c}{2(\gamma_2 \gamma_1 + 1) / \delta_2 \delta_1 + 2(u_2 u_1 / \delta_2 \delta_1)c} \\
&= \frac{\tau^2 - 1 + 2(\tau + c)c}{\tau^2 + 1 + 2\tau c} = \frac{(\tau + c)^2 - s^2}{(\tau + c)^2 + s^2}, \tag{30}
\end{aligned}$$

where c and s are abbreviations of c_{21} and s_{21} , respectively. Equations (29) and (30) are equivalent to Eqs. (13) and (10) of [7], respectively.

An advantage of the vector formalism is that it generalizes automatically from two to three space dimensions. The (input) vectors $\vec{u}_1$ and $\vec{u}_2$, which appear in the boost tensors, specify a plane in three-space. The (output) vectors $\vec{u}_{12}$ and $\vec{u}_{21}$, which appear in the product tensor, are linear combinations of $\vec{u}_1$ and $\vec{u}_2$, so they lie in the aforementioned plane. The vector cross- and dot-products are independent of the coordinate systems used to represent them. If one aligns the x axis with $\vec{u}_1$, the y axis with $\vec{u}_2 - (\vec{u}_2 \cdot \vec{u}_1)\vec{u}_1/u_1^2$ and the z axis with $\vec{u}_1 \times \vec{u}_2$, then the transformation is effectively two-dimensional, and Eqs. (24) and (25) still apply. Two caveats are worth mentioning: First, Eq. (17) can be rewritten in the form $\vec{\omega}_{21} = c_{21} + s_{21}\vec{n} \times$, where $\vec{n} = (\vec{n}_1 \times \vec{n}_2)/|\vec{n}_1 \times \vec{n}_2|$ is the unit vector that defines the axis of rotation. In three dimensions, it remains true that $\vec{\omega}_{21}\vec{n}_1 = \vec{n}_2$. Nonetheless, one should add to the rotation tensor the term $(1 - c_{21})\vec{n}\vec{n}$, which allows the tensor to preserve the parallel components of the vectors on which it acts [9]. Second, in two dimensions, the third (successive) boost is coplanar (in the plane defined by the first two boosts), whereas in three dimensions, the third boost need not be coplanar.

3. Matrix formalism

Let $T = [t, x, y]^t$ and $T' = [t', x', y']^t$ be 3×1 coordinate vectors, and let L be a real 3×3 matrix. Then a Lorentz transformation can be written in the matrix form

$$T' = LT, \quad (31)$$

provided that the transformation matrix satisfies the equivalent equations

$$L^t S L = S, \quad L^{-1} = S L^t S, \quad (32)$$

where $S = \text{diag}(1, -1, -1)$ is the structure (metric) matrix. The first of Eqs. (32) is called the Lorentz condition. It ensures that the inner product (squared interval) $T^t S T = t^2 - x^2 - y^2$ is conserved. The set of Lorentz matrices with determinant 1 (rather than -1) forms a group under multiplication [8, 9]. It is called the special orthogonal group $\text{SO}(1,2)$, or the indefinite orthogonal group, because the metric matrix is indefinite (has positive and negative eigenvalues, which allow the squared interval to be positive or negative). The set of coordinate vectors forms a vector space under addition, which is called Minkowski space.

Examples of Lorentz matrices include the boost matrices

$$B_x(\gamma) = \begin{bmatrix} \gamma & u & 0 \\ u & \gamma & 0 \\ 0 & 0 & 1 \end{bmatrix}, \quad B_y(\gamma) = \begin{bmatrix} \gamma & 0 & u \\ 0 & 1 & 0 \\ u & 0 & \gamma \end{bmatrix}, \quad (33)$$

where γ and u are the (dimensionless) energy and momentum parameters, respectively. The Lorentz and determinant conditions both require that $\gamma^2 - u^2 = 1$, which allows one to write $\gamma = \cosh(\zeta)$ and $u = \sinh(\zeta)$, where ζ is the boost parameter (rapidity). The rotation matrix

$$R(\theta) = \begin{bmatrix} 1 & 0 & 0 \\ 0 & c & -s \\ 0 & s & c \end{bmatrix}, \quad (34)$$

where θ is the rotation angle, $c = \cos(\theta)$ and $s = \sin(\theta)$. $\text{SO}(1,2)$ is closed under multiplication, so products of Lorentz matrices are also Lorentz matrices. Consider the product

$$B(\gamma, \theta) = R(\theta) B_x(\gamma) R^t(\theta), \quad (35)$$

which is symmetric. Written explicitly,

$$B(\gamma, \theta) = \begin{bmatrix} \gamma & uc & us \\ uc & 1 + \delta c^2 & \delta cs \\ us & \delta sc & 1 + \delta s^2 \end{bmatrix}, \quad (36)$$

where $\delta = \gamma - 1$. In Eq. (35), R^t aligns the x axis with the intended boost direction, B_x effects the boost and R returns the axes to their original orientations, so matrix (36) represents a boost of energy γ with direction angle θ . For example, $B_y(\gamma) = R(\pi/2)B_x(\gamma)R^t(\pi/2)$. Equation (35) is a similarity transformation of B_x , which preserves the boost energy. If one were to rewrite matrix (36) in terms of momentum components ($c = u_x/u$ and $s = u_y/u$), one would obtain tensor (4).

The Lorentz condition imposes significant constraints on Lorentz matrices. In [8, 9] we explained why every Lorentz matrix can be written in the block forms

$$\begin{aligned} L &= \begin{bmatrix} \gamma & R \\ C & N + \epsilon CR \end{bmatrix} \\ &= \begin{bmatrix} 1 & 0 \\ 0 & N \end{bmatrix} \begin{bmatrix} \gamma & R \\ R^t & I + \epsilon R^t R \end{bmatrix} \\ &= \begin{bmatrix} \gamma & C^t \\ C & I + \epsilon CC^t \end{bmatrix} \begin{bmatrix} 1 & 0 \\ 0 & N \end{bmatrix}, \end{aligned} \quad (37)$$

where γ and $\epsilon = 1/(\gamma + 1)$ are scalars, R (temporarily) and C are row and column vectors, respectively, and N is a rotation matrix ($C = NR^t$, so $C^t N = R$). The matrices that involve γ and R , or γ and C , are symmetric, so they represent boosts in directions that are determined by R or C . Thus, every Lorentz transformation can be written as a boost followed (or preceded) by a rotation. Notice that Eqs. (15) and Eq. (37) are equivalent. The derivation of the former equation was based on physics, whereas the derivation of the latter is based on mathematics.

In terms of components,

$$L = \begin{bmatrix} \gamma & uc_1 & us_1 \\ uc_2 & c_{21} + \delta c_2 c_1 & -s_{21} + \delta c_2 s_1 \\ us_2 & s_{21} + \delta s_2 c_1 & c_{21} + \delta s_2 s_1 \end{bmatrix}$$

$$= \begin{bmatrix} 1 & 0 & 0 \\ 0 & c_2 & -s_2 \\ 0 & s_2 & c_2 \end{bmatrix} \begin{bmatrix} \gamma & u & 0 \\ u & \gamma & 0 \\ 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} 1 & 0 & 0 \\ 0 & c_1 & s_1 \\ 0 & -s_1 & c_1 \end{bmatrix}, \quad (38)$$

where $c_i = \cos(\theta_i)$, $s = \sin(\theta_i)$, and $\theta_{21} = \theta_2 - \theta_1$. By comparing the first lines of Eqs. (37) and (38), one finds that $R = u[c_1, s_1]$ and $C = u[c_2, s_2]^t$ are momentum vectors with (common) length u , and direction angles θ_1 and θ_2 . It follows from the second line of Eq. (38) that every Lorentz matrix has the decomposition

$$L(\gamma, \theta_1, \theta_1) = R(\theta_2)B(\gamma)R(\theta_1)^t, \quad (39)$$

in which $B = B_x$ is the fundamental boost matrix and $R_i = R(\theta_i)$ is a two-dimensional rotation matrix [8, 9]. Consequently, θ_1 and θ_2 are called the input and output angles, respectively, and θ_{21} is called the difference angle. Notice that Eq. (39) is a simple generalization of Eq. (35). It shows that a general Lorentz matrix is specified by the independent (free) parameters γ , θ_1 and θ_2 .

Every real matrix M has the singular-value (Schmidt) decomposition $M = QDP^t$, where D is a nonnegative diagonal matrix, which represents dilations, and P and Q are orthogonal matrices, which represent basis changes [10]. In Eq. (39), the dilation matrix is replaced by a boost matrix, and three-dimensional orthogonal transformations are replaced by two-dimensional rotations (which are simpler). In the context of Lorentz transformations, the Schmidt-like decomposition (39) is even more useful than the Schmidt decomposition.

Let $L = [l_{ij}]$, where i and j vary from 0 to 2. Then it follows from the first line of Eq. (38) that the energy

$$\gamma = l_{00}. \quad (40)$$

The input and output angles are specified implicitly by the equations

$$\tan(\theta_1) = l_{02}/l_{01}, \quad \tan(\theta_2) = l_{20}/l_{10}, \quad (41)$$

and the difference angle is specified by the equations

$$(\gamma + 1) \cos(\theta_{21}) = l_{11} + l_{22}, \quad (42)$$

$$(\gamma + 1) \sin(\theta_{21}) = l_{21} - l_{12}, \quad (43)$$

from which it follows that

$$\tan(\theta_{21}) = (l_{21} - l_{12})/(l_{11} + l_{22}). \quad (44)$$

If one is presented with a Lorentz matrix (a boost or rotation matrix, or a combination of such matrices), one can read off the energy, and determine the input, output and difference angles, with little effort.

Before proceeding further, two remarks are in order. First, (in two dimensions) rotation matrices satisfy the product rule $R(\theta_2)R(\theta_1) = R(\theta_2 + \theta_1)$. It follows from this rule and Eq. (39) that

$$R(\theta_3)L(\gamma, \theta_1, \theta_2)R^t(\theta_3) = L(\gamma, \theta_1 + \theta_3, \theta_2 + \theta_3). \quad (45)$$

The similarity transform of a Lorentz matrix is another Lorentz matrix. This transformation changes the input and output angles in simple ways, but does not change the difference angle or the energy. Notice that if $\theta_3 = -\theta_1$, the transformed matrix depends only on the difference angle θ_{21} .

Second, consider the transformation equation $Y = LX$, where (temporarily) X and Y play the roles of T and T' , respectively. If one decides to work in terms of the rotated vectors $X' = R^tX$ and $Y' = R^tY$, then $Y' = L'X'$, where $L' = R^tLR$. The inverse of the last equation is $L = RL'R^t$.

Now consider the composition of two arbitrary boosts, which are specified by the energies γ_1 and γ_2 , and the direction angles θ_1 and θ_2 . In a (rotated) frame that is aligned with the first boost, the first boost angle is 0 and the second boost angle is the difference angle θ_{21} . The product matrix

$$\begin{aligned} B'_2 B'_1 &= \begin{bmatrix} \gamma_2 & u_2 c & u_2 s \\ u_2 c & 1 + \delta_2 c^2 & \delta_2 cs \\ u_2 s & \delta_2 cs & 1 + \delta_2 s^2 \end{bmatrix} \begin{bmatrix} \gamma_1 & u_1 & 0 \\ u_1 & \gamma_1 & 0 \\ 0 & 0 & 1 \end{bmatrix} \\ &= \begin{bmatrix} \gamma_2 \gamma_1 + u_2 u_1 c & \gamma_2 u_1 + u_2 \gamma_1 c & u_2 s \\ (u_2 \gamma_1 + \delta_2 u_1 c)c + u_1 & (u_2 u_1 + \delta_2 \gamma_1 c)c + \gamma_1 & \delta_2 cs \\ (u_2 \gamma_1 + \delta_2 u_1 c)s & (u_2 u_1 + \delta_2 \gamma_1 c)s & 1 + \delta_2 s^2 \end{bmatrix}, \end{aligned} \quad (46)$$

where c and s are abbreviations of c_{21} and s_{21} , respectively. It follows from Eqs. (40) and

(46) that the composite energy

$$\gamma' = \gamma_2\gamma_1 + u_2u_1c. \quad (47)$$

It follows from Eqs. (41) and (46) that the composite input and output angles are specified by the equations

$$\tan(\phi') = \frac{u_2s}{\gamma_2u_1 + u_2\gamma_1c}, \quad \tan(\theta') = \frac{(u_2\gamma_1 + \delta_2u_1c)s}{u_1 + (u_2\gamma_1 + \delta_2u_1c)c}, \quad (48)$$

respectively. (When discussing product matrices, it is easier to use different symbols for the input and output angles.) In the context of combined boosts, the difference angle $(\theta' - \phi')$ is called the Wigner angle (θ'_w) . It follows from Eqs. (44) and (46) that the Wigner angle is specified by the equation

$$\tan(\theta'_w) = \frac{(u_2u_1 + \delta_2\delta_1c)s}{\gamma_2 + \gamma_1 + (u_2u_1 + \delta_2\delta_1c)c}. \quad (49)$$

According to Eq. (45), in the (unrotated) laboratory frame, the input and output angles

$$\phi = \phi' + \phi_1, \quad \theta = \theta' + \phi_1, \quad (50)$$

respectively. Backward rotation does not change the energy or difference angle, so Eq. (47) is the well-known formula for the combined energy γ and Eq. (49) is the sought-after formula for the Wigner angle θ_w . It is consistent with Eqs. (24) and (25).

Now consider Lorentz transformations in time and three space dimensions. The special orthogonal group $SO(1,3)$ is the set of real 4×4 matrices L that satisfy the Lorentz condition $L^tSL = S$, where $S = \text{diag}(1, -1, -1, -1)$, and have determinant 1. $SO(1,3)$ has six fundamental matrices, which represent boosts along the x , y and z axes, and rotations about the x , y and z axes. Every Lorentz matrix can be written in the form of matrix (37), in which C is a 3×1 column vector, R is a 1×3 row vector and N is the 3×3 rotation matrix that converts (rotates) R^t to C . This matrix involves two polar angles, which specify the axis of rotation, and one rotation angle, which is the analog of the Wigner angle.

It is easy to verify that

$$\bar{N}_2 L \bar{N}_1^t = \begin{bmatrix} 1 & 0 \\ 0 & N_2 \end{bmatrix} \begin{bmatrix} \gamma & R \\ C & N + \epsilon CR \end{bmatrix} \begin{bmatrix} 1 & 0 \\ 0 & N_1^t \end{bmatrix}$$

$$\begin{aligned}
&= \begin{bmatrix} \gamma & RN_1^t \\ N_2C & N_2NN_1^t + \epsilon N_2CRN_1^t \end{bmatrix} \\
&= \begin{bmatrix} \gamma & R_1 \\ C_2 & N_{21} + \epsilon C_2R_1 \end{bmatrix}, \tag{51}
\end{aligned}$$

where $C_2 = N_2C$ is the new column vector, $R_1 = RN_1^t = (N_1R^t)^t$ is the new row vector and $N_{21} = N_2NN_1^t$ is the new rotation matrix. (Although rotation matrices do not commute in three dimensions, it remains true that the product of rotation matrices is another rotation matrix.) It follows from the identity $C = NR^t$ that $C_2 = N_2N(N_1^tN_1)R^t = (N_2NN_1^t)R_1^t$, so N_{21} is the matrix that rotates R_1^t to C_2 . Thus, the generalized similarity transform of a general Lorentz matrix is another general Lorentz matrix. This transformation changes the row and column momentum vectors in simple ways, but does not change the energy. The relation $N \rightarrow N_2NN_1^t$ is the three-dimensional analog of the two-dimensional relation $\theta_w \rightarrow \theta_w + \theta_2 - \phi_1$ [Eqs. (91) and (101)]. If the input matrix $L = B_x$ represents a boost in the x direction ($C^t = R = [1, 0, 0]$), then the output matrix is a general matrix [Eq. (37)] and Eq. (51) is its Schmidt-like decomposition [Eq. (39)].

4. SU(1,1) and SO(1,2)

In this section, we introduce the special unitary group SU(1,1) and demonstrate the local isomorphism between SU(1,1) and SO(1,2), which is known. This structural similarity allows one to derive results for SU(1,1) and deduce the corresponding results for SO(1,2), without further effort. Before proceeding with this demonstration, it is helpful to describe a similar relation between SU(2) and SO(3), which is better known.

The special unitary group SU(2) is the set of complex 2×2 matrices U that satisfy the unitarity condition $U^\dagger U = I$. If A is a complex 2×1 vector on which U acts, then the unitarity condition ensures that the inner product (norm) $A^\dagger A$ is conserved. In polarization optics [11, 12, 13], $A = [A_x, A_y]^t$ is the amplitude vector of a wave and the norm is its power (photon flux). The set of amplitude vectors forms a vector space under addition, which is called Jones space.

The special orthogonal group SO(3) is the set of real 3×3 matrices R that satisfy the orthogonality condition $R^t R = I$. If X is a real 3×1 vector on which R acts, then the orthogonality condition ensures that the norm $X^t X$ is conserved. In three-dimensional rotations, the vector $X = [x, y, z]$ is the position vector and the norm is its squared length. The set of position vectors forms a vector space, which (in relation to polarization optics) is called Stokes space.

Polarization transformations are locally isomorphic to (have the same local structure as) three-dimensional rotations [9, 11]. The fundamental transformations in Jones space (real and complex beam-splitter transformations, and a differential phase shift) correspond to fundamental transformations in Stokes space (rotations about the x , y and z axes). One can use the correspondence between the associated fundamental matrices to derive results (including product rules) for polarization transformations and deduce the corresponding results for rotations. For SU(2) and SO(3), this local-isomorphism method simplifies the calculations significantly [9, 14], which is why it is well known and often used.

The main subject of this section, which is the local isomorphism between SU(1,1) and SO(1,2), was discussed in [15, 16, 17, 18]. The authors' analyses are mathematical, but clear, so it would be pointless to repeat them here. Instead, we will take an empirical approach and demonstrate the local isomorphism directly.

The special unitary group $SU(1,1)$ is the set of complex 2×2 matrices M that satisfy the equivalent conditions

$$M^\dagger S M = S, \quad M^{-1} = S M^\dagger S, \quad (52)$$

where the metric matrix $S = \text{diag}(1, -1)$. They also satisfy the (special) condition $\det(M) = 1$. The first of Eqs. (52) is called the indefinite unitarity condition, because the metric matrix is indefinite (has positive and negative components). If A is a complex 2×1 vector on which M acts, then the indefinite unitarity condition ensures that the generalized inner product $A^\dagger S A$ is conserved. The set of vectors (spinors) forms a vector space, which is called spinor space [15, 16]. (This space has the same vectors as Jones space, but a different inner product.)

In three-wave mixing [19], which occurs in second-order nonlinear media, a strong pump wave drives weak signal and idler waves ($\pi_p \rightarrow \pi_s + \pi_i$, where π_i represents a photon with frequency ω_i). Similarly, in four-wave mixing [20], which occurs in third-order nonlinear media, one or two strong pump waves drive weak signal and idler waves ($2\pi_p \rightarrow \pi_s + \pi_i$ or $\pi_p + \pi_q \rightarrow \pi_s + \pi_i$). In each process, signal and idler photons are produced in pairs, so the difference between the signal and idler powers (photon fluxes) is constant. In the strong-pump approximation, the pump power(s) is (are) constant, and the coupled equations for the signal and idler amplitudes are linear. The amplitude vector $A = [A_s, A_i^*]^t$ and the inner product is the signal-idler power (flux) difference.

Examples of indefinite unitary matrices include the boost-like matrices

$$B_1 = \begin{bmatrix} \mu_1 & \nu_1 \\ \nu_1 & \mu_1 \end{bmatrix}, \quad B_2 = \begin{bmatrix} \mu_2 & i\nu_2 \\ -i\nu_2 & \mu_2 \end{bmatrix}, \quad (53)$$

where μ_i and ν_i are real parameters that satisfy the auxiliary equation $\mu_i^2 - \nu_i^2 = 1$, and the differential phase-shift matrix

$$P_3 = \begin{bmatrix} e_3 & 0 \\ 0 & e_3^* \end{bmatrix}, \quad (54)$$

where $e_3 = \exp(i\phi_3)$. These matrices describe a real boost, a complex boost and a differential phase shift, respectively. Matrices (53) are not Lorentz boost matrices, but we use the term because the identity $\mu^2 - \nu^2 = 1$ is equivalent to $\gamma^2 - u^2 = 1$. This identity allows one to write $\mu = \cosh(\zeta)$ and $\nu = \sinh(\zeta)$, where ζ is the boost parameter.

$SU(1,1)$ is closed under multiplication, so the products of indefinite unitary matrices are also indefinite unitary matrices. For example, consider the product matrix

$$\begin{aligned} M(\mu, \phi) &= P(\phi)B_1(\mu)P^\dagger(\phi) \\ &= \begin{bmatrix} \mu & \nu e_\phi^2 \\ \nu(e_\phi^*)^2 & \mu \end{bmatrix}. \end{aligned} \quad (55)$$

We will refer to all such matrices as boost matrices, because they are similarity transforms of the real boost matrix. Such transformations do not affect the magnitude or phase of μ . In the same way that a Lorentz boost in the y direction is a rotated version of a boost in the x direction [Eq. (35) with $\phi = \pi/2$], the complex boost is a phase-shifted version of the real boost [Eq. (55) with $\phi = \pi/4$].

By applying the indefinite unitarity condition (52) to a matrix M and demanding that $\det(M) = 1$ [rather than $\exp(i\psi)$], one can show that every indefinite unitary matrix can be written in the form

$$M = \begin{bmatrix} \mu & \nu \\ \nu^* & \mu^* \end{bmatrix}, \quad (56)$$

where μ and ν are (temporarily) complex parameters that satisfy the auxiliary equation $|\mu|^2 - |\nu|^2 = 1$. Matrix (56) is specified by the free parameters $|\mu|$, ϕ_μ and ϕ_ν . Matrix (55) has the generalization

$$\begin{aligned} M(\mu, \phi_1, \phi_2) &= P(\phi_2)B_1(\mu)P^\dagger(\phi_1) \\ &= \begin{bmatrix} \mu e_2 e_1^* & \nu e_2 e_1 \\ \nu e_2^* e_1^* & \mu e_2^* e_1 \end{bmatrix}, \end{aligned} \quad (57)$$

where $e_i = \exp(i\phi_i)$. By comparing matrices (56) and (57), one finds that they have the same form, in which the components in the bottom row are conjugates of components in the top row. The equivalence conditions are $\mu_c = \mu_r e_2 e_1^*$ and $\nu_c = \nu_r e_2 e_1$, where the subscripts c and r stand for complex and real, respectively. If matrix (56) is specified, then

$$\mu_r = |\mu_c|, \quad \phi_1 = (\phi_\nu - \phi_\mu)/2, \quad \phi_2 = (\phi_\mu + \phi_\nu)/2, \quad (58)$$

whereas if matrix (57) is specified, then

$$|\mu_c| = \mu_r, \quad \phi_\mu = \phi_2 - \phi_1, \quad \phi_\nu = \phi_2 + \phi_1. \quad (59)$$

The preceding results show that every indefinite unitary matrix has the Schmidt-like decomposition

$$M = P(\phi_2)B(\mu)P^\dagger(\phi_1), \quad (60)$$

where $B = B_1$ is a real boost matrix and $P_i = P(\phi_i)$ is a phase-shift matrix. The parameters μ , ϕ_1 and ϕ_2 , which are specified by Eqs. (58), are called the boost strength, and the input and output phase-angles (phases), respectively. Notice that the difference phase $\phi_2 - \phi_1 = \phi_\mu$. This phase is also called the Wigner phase. It is easy to verify that

$$P(\phi_3)M(\mu, \phi_1, \phi_2)P^\dagger(\phi_3) = M(\mu, \phi_1 + \phi_3, \phi_2 + \phi_3). \quad (61)$$

The similarity transform of an indefinite unitary matrix is another indefinite unitary matrix. This transformation changes the input and output phases in simple ways, but does not change the difference (Wigner) phase or the boost strength. Notice the similarities between Eqs. (39) and (60), and Eqs. (45) and (61).

Let X and Y be column vectors, and consider the transformation $Y = MX$. If one decides to work with the phase-shifted vectors $X' = P^\dagger X$ and $Y' = P^\dagger Y$, then $Y' = M'X'$, where $M' = P^\dagger MP$. The inverse of the last equation is $M = PM'P^\dagger$.

Now consider the composition of two boosts, which are specified by the boost strengths μ_1 and μ_2 , and the phases ϕ_1 and ϕ_2 . and suppose that

$$Y = (P_2 B_2 P_2^\dagger)(P_1 B_1 P_1^\dagger)X. \quad (62)$$

Then, as explained above, this equation can be rewritten as $Y' = M'X'$, where the primed vectors $X' = P_1^\dagger X$ and $Y' = P_1^\dagger Y$, and the primed matrix

$$M' = (P_1^\dagger P_2)B_2(P_2^\dagger P_1)B_1. \quad (63)$$

The first three matrices on the right side of Eq. (63) represent a complex boost, with phase $\phi_{21} = \phi_2 - \phi_1$ [Eq. (55)]. Hence, the primed matrix

$$\begin{aligned} M' &= \begin{bmatrix} \mu_2 & \nu_2 f_{21} \\ \nu_2 f_{21}^* & \mu_2 \end{bmatrix} \begin{bmatrix} \mu_1 & \nu_1 \\ \nu_1 & \mu_1 \end{bmatrix}, \\ &= \begin{bmatrix} \mu_2 \mu_1 + \nu_2 \nu_1 f_{21} & \mu_2 \nu_1 + \nu_2 \mu_1 f_{21} \\ \mu_2 \nu_1 + \nu_2 \mu_1 f_{21}^* & \mu_2 \mu_1 + \nu_2 \nu_1 f_{21}^* \end{bmatrix}, \end{aligned} \quad (64)$$

where $f_{21} = \exp(i2\phi_{21})$. It follows from Eqs. (56) and (64) that the squared boost parameters

$$|\mu'|^2 = \mu_2^2\mu_1^2 + \nu_2^2\nu_1^2 + 2\mu_2\nu_2\mu_1\nu_1d_{21}, \quad (65)$$

$$|\nu'|^2 = \mu_2^2\nu_1^2 + \nu_2^2\mu_1^2 + 2\mu_2\nu_2\mu_1\nu_1d_{21}, \quad (66)$$

where $d_{21} = \cos(2\theta_{21})$. (d stands for double and is the letter that follows c .) It is easy to verify that the difference $|\mu'|^2 - |\nu'|^2 = 1$ (as it should do) and the sum

$$|\mu'|^2 + |\nu'|^2 = (\mu_2^2 + \nu_2^2)(\mu_1^2 + \nu_1^2) + (2\mu_2\nu_2)(2\mu_1\nu_1)d_{21}. \quad (67)$$

One can use $|\mu'|^2$, $|\nu'|^2$ or $|\mu'|^2 + |\nu'|^2$ to quantify the boost strength. The component phases are specified implicitly by the equations

$$\tan(\phi'_\mu) = \frac{\nu_2\nu_1t_{21}}{\mu_2\mu_1 + \nu_2\nu_1d_{21}}, \quad \tan(\phi'_\nu) = \frac{\nu_2\mu_1t_{21}}{\mu_2\nu_1 + \nu_2\mu_1d_{21}}, \quad (68)$$

where $t_{21} = \sin(2\phi_{21})$. (t is the letter that follows s .) In the context of combined boosts, it is better to use separate symbols for the input phase ϕ' and the output phase θ' . It follows from Eqs. (58) and (68) that

$$\tan(2\phi') = \frac{\mu_2\nu_2t_{21}}{(\mu_2^2 + \nu_2^2)\mu_1\nu_1 + \mu_2\nu_2(\mu_1^2 + \nu_1^2)d_{21}}, \quad (69)$$

$$\tan(2\theta') = \frac{[\mu_2\nu_2(\mu_1^2 + \nu_1^2) + 2\nu_2^2\mu_1\nu_1d_{21}]t_{21}}{\mu_1\nu_1 + [\mu_2\nu_2(\mu_1^2 + \nu_1^2) + 2\nu_2^2\mu_1\nu_1d_{21}]d_{21}}. \quad (70)$$

The unprimed matrix $M = P_1 M' P_1^\dagger$. Written explicitly,

$$M = \begin{bmatrix} \mu_2\mu_1 + \nu_2\nu_1f_{21} & (\mu_2\nu_1 + \nu_2\mu_1f_{21})e_1^2 \\ (\mu_2\nu_1 + \nu_2\mu_1f_{21}^*)(e_1^*)^2 & \mu_2\mu_1 + \nu_2\nu_1f_{21}^* \end{bmatrix}. \quad (71)$$

It follows from Eqs. (64) and (71) that the component phases are

$$\phi_\mu = \phi'_\mu, \quad \phi_\nu = \phi'_\nu + 2\phi_1, \quad (72)$$

and it follows from Eqs. (58) and (71) that the input and output phases are

$$\phi = (\phi'_\nu - \phi'_\mu)/2 + \phi_1, \quad \theta = (\phi'_\mu + \phi'_\nu)/2 + \phi_1, \quad (73)$$

respectively. Notice that the Wigner phase $\theta - \phi = \phi'_\mu = \phi_\mu$ does not depend on ϕ_1 directly. [See the comment after Eq. (61).] Notice also that this phase is specified by the first of Eqs.

(68), which was obtained by a simple matrix multiplication. This formula is equivalent to formulas derived previously [17, 18, 21, 22].

The preceding results can be simplified slightly. As explained after Eq. (54), one can write $\mu = \cosh(\zeta) = C$ and $\nu = \sinh(\zeta) = S$. It follows from these definitions that $C^2 + S^2 = \cosh(2\zeta) = D$ and $2SC = \sinh(2\zeta) = T$. By using this notation, one can rewrite Eq. (67) as

$$D' = D_2 D_1 + T_2 T_1 d_{21}, \quad (74)$$

and one can rewrite Eqs. (69) and (70) as

$$\tan(2\phi') = \frac{T_2 t_{21}}{D_2 T_1 + T_2 D_1 d_{21}}, \quad (75)$$

$$\tan(2\theta') = \frac{[T_2 D_1 + (D_2 - 1) T_1 d_{21}] t_{21}}{T_1 + [T_2 D_1 + (D_2 - 1) T_1 d_{21}] d_{21}}, \quad (76)$$

respectively. Notice that all the arguments in these equations are double arguments. By applying a trigonometric identity to the first of Eqs. (68), and using the identities $C^2 = (D + 1)/2$ and $S^2 = (D - 1)/2$, one can show that

$$\tan(2\phi'_\mu) = \frac{[T_2 T_1 + (D_2 - 1)(D_1 - 1)d_{21}] t_{21}}{D_2 + D_1 + [T_2 T_1 + (D_2 - 1)(D_1 - 1)d_{21}] d_{21}}. \quad (77)$$

If one were to derive Eq. (77) directly ($\phi'_\mu = \theta' - \phi'$), by using Eqs. (75) and (76), one would obtain a fraction whose numerator and denominator are both proportional to $\gamma' - 1$. By canceling this common factor, one would obtain Eq. (77).

In passing, the composition of two symplectic dilations was discussed in [23]. Equations (65) and (66) are equivalent to Eqs. (86) and (87) of that paper, the first and second of Eqs. (68) are equivalent to the second and first of Eqs. (88), respectively, and Eqs. (75) and (76) are equivalent to the first and second of Eqs. (89). These equivalences are manifestations of the isomorphism between $\text{Sp}(2)$ and $\text{SU}(1,1)$, which was discussed in [9].

How do the $\text{SU}(1,1)$ results compare to the $\text{SO}(1,2)$ results? Equations (67) and (68) do not resemble Eqs. (47) and (48), but Eqs. (74) – (76) do ($D_i \leftrightarrow \gamma_i$ and $T_i \leftrightarrow u_i$). Furthermore, Eq. (77) resembles Eq. (49). The only difference between the $\text{SU}(1,1)$ formulas and the $\text{SO}(1,2)$ formulas is that the former involve double arguments, whereas the latter involve single arguments. This argument difference is caused by a normalization difference, which we now explain.

Most indefinite unitary matrices (the ones of practical interest) can be written as the exponentials of generating matrices: $M = \exp(G)$, where $G = \sum_i G_i k_i$ is a linear combination of basis generators. For $SU(1,1)$, the basis generators are

$$G_1 = \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix}, \quad G_2 = \begin{bmatrix} 0 & i \\ -i & 0 \end{bmatrix}, \quad G_3 = \begin{bmatrix} i & 0 \\ 0 & -i \end{bmatrix}. \quad (78)$$

These matrices satisfy the commutation relations

$$[G_1, G_2] = -2G_3, \quad [G_2, G_3] = 2G_1, \quad [G_3, G_1] = 2G_2, \quad (79)$$

where the commutator $[x, y] = xy - yx$. By using the identities $G_1^2 = G_2^2 = I$ and $G_3^2 = -I$, one can show that matrices (78) generate the fundamental matrices (53) and (54). In this context, the generator coefficients $k_1 = \zeta_1$, $k_2 = \zeta_2$ and $k_3 = \phi_3$.

Likewise, every indefinite orthogonal matrix of practical interest can be written in the exponential form $L = \exp(H)$, where $H = \sum_i H_i l_i$. For $SO(1,2)$, the generators

$$H_1 = \begin{bmatrix} 0 & 1 & 0 \\ 1 & 0 & 0 \\ 0 & 0 & 0 \end{bmatrix}, \quad H_2 = \begin{bmatrix} 0 & 0 & 1 \\ 0 & 0 & 0 \\ 1 & 0 & 0 \end{bmatrix}, \quad H_3 = \begin{bmatrix} 0 & 0 & 0 \\ 0 & 0 & -1 \\ 0 & 1 & 0 \end{bmatrix} \quad (80)$$

satisfy the commutation relations.

$$[H_1, H_2] = -H_3, \quad [H_2, H_3] = H_1, \quad [H_3, H_1] = H_2. \quad (81)$$

It is easy to verify that matrices (80) generate the fundamental matrices (33) and (34). In this context, $l_1 = \zeta_1$, $l_2 = \zeta_2$ and $l_3 = \theta_3$. One relates the two sets of exponential matrices by relating their coefficients k_i and l_i (so the matrices have proportional coefficients, but different generators).

The generators of $SU(1,1)$ satisfy commutation relations (79), in which the structure coefficients are ± 2 , whereas the generators of $SO(1,2)$ satisfy relations (81), in which the coefficients are ± 1 [9]. To make fair comparisons between the $SU(1,1)$ and $SO(1,2)$ results, one must replace the $SU(1,1)$ parameters ζ , ϕ and θ by $\zeta/2$, $\phi/2$ and $\theta/2$, respectively (where ϕ and θ are the input and output phases). These replacements change the double arguments in Eqs. (74) – (77) into single arguments. The modified versions of these equations are equivalent to Eqs. (47) – (49). Thus, $SU(1,1)$ is locally isomorphic to $SO(1,2)$.

If one knew in advance that $SU(1,1)$ is locally isomorphic to $SO(1,2)$, and which unitary generator corresponds to which orthogonal generator, then one would only need to derive Eqs. (68) and (72), which is easy to do ($\theta_w = \phi_\mu$). However, if one had to establish the isomorphism first, for example by showing that the relations between the generator coefficients of the product and constituent matrices are equivalent [9], then doing so, and using the $SU(1,1)$ results to deduce the corresponding $SO(1,2)$ results, would require more work than deriving the $SO(1,2)$ results directly.

In time and three space dimensions, Lorentz matrices are members of $SO(1,3)$, which is locally isomorphic to the special linear group $SL(2,C)$ [3]. In principle, one can derive results for $SL(2,C)$ and deduce the corresponding results for $SO(1,3)$.

5. Summary

To practitioners of special relativity, it is well known that the composition of two nonparallel Lorentz boosts is not another boost: It is a boost followed by a rotation. Although it is straightforward to calculate the energy and direction of the combined boost, it is difficult to calculate the rotation angle, which is called the Wigner angle. In this article, we described three ways to determine the Wigner angle.

In Sec. 2, we used the vector (tensor) formalism to analyze the composition of two boosts. Two equivalent formulas for the associated product tensor were derived. The first formula involves the momenta $\vec{u}_1$ and $\vec{u}_2$ that define the boosts [Eqs. (10) – (14)], whereas the second involves the momenta $\vec{u}_{12}$ and $\vec{u}_{21}$ that appear in the product tensor [Eqs. (15) and (19)]. The derivation of the second formula was based on the *a priori* assumption that the composition of two boosts is a boost followed by a rotation. We explained why the angle between $\vec{u}_{12}$ and $\vec{u}_{21}$ is the Wigner angle, and used the cross- and dot-products of these vectors to derive formulas for the sine and cosine of this angle [Eqs. (24) and (25)].

In Sec. 3, we used the matrix formalism to analyze the same problem. The special orthogonal group $SO(1,2)$ consists of real 3×3 matrices L that satisfy the indefinite orthogonality (Lorentz) condition $L^t S L = S$, where $S = \text{diag}(1, -1, -1)$ is the structure (metric) matrix. This condition ensures that Lorentz transformations of the coordinate vector $T = [t, x, y]^t$ preserve the inner product (squared interval) $T^t S T = t^2 - x^2 - y^2$. The Lorentz condition imposes significant constraints on Lorentz matrices, which ensure that each matrix has the Schmidt-like decomposition $L(\gamma, \theta_1, \theta_2) = R(\theta_2)B(\gamma)R^t(\theta_1)$, where $B(\gamma)$ represents a boost in the x direction with energy γ , and $R(\theta_i)$ represents a rotation through the (input or output) angle θ_i [Eqs. (37) – (39)]. This decomposition can be rewritten in the equivalent form $L(\gamma, \theta_1, \theta_2) = R(\theta_{21})B(\gamma, \theta_1)$, where $B(\gamma, \theta_1) = R(\theta_1)B(\gamma)R^t(\theta_1)$ represents a boost with direction angle θ_1 and $R(\theta_{21})$ represents a rotation through the difference (Wigner) angle $\theta_{21} = \theta_2 - \theta_1$. (The second decomposition justifies the assumption mentioned above.) If one is presented with a Lorentz matrix, decomposition (38) allows one to read off the energy [Eq. (40)], and provides equations for the input and output angles [Eqs. (41)]. It also provides equivalent equations for the cosine, sine and tangent of the Wigner angle [Eqs. (42) – (44)]. Rotating the axes used to analyze a Lorentz transformation corresponds to making a sim-

ilarity transformation of the associated Lorentz matrix [Eq. (45)]. Such a transformation changes the input and output angles in simple ways, but does not change the Wigner angle or the energy. In our analysis of two boosts, we used rotated axes to simplify the calculation of the product matrix [Eq. (46)], then converted the results from the rotated frame back to the laboratory frame. The combined energy was specified in Eq. (47), the input and output angles were specified in Eqs. (48) and (50), and the tangent of the Wigner angle was specified in Eq. (49).

In Sec. 4, we demonstrated the local isomorphism (structural similarity) between $SU(1,1)$ and $SO(1,2)$. The special unitary group $SU(1,1)$ consists of complex 2×2 matrices M that satisfy the indefinite unitarity condition $M^\dagger S M = S$, where $S = \text{diag}(1, -1)$ is the metric matrix. This condition ensures that indefinite unitary transformations of the spinor $A = [u, v]^t$ preserve the inner product $A^\dagger S A = |u|^2 - |v|^2$. The indefinite unitarity condition imposes significant constraints on indefinite unitary matrices, which ensure that each matrix has the Schmidt-like decomposition $M(\mu, \phi_1, \phi_2) = P(\phi_2) B(\mu) P^t(\phi_1)$, where $B(\mu)$ represents a real boost with strength μ , and $P(\phi_i)$ represents a differential phase shift through the (input or output) phase angle ϕ_i [Eqs. (58) and (60)]. Changing the reference phase of an indefinite unitary transformation corresponds to making a similarity transformation of the associated matrix [Eq. (55)]. Such a transformation changes the input and output phases in simple ways, but does not change the difference (Wigner) phase or the boost strength. The similarities between these results and the preceding ones are obvious. The strength of a combined boost was specified in Eq. (74), the input and output phases were specified in Eqs. (75) and (76), and the tangent of the Wigner half- and full-phases were specified in Eqs. (68) and (77). The equivalence of the indefinite unitary and orthogonal results is a manifestation of the local isomorphism between $SU(1,1)$ and $SO(1,2)$. For the problem considered (composition of boosts), the indefinite unitary and orthogonal analyses were of comparable difficulty.

Finally, for completeness, the composition of two arbitrary transformations is discussed in the appendix. The analysis of this general problem is no more difficult than that of the special problem described above.

In conclusion, we described three methods to determine the Wigner angle, all of which

work well. Although the indirect (local isomorphism) method significantly simplifies the analysis of rotations in three dimensions [9, 14], it does not simplify the analysis of Lorentz transformations in time and two space dimensions, because the direct (matrix and vector) methods are straightforward to implement.

Appendix: Two arbitrary transformations

In this appendix, we generalize the analysis of Sec. 4, which applied to the composition of two boosts. For two arbitrary $SU(1,1)$ transformations,

$$Y = (Q_2 B_2 P_2^\dagger)(Q_1 B_1 P_1^\dagger)X. \quad (82)$$

Equation (71) can be written in the form $Y = M_4 X$, where the final matrix $M_4 = Q_2 M_3 P_1^\dagger$ and the intermediate matrix $M_3 = B_2(P_2^\dagger Q_1)B_1$. In the last equation, $P_2^\dagger Q_1 = P^\dagger(\phi_{21})$, where $\phi_{21} = \phi_2 - \theta_1$. Written explicitly,

$$\begin{aligned} M_3 &= \begin{bmatrix} \mu_2 & \nu_2 \\ \nu_2 & \mu_2 \end{bmatrix} \begin{bmatrix} e_{21}^* & 0 \\ 0 & e_{21} \end{bmatrix} \begin{bmatrix} \mu_1 & \nu_1 \\ \nu_1 & \mu_1 \end{bmatrix} \\ &= \begin{bmatrix} \mu_2 \mu_1 e_{21}^* + \nu_2 \nu_1 e_{21} & \mu_2 \nu_1 e_{21}^* + \nu_2 \mu_1 e_{21} \\ \nu_2 \mu_1 e_{21}^* + \mu_2 \nu_1 e_{21} & \mu_2 \mu_1 e_{21} + \nu_2 \nu_1 e_{21}^* \end{bmatrix}, \end{aligned} \quad (83)$$

where $e_{21} = \exp(i\phi_{21})$. The squared boost parameters are

$$|\mu_3|^2 = \mu_2^2 \mu_1^2 + \nu_2^2 \nu_1^2 + 2\mu_2 \nu_2 \mu_1 \nu_1 (c_{21}^2 - s_{21}^2), \quad (84)$$

$$|\nu_3|^2 = \mu_2^2 \nu_1^2 + \nu_2^2 \mu_1^2 + 2\mu_2 \nu_2 \mu_1 \nu_1 (c_{21}^2 - s_{21}^2). \quad (85)$$

It is easy to verify that the difference $|\mu_3|^2 - |\nu_3|^2 = 1$ and the sum

$$|\mu_3|^2 + |\nu_3|^2 = (\mu_2^2 + \nu_2^2)(\mu_1^2 + \nu_1^2) + (2\mu_2 \nu_2)(2\mu_1 \nu_1)(c_{21}^2 - s_{21}^2). \quad (86)$$

The component phases are specified implicitly by the equations

$$\tan(\phi_{\mu_3}) = -\frac{(\mu_2 \mu_1 - \nu_2 \nu_1)s_{21}}{(\mu_2 \mu_1 + \nu_2 \nu_1)c_{21}}, \quad \tan(\phi_{\nu_3}) = \frac{(\nu_2 \mu_1 - \mu_2 \nu_1)s_{21}}{(\nu_2 \mu_1 + \mu_2 \nu_1)c_{21}}. \quad (87)$$

It follows from Eqs. (58) and (87) that the input and output phases are specified by the equations

$$\tan(2\phi_3) = \frac{2\mu_2 \nu_2 s_{21} c_{21}}{(\mu_2^2 + \nu_2^2)\mu_1 \nu_1 + \mu_2 \nu_2 (\mu_1^2 + \nu_1^2)(c_{21}^2 - s_{21}^2)}, \quad (88)$$

$$\tan(2\theta_3) = \frac{-2\mu_1 \nu_1 s_{21} c_{21}}{\mu_2 \nu_2 (\mu_1^2 + \nu_1^2) + (\mu_2^2 + \nu_2^2)\mu_1 \nu_1 (c_{21}^2 - s_{21}^2)}. \quad (89)$$

The final parameters

$$\mu_4 = \mu_3 e_2 e_1^*, \quad \phi_4 = \phi_3 + \phi_1, \quad \theta_4 = \theta_3 + \theta_2, \quad (90)$$

from which it follows that the final difference (Wigner) phase

$$\theta_{w4} = \theta_{w3} + \theta_2 - \phi_1, \quad (91)$$

where $\theta_{w3} = \theta_{\mu 3}$ was specified by the first of Eqs. (87).

By using the double-argument notation of Sec. 4, one can rewrite Eqs. (86), (88) and (89) in the forms

$$D_3 = D_2 D_1 + T_2 T_1 d_{21}, \quad (92)$$

$$\tan(2\phi_3) = \frac{T_2 t_{21}}{D_2 T_1 + T_2 D_1 d_{21}}, \quad (93)$$

$$\tan(2\theta_3) = \frac{-T_1 t_{21}}{T_2 D_1 + D_2 T_1 d_{21}}, \quad (94)$$

respectively. By using the identities $\mu_2^2 \mu_1^2 + \nu_2^2 \nu_1^2 = (D_2 D_1 + 1)/2$ and $\mu_2^2 \mu_1^2 - \nu_2^2 \nu_1^2 = (D_2 + D_1)/2$, one can rewrite the first of Eqs. (87) in the double-argument form

$$\tan(2\phi_{\mu 3}) = \frac{-(D_2 + D_1)t_{21}}{T_2 T_1 + (D_2 D_1 + 1)d_{21}}. \quad (95)$$

Notice that Eqs. (92) and (93) are identical to Eqs. (74) and (75), respectively, whereas Eq. (94) differs from Eq. (76). These results reflect the fact that $M' = P_{21} M_3$: The matrices of interest only differ by an output phase shift, so the boost strengths and input angles are equal, whereas the output angles are different. The Wigner phases also differ, but in a relatively simple way (θ'_w depends on $\phi_2 - \phi_1$ and $\theta_w = \theta'_w$, whereas θ_3 depends on $\phi_2 - \theta_1$ and $\theta_{w4} = \theta_{w3} + \theta_2 - \phi_1$). Overall, the general problem is no harder to solve than the special problem (upon which many papers have focused).

In passing, the composition of two symplectic transformations was discussed in [23]. Equations (92) – (94) are identical to Eqs. (C9), (C11) and (C12) of that paper. These identities are manifestations of the isomorphism between $\text{Sp}(2)$ and $\text{SU}(1,1)$, which was discussed in [9].

The combination of two Lorentz transformations was discussed in [8]. The input–output equation has the same form as Eq. (82), but the matrices involved are real 3×3 matrices (so $\dagger$ is replaced by t), B_i represents a boost in the x direction, and P_i and Q_i represent

rotations about the t axis (in the xy plane). The intermediate matrix

$$\begin{aligned}
L_3 &= \begin{bmatrix} \gamma_2 & u_2 & 0 \\ u_2 & \gamma_2 & 0 \\ 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} 1 & 0 & 0 \\ 0 & c & s \\ 0 & -s & c \end{bmatrix} \begin{bmatrix} \gamma_1 & u_1 & 0 \\ u_1 & \gamma_1 & 0 \\ 0 & 0 & 1 \end{bmatrix} \\
&= \begin{bmatrix} \gamma_2\gamma_1 + u_2u_1c & \gamma_2u_1 + u_2\gamma_1c & u_2s \\ u_2\gamma_1 + \gamma_2u_1c & u_2u_1 + \gamma_2\gamma_1c & \gamma_2s \\ -u_1s & -\gamma_1s & c \end{bmatrix}, \tag{96}
\end{aligned}$$

where $c = \cos(\phi_2 - \theta_1)$ and $s = \sin(\phi_2 - \theta_1)$. This matrix is the product of Lorentz matrices, so it is also a Lorentz matrix, with the decomposition $L_3 = Q_3(\theta_3)B_3(\gamma_3)P_3^t(\phi_3)$.

It follows from Eqs. (40) and (96) that the intermediate energy

$$\gamma_3 = \gamma_2\gamma_1 + u_2u_1c, \tag{97}$$

which is a symmetric function of γ_1 and γ_2 , and depends on the difference angle $\phi_2 - \theta_1$. According to Eq. (38), the first row of the product matrix is $[\gamma_3, u_3c_\phi, u_3s_\phi]$, where $c_\phi = \cos(\phi_3)$, and the first column is $[\gamma_3, u_3c_\theta, u_3s_\theta]^t$, where $c_\theta = \cos(\theta_3)$. The definitions of s_ϕ and s_θ are similar. It follows from Eqs. (41) and (96) that the intermediate input and output angles are specified implicitly by the equations

$$\tan(\phi_3) = \frac{u_2s}{\gamma_2u_1 + u_2\gamma_1c}, \quad \tan(\theta_3) = \frac{-u_1s}{u_2\gamma_1 + \gamma_2u_1c}. \tag{98}$$

It follows from Eqs. (44) and (96) that the intermediate difference angle is specified by the equation

$$\tan(\theta_3 - \phi_3) = \frac{-(\gamma_2 + \gamma_1)s}{u_2u_1 + (\gamma_2\gamma_1 + 1)c}. \tag{99}$$

If one were to derive Eq. (99) directly, by using Eqs. (98), one would obtain a fraction whose numerator and denominator are both proportional to $\gamma_3 - 1$. By canceling this common factor, one would obtain Eq. (99).

The final matrix $L_4 = Q_2(\theta_2)L_3(\gamma_3, \phi_3, \theta_3)P_1^t(\phi_1)$, from which it follows that

$$\gamma_4 = \gamma_3, \quad \phi_4 = \phi_1 + \phi_3, \quad \theta_4 = \theta_2 + \theta_3. \tag{100}$$

It also follows that

$$\theta_4 - \phi_4 = \theta_3 - \phi_3 + \theta_2 - \phi_1. \tag{101}$$

Equations (97) – (101) are valid for arbitrary transformations (combinations of boosts and rotations). They are the product rules for Lorentz matrices, written in terms of the Schmidt-like parameters γ , ϕ and θ . In particular, Eqs. (99) and (101) specify the difference (Wigner) angle. Given the complexity of matrices of the form (38), it is remarkable that the product rules and the difference formula are so simple.

As we explained in the text, the generators of $SU(1,1)$ and $SO(1,2)$ have different normalizations. To make a fair comparison between results for $SU(1,1)$ and $SO(1,2)$, one must replace the $SU(1,1)$ coefficients ζ , ϕ and θ by $\zeta/2$, $\phi/2$ and $\theta/2$, respectively. These replacements change the double arguments in Eqs. (92) – (94) into single arguments, like the ones in Eqs. (97) and (98). The $SU(1,1)$ and $SO(1,2)$ equations are equivalent, because the groups are locally isomorphic. Although one could use this relation to deduce the $SO(1,2)$ formulas from the $SU(1,1)$ formulas, the $SO(1,2)$ calculation is straightforward by itself, so no deduction is necessary.

References

- [1] English translations of key papers by A. Einstein, H. A. Lorentz, H. Minkowski and H. Weyl are contained in the compendium *Principle of Relativity* (Dover, 1923).
- [2] H. Goldstein, C. Poole and J. Safko, *Classical Dynamics, 3rd Ed.* (Addison-Wesley, 2002). See Chap. 7.
- [3] J. D. Jackson, *Classical Electrodynamics, 3rd Ed.* (Wiley, 1999). See Chap. 11.
- [4] L. D. Landau and E. M. Lifshitz, *Classical Theory of Fields, 4th Ed.* (Pergamon, 2013). See Chap. 1.
- [5] E. P. Wigner, “On unitary representations of the inhomogeneous Lorentz group,” *Ann. Math.* **40**, 149–204 (1939).
- [6] J. T. Cushing, “Vector Lorentz transformations,” *Am. J. Phys.* **35**, 858–862 (1967). Factors of $1/v^2$ are missing from the last terms in Eqs. (16a), (27) and (29b).
- [7] A. Ben-Menahem, “Wigner’s angle revisited,” *Am. J. Phys.* **53**, 62–66 (1985). See Eqs. (10) and (13).
- [8] C. J. McKinstrie and M. V. Kozlov, “Lorentz transformations in time and two space dimensions,” submitted for publication (arXiv.2508.1702). The general form of a Lorentz matrix is derived in Sec. 3.5, and combinations of boosts and arbitrary transformations are discussed in Sec. 3.9. The vector formalism for Lorentz transformations is described in Apps. B and C.
- [9] C. J. McKinstrie and M. V. Kozlov, “Exponentiation and decomposition of common operators 1: Classical applications,” *J. Mod. Opt.* **73**, 754–786 (2026), doi.org/10.1080/09500340.2026.2628812. The isomorphism between $\text{Sp}(2)$ and $\text{SU}(1,1)$, and the local isomorphism between $\text{Sp}(2)$ and $\text{SO}(1,2)$, are discussed in Secs. 6.1 and 6.2, respectively. The local isomorphism between $\text{SU}(2)$ and $\text{SO}(3)$ is discussed in Sec. 6.3, and the analog of the Jones–Stokes formalism for $\text{SU}(1,1)$ and $\text{SO}(1,2)$ is discussed in App. F.
- [10] C. A. Horn and C. R. Johnson, *Matrix Analysis, 2nd Ed.* (Cambridge, 2013).

- [11] J. P. Gordon and H. Kogelnik, “PMD fundamentals: Polarization mode dispersion in optical fibers,” *Proc. Nat. Acad. Sci.* **97**, 4541–4550 (2000).
- [12] D. H. Goldstein, *Polarized Light, 3rd Ed.* (CRC Press, 2011).
- [13] R. Chipman, W. S. T Lam and G. Young, *Polarized Light and Optical Systems* (CRC Press, 2018).
- [14] A. H. J. de Ruiter, C. J. Damaren and J. R. Forbes, *Spacecraft Dynamics and Control: An Introduction* (Wiley, 2013). See pp. 27 – 32.
- [15] R. Penrose and W. Rindler, *Spinors and Space–Time, Vol. 1* (Cambridge, 1984).
- [16] C. W. Misner, K. S. Thorne and J. A. Wheeler, *Gravitation* (Princeton, 2017).
- [17] G. F. Torres del Castillo, “Application of double numbers in the representation of the Lorentz transformations,” *Rev. Mex. Fis.* **20**, 010204 (2023) and references therein. See Eqs. (24) and (25).
- [18] G. F. Torres del Castillo, “Application of the $SU(1, 1)$ spinors in the study of the Lorentz transformations,” *Rev. Mex. Fis.* **20**, 040701 (2023). See Eq. (22).
- [19] R. W. Boyd, *Nonlinear Optics, 4th Ed.* (Elsevier, 2020).
- [20] M. E. Marhic, *Fiber Optical Parametric Amplifiers, Oscillators and Related Devices* (Cambridge, 2008).
- [21] C. B. van Wyk, “Rotation associated with the product of two Lorentz transformations,” *Am. J. Phys.* **52**, 853–854 (1984). See Eq. (6).
- [22] J. A Rhodes and M. D. Semon, “Relativistic velocity space, Wigner rotation and Thomas precession,” *Am. J. Phys.* **72**, 943–960 (2004). See Eq. (145).
- [23] C. J. McKinstrie and M. V. Kozlov, “Introduction to the symplectic group $Sp(2)$,” *Can. J. Phys.* **104**, 1–14 (2026), doi.org/10.1139/cjp-2025-0267. Compositions of dilations and arbitrary transformations are discussed in Sec. 4 and App. C, respectively.