

Circuit for Shor's algorithm using $2n+3$ qubits

Stephane Beauregard

Abstract

We try to minimize the number of qubits needed to factor a number of n bits using Shor's algorithm on a quantum computer. The best we could achieve was a circuit with $2n+3$ qubits and $O(n^3 \lg(n))$ quantum gates, but with a depth of $O(n^3)$. The circuit is computable in polynomial time on a classical computer and is completely general as it does not rely on any properties of the number to be factored.

1 Introduction

Since Shor [1] discovered a polynomial time algorithm for factorization on a quantum computer, a lot of effort has been directed at building a working quantum computer. Despite all these efforts, it is still extremely difficult to control even a few qubits. It is thus of great interest to study exactly how few qubits do we need to factor a number of n bits.

Quantum factorization consists of classical preprocessing, a quantum algorithm for order-finding and classical postprocessing [1, 2] (e.g. 1). We will concentrate on the quantum part of factorization and consider classical parts as being free as long as they are computable in polynomial time. The only use of quantum computation in Shor's algorithm is to find the order of x modulo N , where N is an n -bits integer that we want to factor. The order r of x modulo N is the least positive integer such that $x^r \equiv 1 \pmod{N}$.

It should be noted that finding the order of x modulo N is the same as finding the period of the function $f(y) = (xy) \pmod{N}$. For completeness, we give the full algorithm as given in [2] for factoring N here:

Département de Physique et Département d'Informatique et de Recherche Opérationnelle, Université de Montréal, beaurest@iro.umontreal.ca. Supported by NSERC.




Figure 1: The order-finding circuit for quantum factorization. U_a implements $x \mapsto j(ax) \bmod N$ and the measurements followed by classical postprocessing yields the order r of $a \bmod N$ with good probability.

1. If N is even, return the factor 2.
2. Classically determine if $N = p^q$ for $p \leq 1$ and $q \leq 2$ and if so return the factor p (this can be done in polynomial time).
3. Choose a random number a such that $1 < a < N - 1$. Using Euclid's algorithm, determine if $\gcd(a; N) > 1$ and if so, return the factor $\gcd(a; N)$.
4. Use the order-finding quantum algorithm to find the order r of $a \bmod N$.
5. If r is odd or r is even but $a^{r/2} \not\equiv \pm 1 \pmod{N}$, then go to step 3. Otherwise, compute $\gcd(a^{r/2} - 1; N)$ and $\gcd(a^{r/2} + 1; N)$. Test to see if one of these is a non-trivial factor of N , and return the factor if so.

It can be shown that with probability at least one half, r will be even and $a^{r/2} \not\equiv \pm 1 \pmod{N}$ [2]. The quantum part of the algorithm (step 4) is known to be computable in polynomial time on a quantum computer, however the exact time required depends on the exact implementation. The other important aspect of the implementation is the total number of qubits needed to run the quantum part of the algorithm. We concentrate on reducing the number of qubits while keeping track of the number of quantum gates in the quantum circuit and of its depth, which is related to the running time of the algorithm.




Figure 2: The quantum addition as described by Daper [4].

2 The circuit

The circuit for factorization that will be discussed here is derived from a quite straightforward circuit from Vedral, Barenco and Ekert [3]. To reduce the number of qubits, we use a variant of a quantum addition algorithm described in Daper [4] (Fig. 2). This quantum addition takes as input n qubits representing a number a , and n more qubits containing the quantum Fourier transform of another number b , noted $\phi(b)$. After the addition the first register keeps the same value a but the bottom register now contains the quantum Fourier transform of $(a + b) \bmod 2^n$, noted $\phi(a + b)$.




Figure 3: The circuit for addition of a classical value a to the quantum value b in the Fourier space. The gates A_i are classically computed combinations of phase shifts.

2.1 The adder gate

Adding two quantum registers is, however, more than we ask for. What we need is to find the period of the function $(ax) \bmod N$ where a is a classical random number smaller than N . Since a is classical, we only need to be able to add a classical value to a quantum register, which is quite easier. We only have to change the qubits representing a in figure 2 to classical bits. The controlled gates are then classically controlled, and since we know what a is beforehand, we might as well precompute the product of all gates on each single qubit and apply only one gate for every single qubit (fig. 3). These are one-qubit gates, which also makes them easier to implement.

Since the addition takes place in the Fourier space, we will call this network the $\text{ADD}(a)$ where a is the classical value added to the quantum register. In order to prevent overflow, we need $n + 1$ qubits for the quantum register instead of n , so that $|b\rangle$ is effectively the QFT of an $(n + 1)$ -qubit register containing a n bit number (thus the most significant qubit before the QFT preceding the addition is always $|0\rangle$).




Figure 4: The reverse $\text{ADD}(a)$ gate.

If we run this $\text{ADD}(a)$ backward with input $|b\rangle$, we get either $|b - a\rangle$ if $b \geq a$, or $|2^{n+1} - (a - b)\rangle$ if $b < a$. Thus if $b < a$, the most significant bit of

the answer is always 1, whereas it is always 0 if $b \geq a$. This reverse ADD (a) gate can be useful for subtraction and comparison purposes (fig. 4).




Figure 5: The doubly controlled ADD (a) MOD (N) gate with $c_1 = c_2 = 1$. If either of the control qubits is in state $|1\rangle$, the output of the gate is $|j(b)\rangle$ since $b < N$.

2.2 The modular adder gate

Now that we have a ADD (a) gate, we can use it to build a modular adder gate (fig. 5). For future use, two control qubits are included in the circuit. For the modular adder gate, we need to compute $a + b$ and subtract N if $a + b \geq N$. However, it is not so easy to implement this operation in a reversible way. The input to the ADD (a) MOD (N) gate is $|b\rangle$ with $b < N$, and the number a that we add is also smaller than N .

We begin by applying a ADD (a) gate to the register $|b\rangle$. The quantum register now contains $|a + b\rangle$ with no overflow because we were careful enough to put an extra empty qubit ($|1\rangle$) along with the value b before applying the QFT. We next run a reverse ADD (N) to get $|a + b - N\rangle$. If $a + b < N$, we did not have to subtract N but now we can determine if $a + b < N$ just by checking the most significant bit of $a + b - N$. However, to access this most significant bit we need to inverse the QFT on the whole register

containing $(a + b \bmod N)$. We can then use this qubit as the controlling qubit of a controlled-not gate acting on an ancillary qubit. It is then possible to reapply the QFT and use this ancilla as a control qubit for a $\text{ADD}(N)$ controlled gate, so that if $a + b < N$ we add back the value N that we subtracted earlier. We now have $((a + b) \bmod N)$ in the register, and we are done except for the ancilla which is now a junk bit. We have to restore it to $|0\rangle$ somehow, otherwise the computation will not be clean and the algorithm will not work¹.

Restoring the ancilla to $|0\rangle$ is no easy task if we do not want to waste qubits. We can still do it by using the identity:

$$(a + b) \bmod N = a, \quad a + b < N : \quad (1)$$

Hence, we only have to compare $(a + b) \bmod N$ with the value a using essentially the same trick as before. We run an inverse $\text{ADD}(a)$ followed by an inverse QFT to get the most significant qubit of $(a + b) \bmod N - a$. This qubit is $|1\rangle$ if $(a + b) \bmod N < a$. We apply a NOT gate on this qubit and use it as the controlling qubit of a controlled-not gate targeting the ancilla. The ancilla is thus restored to $|0\rangle$ and we can apply a NOT gate again on the control wire, followed by a QFT and a $\text{ADD}(a)$ gate on the quantum register. After this, we have a clean computation of $(a + b) \bmod N$ in the Fourier space.

Again, what we need exactly is a doubly controlled version of the $\text{ADD}(a) \bmod N$ gate. In order to reduce the complexity of the circuit, we will doubly control only the $\text{ADD}(a)$ gates instead of all the gates (g. 5). If the $\text{ADD}(a)$ gates are not performed, it is easy to verify that the rest of the circuit implements the identity on all qubits because $b < N$.

2.3 The controlled multiplier gate

The next step is to use the doubly controlled $\text{ADD}(a) \bmod N$ gate to build a controlled multiplier gate that we will call $\text{CMULT}(a) \bmod N$ (g. 6). This gate takes three inputs, $|x\rangle, |y\rangle$, and its output depends on the qubit $|z\rangle$. If $|z\rangle = |1\rangle$, the the output is $|x\rangle, |y\rangle + (ax) \bmod N$. If $|z\rangle = |0\rangle$, then the input is unchanged and stays $|x\rangle, |y\rangle$. This gate is very

¹Indeed, for the order-finding algorithm to work, we need to find the period of $(ax) \bmod N$ but the period of the garbage bits can be something else.




Figure 6: The CM ULT (a)MOD (N) gate.

straightforward to implement using doubly controlled ADD (a)MOD (N) gates. We use the identity:

$$(ax) \bmod N = (\dots((2^0 ax_0) \bmod N + 2^1 ax_1) \bmod N + \dots + 2^{n-1} ax_{n-1}) \bmod N : \quad (2)$$

Thus we only need n successive doubly controlled modular adder gates that each add a different value $(2^i a) \bmod N$ with $0 \leq i < n$ to get the CM ULT (a)MOD (N) gate. We now have a controlled gate that takes $|j\rangle$ to $|j + (ax) \bmod N\rangle$. What we would need instead is a controlled gate that takes $|j\rangle$ to $|j(ax) \bmod N\rangle$. This can however be obtained by a clever trick from reversible computing that uses two controlled multiplication gates (Fig 7).

We first apply the CM ULT (a)MOD (N) gate to $|j\rangle|x\rangle$. We follow with a SWAP between the two registers if the qubit $|j\rangle = |1\rangle$ (that is effectively a controlled-SWAP on the registers). It should be said that we only need to control-SWAP n qubits, not $n + 1$. Indeed, the most significant qubit of $(ax) \bmod N$ will always be 0 since we were careful to include one extra qubit to store the overflow in the ADD (a) gate. We then finish with the inverse of a CM ULT (a^{-1})MOD (N) circuit. The value a^{-1} , which is the inverse of $a \bmod N$, is computable classically in polynomial time using Euclid's algorithm and it always exists since a is not a factor of N . The fact that we apply the inverse of the circuit means that the circuit effectively takes $|j\rangle|x\rangle$ to $|j\rangle|j(a^{-1}x) \bmod N\rangle$.




Figure 7: The controlled- U_a gate.

The resulting gate will be called $C-U_a$ for controlled- U_a . It does nothing if $j_i = j_i$ but if $j_i = j_i$, then the two registers take the following values:

$$\begin{aligned} j_i j_i &= j_i j_i (ax) \bmod N i = j_i (ax) \bmod N i j_i \\ j_i (ax) \bmod N i j_i &= a^{-1} (ax) \bmod N i = j_i (ax) \bmod N i j_i \end{aligned} \quad (3)$$

Since the bottom register returns to j_i after the computation, we can consider this extra register as being part of the $C-U_a$ gate, thus the gate effectively takes j_i to $j_i (ax) \bmod N i$. This is exactly the gate we need to run the quantum order-finding circuit (g1). Of course, we don't need to apply $C-U_a$ n times to get $(C-U_a)^n$ because we can directly run $C-U_{a^n}$ (where $a^n \bmod N$ is computed classically) which is the same as $(C-U_a)^n$ since:

$$(a^n x) \bmod N = \underbrace{(a \dots (a (ax) \bmod N) \dots)}_{n \text{ times}} \bmod N : \quad (4)$$

2.4 The one controlling-qubit trick

The advantage of using the $C-U_{a^{2^j}}$ gates for Shor's algorithm is the fact that we don't really need the total $2n$ controlling qubits. In fact, it can be shown that only one controlling qubit is sufficient [5, 6, 7]. This is possible because the controlled- U gates all commute and the inverse QFT can be applied semi-classically. Indeed, we can get all the bits of the answer sequentially as in figure 8. Each measured bit dictates what unitary transformation we have to apply after every controlled- U steps before the next measurement. This




Figure 8: The one control qubit trick for factoring. The R gates depend on the measurement results and implement the inverse QFT.

simulates the inverse QFT followed by a measurement on all qubits as in figure 1. We save an important number of qubits this way, and in fact we need only a total of $2n + 3$ qubits to factor an n -bit number as we will show in the exact complexity analysis.

Quantum Fourier Transform




Figure 9: The exact QFT

2.5 The QFT

The implementation of the exact QFT on n qubits requires $O(n^2)$ operations [2] (g. 9). However, in physical implementations, there will always be a threshold for the gates precision. Since many phase shifts will be almost negligible, we will in practice ignore the ones with k higher than a certain threshold k_{max} . This approximate QFT is in fact very close to the exact QFT even with k_{max} logarithmic in n . In fact, it has been shown [8] that by keeping all gates R_k with $k \leq k_{max}$, the approximate QFT differs from the QFT by a multiplicative factor $e^{i\epsilon}$ where $\epsilon \leq 2^{-n} 2^{-k_{max}}$. Thus, to get the precision up to a multiplicative factor e^{ϵ} , one only needs to choose

$k_{\max} \leq O(\lg(\frac{n}{\epsilon}))$.

The implementation of the approximate QFT on n qubits requires $O(n \lg(n))$ gates. There seems to be no obvious way to reduce the depth of either the exact QFT and the approximate QFT on n qubits below $O(n)$ without using extra qubits [9]. The depth of the QFT on $n + 1$ qubits is thus $O(n)$ with the little parallelization available without extra qubits.

2.6 The controlled-SWAP




Figure 10: The controlled-SWAP gate.

The controlled-SWAP on one qubit is very easy to implement (Fig. 10). Only two controlled-not and one Toffoli are needed to perform the SWAP on two qubits controlled by a third. Thus, $O(n)$ gates are needed to control-SWAP n qubits, that is swap n qubits with n others with one control qubit.

3 Complexity analysis

We now analyze the complexity of the given circuit for performing factorization of an n -bit number N . The analysis keeps track of the number of qubits, the number of gates and the depth of the circuit. For the depth of the circuit, we consider that it will be possible to apply simultaneously different quantum gates that act on different qubits of the quantum computer. However, we consider impossible to have one qubit controlling many operations in the same step. The gates considered elementary are the following: one qubit gates, controlled-nots, two qubits conditional phase shifts, Toffoli gates and three qubits conditional phase shifts (twice controlled). It should be pointed out that all these gates can be implemented using a constant number of single qubit gates and controlled-nots [10].

The ADD(a) circuit (g. 3), where a is a classical value, requires $n + 1$ qubits and $O(n)$ single qubit gates in constant depth. The number of qubits is $n + 1$ because we need an extra qubit to prevent overflows. When a control qubit is added to the circuit, the depth becomes $O(n)$ since the conditional phase shifts have to be done sequentially. Indeed, the control qubit has to control each phase shift one at a time.

The doubly controlled ADD(a)MOD(N) circuit (g. 5) requires $n + 4$ qubits. It also requires $O(nk_{max})$ gates, but has a depth of only $O(n)$ regardless of k_{max} because the QFTs can be somewhat parallelized.

The CMULT(a)MOD(N) circuit is only n doubly controlled ADD(a)MOD(N) circuits. It thus takes $2n + 3$ qubits, $O(n^2k_{max})$ gates and a depth of $O(n^2)$ to implement the CMULT(a)MOD(N) circuit. Two of these circuits along with the controlled-SWAP are needed for the $C-U_a$ circuit.

The controlled-SWAP on n qubits requires only $O(n)$ gates and depth, so the $C-U_a$ circuit requires $2n + 3$ qubits, $O(n^2k_{max})$ gates and a depth of $O(n^2)$ again.

For the whole ordering circuit, that is the whole quantum part of Shor's algorithm, we need n of these $C-U_a$ circuits. The quantum resources needed are thus $2n + 3$ qubits, $O(n^3k_{max})$ gates and a depth of $O(n^3)$.

If we wanted to use the exact QFT, then we would take $k_{max} = n$. As we argued earlier, this would not be clever because the implementation is certain to have hardware errors anyway. We thus use the approximate QFT with in precision of the exact QFT, so we use $k_{max} = O(\lg(\frac{n}{\epsilon}))$ and the number of gates is in $O(n^3 \lg(n))$ for any fixed ϵ .

4 Conclusion

Putting together several tricks, we have developed a circuit for the quantum part of the factorization algorithm, that is the ordering algorithm, while focusing on reducing the number of qubits. The number of qubits needed is $2n + 3$ and the depth is $O(n^3)$.

Given the values a and N , this circuit gives the order r of a modulo N with probability as close to 4^{-2} as we want, depending on ϵ . Most probably, many runs of this algorithm are needed to factor a number. Also, the randomly chosen value a is hardwired in the circuit and there is a possibility (about one half) that it will be necessary to choose a new value a and run

a new ordering algorithm on it. This is not a problem if the quantum computer is a physical device where the gates are interactions controlled by a classical computer such as laser pulses on trapped ions, NMR and most implementation proposals. Indeed, the circuit can easily be classically computed. As a matter of fact, a quantum computer consisting of a physical system controlled by a classical computer is the most conceivable option at this point.

Explicit circuits for modular exponentiation have been published [3, 11] shortly after the discovery of the factorization algorithm by Shor. These circuits are however slightly less efficient than the one developed here. The interested reader should also look at [6] for an extended analysis of possible circuits for Shor's algorithm.

The author is very grateful to Michel Arseneault for many helpful comments and corrections, and would also like to thank Jose Manuel Fernandez. This work was supported in part by CSE of Canada, and the author acknowledges support from NSERC of Canada.

References

- [1] P.W. Shor, *SIAM Journal on Computing* 26 (1997) 1484. Also on quant-ph/9508027.
- [2] Michael A. Nielsen and Isaac L. Chuang, *Quantum Computation and Quantum Information*. Cambridge University Press, 2000.
- [3] V. Vedral, A. Barenco, and A. Ekert, *Physical Review A* 54 (1996) 147. Also on quant-ph/9511018.
- [4] T. Draper, quant-ph/0008033.
- [5] R. Cleve, A. Ekert, C. Mocchiavello and M. Mosca, *Proceedings of the Royal Society of London A*, 454, 339. Also on quant-ph/9708016.
- [6] C. Zalka, quant-ph/9806084.
- [7] S. Parker and M.B. Plenio, *Physical Review Letters* 85 (2000) 3049. Also on quant-ph/0001066.
- [8] D. Coppersmith, IBM Research Report No. RC19642, 1996. Also on quant-ph/0201067.

- [9] C .M oore and M .N ilsson, *SIAM Journal on Computing*, 31 (2002) 799.
Also on quant-ph/9808027.
- [10] A . Barenco, C . Bennett, R . C leve, D P . D ÷ incenzo, N . M argolus, P .
Shor, T . Sleator, J A . Sm olin and H . W eifurter, *Physical Review A* 52
3457 (1995). Also on quant-ph/9503016.
- [11] D . Beckm an, A . N . Chari, S . D evabhaktuni, and J . P reskill, *Physical
Review A* 54 (1996) 1034. Also on quant-ph/9602016.