

## Interpreting Energy as the Rate of Quantum Computation

Michael P. Frank

FAMU-FSU College of Engineering, Dept. of Electrical & Computer Engineering, 2525 Pottsdamer St., Rm. 341, Tallahassee, FL 32310, e-mail: mpf@eng.fsu.edu.

October 16, 2019

**Abstract** Over the last few decades, progress in fields such as the physical limits of computing and quantum computing has increasingly taught us that it can be helpful to think about physics itself in computational terms. For example, recent work has shown that the energy of a quantum system limits the rate at which it can perform significant computational operations, and suggests that we might validly interpret energy as in fact *being* the speed at which a system is “computing,” in some appropriate sense of the word. In this paper, we explore the precise nature of this connection. Elementary results in quantum theory show that the energy of any quantum system corresponds exactly to the angular velocity of state-vector rotation (defined in a certain natural way) in Hilbert space, and also to the rate at which the state-vector’s components (in any basis) sweep out area in the complex plane. The total angle traversed (or area swept out) corresponds to the action of the Hamiltonian operator, and we can also consider it to be a measure of “computational work,” which we will dub the *effort*. For any specific classical or quantum computational operation, we can (in principle at least) characterize the minimum effort required to perform it on a worst-case input state, and this in turn determines the minimum time required for quantum systems of a given energy to carry out that operation on worst-case inputs. We calculate the minimum effort required to carry out some basic 1-bit and  $n$ -bit quantum and classical operations in an simple unconstrained scenario.

**Key words** Time evolution operator, Margolus-Levitin theorem, Hamiltonian energy, action of the Hamiltonian operator, quantum logic gates, energy as computing, physics as computation

## Contents

1	Introduction . . . . .	2
2	Background . . . . .	4
3	Preview . . . . .	5
4	A Simple Example . . . . .	6
5	Basic Framework . . . . .	7
6	Defining Computational Effort . . . . .	9
7	Generalizing to Arbitrary Bases . . . . .	13
8	Generalizing to Time-dependent Hamiltonians . . . . .	17
9	More Abstract Scenarios . . . . .	19
10	Effort to Perform an Operation . . . . .	20
11	Specific Operations . . . . .	23
	11.1 General two-dimensional unitaries . . . . .	23
	11.2 Specific single-qubit gates . . . . .	27
	11.3 Effort required for infidelity . . . . .	29
	11.4 Higher-dimensional operations . . . . .	31
	11.5 Classical reversible and irreversible Boolean operations . . . . .	33
12	Conclusion . . . . .	34

## 1 Introduction

Over the years, the quest to characterize the fundamental physical limits of information processing has also helped to give us a deeper understanding of physics itself. For example, Shannon’s studies of the limits of communication [1] taught us that the entropy of a system can also be considered to be a measure of the expected amount of unknown or incompressible information that is encoded in the state of that system. Landauer’s [2] and Bennett’s [3] analyses of the lower limit to the energy dissipation of computational operations led to Bennett’s resolution [4] of the famous Maxwell’s demon paradox, via the realization that the demon’s record of its past perceptions is a form of physical entropy, which must be returned to the environment when that information is erased. More recently, Margolus and Levitin [5] showed that the energy of a quantum system limits the rate at which it can perform computational “operations” of a certain type, namely, transitions between distinguishable (orthogonal) quantum states. In the last few years, several highly visible articles by Lloyd and colleagues [6, 7, 8] have elaborated on this theme by suggesting that we can think of all variety of physical systems (ranging from particles and black holes to the entire universe) as comprising natural computers, with each system’s “memory capacity” given by its maximum entropy, and its “computational performance” given by its total energy. We should also note that Ed Fredkin has been promoting a universe-as-computer philosophy for many decades.

The concept of interpreting physics as computing is certainly an exciting theme to pursue, due to its promise of conceptual unification, but we would like to proceed carefully with this program, and take the time to understand the details of this potential unification more thoroughly and rigorously. While taking care to get all of the details exactly right, we would like not only to establish that a given physical

quantity “limits” or “relates to” a given informational or computational quantity, but also justify the even stronger statement that the physical quantity actually *is*, at root, a fundamentally informational or computational quantity, one that has been traditionally expressed in terms of operationally defined physical units for reasons that can be viewed as being merely historical in nature.

As one of the most famous examples of this type of conceptual progression, Rudolph Clausius [9] first defined entropy as the ratio of marginal heat to temperature,  $dS = dQ/T$ , and at the time, entropy had no further explanation. Later, Ludwig Boltzmann [10] proposed the relation  $S \propto -H = -\int f \log f d\xi$  (where  $f$  is a probability density function ranging over particle energies or velocity vectors  $\xi$ ), which was backed up by his “H-theorem” showing that  $H$  spontaneously decreases over time for statistical reasons. In subsequent decades, this relation for entropy evolved and was generalized to become Boltzmann’s eventual epitaph  $S = k \log W$ , which related entropy to the logarithm of the number of ways  $W$  of arranging a system [11].<sup>1</sup> Boltzmann’s logarithmic quantity  $H$  (in a discrete and negated form) was later recognized by Shannon and others to also be an appropriate measure of the information content of a system. But, Boltzmann’s fundamental insight regarding the nature of entropy can be viewed as having gone far beyond just *relating* a physical quantity to an information-based one. Rather, it can be viewed as telling us that physical entropy, at root, *is* really nothing but an informational quantity, one which merely manifests itself in terms of measurable physical units of heat and temperature due to the fact that these quantities themselves have an origin that is ultimately of a statistical nature, *e.g.*, heat as disorganized energy.

Indeed, the long-term quest of physics to eventually create a grand unified “theory of everything” can be viewed as the effort to eventually reveal *all* physical concepts, quantities, and phenomena as being manifestations of underlying structures and processes that are purely mathematical and statistical in nature, and that therefore have an informational/computational flavor, at least insofar as the entire realm of formal mathematics can be viewed as being a fundamentally “computational” entity. As one interesting logical conclusion of this conceptual progression, if all observed phenomena are indeed eventually explicable as being aspects of some underlying purely mathematical/computational system, then we can argue that in the end, there really is no need for a separate *physical* ontology at all any more; we could instead validly suppose that the entire “physical” world really *is* nothing but a certain (very elaborate and complex) abstract mathematical or computational object. Such a viewpoint has many attractive philosophical features, at least from the perspective of a hard-core rationalist. One prominent proponent of such musings is Tegmark, *e.g.*, see [12].

However, regardless of one’s personal feelings towards such far-ranging philosophical agendas, if we can at least show that it is self-consistent to say that a given physical quantity can be exactly identified with a given mathematical or computational quantity, then, as scientists, we can certainly all agree that the most parsimonious description of physics will indeed be one that does make that identification, since otherwise our description of the world would be burdened with an unneces-

---

<sup>1</sup> The references to Clausius and Boltzmann in this paragraph are also taken from [11].

sary proliferation of artificially distinct concepts, in violation of Ockham’s razor, the most fundamental principle of scientific thought.

In this paper, we will primarily concern ourselves with just one small aspect of the grander theme of interpreting physics as information processing. Specifically, we focus on the idea of interpreting the physical energy content of a given system as being simply a measure of the rate at which that system is undergoing a certain ubiquitous physical process—namely, quantum state evolution—which can also be viewed as a computational process (as we do in quantum computing). In other words, the premise is that physical energy is nothing but the *rate of quantum computing*, if the meaning of this phrase is appropriately defined. This paper will clarify precisely in what sense this statement is true.

We’ll also see that the concept of physical *action*, in a certain (somewhat generalized) sense, corresponds to a computational concept of the *amount of computational work*, which we’ll also call *effort* for short.

Of course, it is not necessarily the case that a given system will have been prepared in such a way that all of its physical computational activity will actually be directly applied towards the execution of a target application algorithm of interest. In most systems, only a small fraction of the system’s energy will be engaged in application logic on computational degrees of freedom, while the rest will be devoted to auxiliary supporting purposes such as maintaining the stability of the machine’s structure, dissipating excess heat to the environment, *etc.*

For that part of energy that *is* directly engaged in carrying out desired logical operations, we will see that one fruitful application of the computational interpretation of energy will be in allowing us to characterize the minimum energy that is required in order to carry out a given computational operation in a given period of time. In section 11, we will show how to calculate this figure for a variety of simple quantum logic operations, and we briefly discuss how to generalize it to apply to classical reversible and irreversible Boolean operations as well.

## 2 Background

The earliest hints about the relationship between energy and the rate of computing can be found in Planck’s original  $E = h\nu$  relation for light, which tells us that an electromagnetic field oscillation having a frequency of  $\nu$  requires an energy at least  $h\nu$ , where  $h \simeq 6.626 \times 10^{-34} \text{Js}$  is Planck’s constant. Alternatively, a unit of energy  $E$ , when devoted to a single photonic quantum, results in an oscillation (which can be considered to be a very simple sort of computational process) occurring at a cycle rate of  $\nu = E/h$ .

Also suggestive is the Heisenberg energy-time uncertainty principle  $\Delta E \Delta t \geq h/2$ , which relates the standard deviation or uncertainty in energy  $\Delta E$  to the minimum time interval  $\Delta t$  required to measure energy with that precision; the measurement process can be considered a type of computation. However, this relation by itself only suggests that the *spread* of energy has something to do with the rate of a process of interest; whereas we are interested in finding a meaning for the absolute energy, itself.

More recently (in 1998), Margolus and Levitin [5] showed that in any quantum system, a state with a quantum-average energy  $E$  above the ground state of the system takes at least time  $\Delta t \geq \underline{t} = h/4E$  to evolve to an orthogonal state, along with a tighter bound of  $\Delta t \geq \underline{t}_N = (N - 1)h/2NE$  that is applicable to a trajectory that passes through a cycle of  $N$  mutually orthogonal states before returning to the initial state. In the limit as  $N \rightarrow \infty$ ,  $\underline{t}_N \rightarrow h/2E$ , twice the minimum time of  $\underline{t} = \underline{t}_2$  which applies to a cycle between 2 states. Both bounds are achievable in principle, in freely constructed quantum systems.

In a widely-publicized paper in *Nature* in 2000, Lloyd [6] used the Margolus-Levitin result to calculate the maximum performance of a 1 kg “ultimate laptop,” in a hypothetical scenario where all of the machine’s rest mass-energy is devoted to carrying out a desired computation.

Two years later, Levitin, Toffoli and Walton [13] investigated the minimum time to perform a specific quantum logic operation, namely a CNOT (controlled-NOT) together with an arbitrary phase rotation, in systems of a given energy  $E$ .

In 2003, Giovannetti, Lloyd and Maccone [14, 15] explored tighter limits on the time required to reduce the fidelity between initial and final states to a given level, taking into account the magnitudes of both  $E$  and  $\Delta E$ , the system’s degree of entanglement, and the number of interaction terms in the system’s Hamiltonian.

Results such as the above suggest that energy might fruitfully be *exactly* identified with the rate of raw, low-level quantum-physical “computing” that is taking place within a given physical system, in some appropriate sense, if only the quantity “amount of computing” could be defined accordingly. We would like to show that some well-defined and well-justified measure of the rate at which “computational work” is being carried out within any quantum system is indeed *exactly* equal to the energy of that system.

### 3 Preview

In subsequent sections of this paper, we address the aforementioned goal by proposing a well-defined, real-valued measure of the total *amount of change* undergone over the course of *any* continuous trajectory of a state vector along the unit sphere in Hilbert space. This measure is simply given by the line integral of the magnitude of the imaginary component of the inner product between infinitesimally adjacent normalized state vectors along the given path. This quantity is invariant under any time-independent change of basis, since the inner product itself is. It is also numerically equal to twice the complex-plane area (relative to the origin) that is circumscribed or “swept out” by the coefficients of the basis vector components, in any basis. And for closed paths, this quantity is even invariant under not only rotations but also translations of the complex plane. Finally, our quantity can be perhaps most simply characterized as being the action of the Hamiltonian; this is to be contrasted with the usual action (of the Lagrangian), whose precise computational meaning we’ll address later on.

We propose that the above-described measure of “amount of change” is the most natural measure of the amount of computational “work” performed or computational “effort” exerted by a system as it undergoes that specific trajectory.

(Note this concept of *computational work* is a completely separate usage of the word “work” from the usual usage in physics, to mean organized energy.) We will see that this measure is indeed appropriate later when we show that specific quantum and classical logic gate operations incur definite minimum worst-case costs in terms of this measure of effort.

We will show that in any quantum system, the instantaneous rate at which change occurs (computational work is done, effort is exerted) for any state, under any time-dependent Hamiltonian operator, is exactly given by the instantaneous Hamiltonian energy of the state. Thus, the energy is the rate of computation.

#### 4 A Simple Example

In this section, we start by presenting a simple concrete example in order to motivate our later, more general definitions. Consider any quantum system subject to a constant (time-independent) Hamiltonian operator  $H$ . Let  $|G\rangle$  and  $|E\rangle$  be any normalized, non-degenerate pair of the system’s energy eigenstates. (The names chosen are meant to suggest the ground and excited states of a non-degenerate two-state system, but actually it is not necessary for purposes of our example that there be no additional states of higher or lower energy.) Since the Hamiltonian is only physically defined up to an additive constant, adjust the eigenvalue that corresponds to vector  $|G\rangle$  to have value 0 (i.e. let  $H|G\rangle = 0$ ), and then let  $E$  denote the eigenvalue of  $|E\rangle$  (i.e.,  $H|E\rangle = E|E\rangle$ ). For example, for a two-state system, we could let  $H = (1 + \sigma_z)E/2$  with the usual definition of  $\sigma_z = \begin{bmatrix} 1 & 0 \\ 0 & -1 \end{bmatrix}$ ; then  $|G\rangle = \begin{bmatrix} 0 \\ 1 \end{bmatrix}$  and  $|E\rangle = \begin{bmatrix} 1 \\ 0 \end{bmatrix}$ .

Now, consider the initial state  $|\psi_0\rangle = (|G\rangle + |E\rangle)/\sqrt{2}$  at time  $t = 0$ , and let it evolve over time under the influence of the system’s Hamiltonian; letting  $|\psi(t)\rangle = e^{iHt/\hbar}|\psi_0\rangle$  denote the state vector at time  $t$ .<sup>2</sup> Let  $c_{|G\rangle}(t)$  and  $c_{|E\rangle}(t)$  denote  $\langle G|\psi(t)\rangle$  and  $\langle E|\psi(t)\rangle$  respectively, i.e., the components (complex coefficients) of the state vector  $|\psi(t)\rangle$  when decomposed in a basis that includes  $|G\rangle, |E\rangle$  as basis vectors. Initially,  $c_{|G\rangle}(t) = c_{|E\rangle}(t) = 1/\sqrt{2}$ . Over time,  $c_{|E\rangle}$  phase-rotates in the complex plane in a circle about the origin, at an angular velocity of  $\omega_{|E\rangle} = E/\hbar$ . In time  $t = 2E/\hbar$ , it rotates by a total angle of  $\theta = \pi$ . The area swept out by the line between  $c_{|E\rangle}(t)$  and the origin is  $a_{|E\rangle} = \frac{1}{2}\pi|c_{|E\rangle}|^2 = \pi/4$ . This is the area of a semi-circular disc with radius  $r_{|E\rangle} = |c_{|E\rangle}| = 1/\sqrt{2}$ . Meanwhile,  $c_{|G\rangle}(t)$  is stationary and sweeps out zero area. The total area swept out by both components is thus  $a = \pi/4$ .

Does the area swept out by the complex components of the state vector depend on the choice of basis? We will answer this question more generally later, but for now, consider, for example, a new basis that includes basis vectors  $|0\rangle, |1\rangle$  where  $|0\rangle = (|G\rangle + |E\rangle)/\sqrt{2}$  and  $|1\rangle = (|G\rangle - |E\rangle)/\sqrt{2}$ . Consider the evolution again starting from the same initial state as before,  $|\psi_0\rangle = |0\rangle$ . Note that the final

<sup>2</sup> For convenience, we use the opposite of the ordinary sign convention in the time-evolution operator.

state after time  $t = 2E/\hbar$  is  $|1\rangle$ . In the new basis, the coefficients  $c_{|0\rangle}(t)$  and  $c_{|1\rangle}(t)$  respectively trace out the upper and lower halves of a circle of radius  $1/2$  centered at the point  $1/2 + 0i$ . The total area swept out by both components (on lines between them and the origin) is the area of this circle,  $a = \pi(1/2)^2 = \pi/4$ . Note that the total area in this new basis is still  $\pi/4$ . At this point we may naturally ask, is this true in any basis? Later we will see that the answer is yes, and moreover, the area swept out is independent of the basis for *any* trajectory of *any* initial state. The area swept out will be our proposed measure of the amount of computational work performed or effort exerted by a system in undergoing any specific state-vector trajectory.

## 5 Basic Framework

In this section we proceed to set forth a general framework as a basis for the subsequent analysis. Let  $\mathcal{H}$  be any Hilbert space, and let  $H(t)$  be any continuous mapping from a real-valued parameter  $t$  (“time”) to Hermitian operators on  $\mathcal{H}$ ; in other words,  $H$  can be considered to be a (most generally) time-dependent Hamiltonian, given some implicit energy units.

We start our framework with the physical concept of action, which is, most generally, the integral over time (or along some temporal path) of a quantity having units of energy. Typical units of action include Planck’s constants  $h$  and  $\hbar$ , which, as we will see can also be construed as representing *angles* of 1 circle ( $360^\circ$ ) and 1 radian, respectively.

For any times  $t_1, t_2 \in \mathbb{R}$ , we define the *action operator of  $H$  from  $t_1$  to  $t_2$*  to be:

$$A_H(t_1, t_2) = \int_{t=t_1}^{t_2} H(t) dt \quad (1)$$

Of course, in the special case where we have a time-independent  $H(t) = H$  (const.), we can simplify the action operator to just  $A_H(t_1, t_2) = A_H(\Delta t) = H\Delta t$  where  $\Delta t = t_2 - t_1$ .

Note that, although the action quantity that is most frequently used in physics (e.g., in Hamilton’s principle) is the action of the *Lagrangian*  $L = pv - H$ , it is also perfectly valid and reasonable for us to define the more general notion of the action “of” any quantity that has units of energy, by integrating that energy quantity over time as in eq. (1). In this case, we are referring to the action of the *Hamiltonian*, rather than the usual action of the Lagrangian.

Let us also define the *unitary transform from  $t_1$  to  $t_2$  under  $H$*  to be

$$U_H(t_1, t_2) = e^{iA_H(t_1, t_2)} \quad (2)$$

This is just the usual quantum time-evolution operator which transforms state vectors from time  $t_1$  to  $t_2$  under a given time-dependent Hamiltonian  $H(t)$ , given time and energy units chosen such that  $\hbar = 1$ .<sup>3</sup> Often, by convention a minus sign is

<sup>3</sup> Technically, in order for eq. (2) to equal the true time-evolution operator, we must also require that  $H(t)$  commute with its time-derivative  $\dot{H}(t)$ . However, this caveat ends up not affecting our later results.

inserted inside the exponential, but this is a purely arbitrary choice and we avoid it in this document. Henceforth, we will almost always omit the  $H$  subscript from  $U$  and  $A$ , although these operators should still be understood, in the context of the present discussion, to be always implicitly dependent on  $H$ .

If we expand the expression (2) for  $U$  as a Taylor series, we note that (suppressing the  $t_1, t_2$  parameters for clarity)

$$\begin{aligned}
 U &= e^{iA} \\
 &= \sum_{n=0}^{\infty} \frac{(iA)^n}{n!} \\
 &= 1 + iA - \frac{A^2}{2} - \frac{iA^3}{6} + \dots \\
 &= 1 + iA + O(A^2)
 \end{aligned} \tag{3}$$

where the  $O(A^2)$  notation here is expressing the fact that if we were to scale to ever *smaller*  $A$ , *e.g.*, in considering the parameterized family of action operators  $A(k) = A_H(t_1, t_1 + (t_2 - t_1)/k)$  as  $k \rightarrow \infty$ , the sum of the  $A^2$ ,  $A^3$ , *etc.* terms would become asymptotically bounded in magnitude by a term that scales as  $A^2$ , and that thus would be negligible in comparison with  $A$ . In other words, as  $k \rightarrow \infty$ ,

$$U(k) \rightarrow 1 + iA(k). \tag{4}$$

Assuming that  $H(t)$  is a continuous function of  $t$ , it follows that for any infinitesimal time interval of magnitude  $\Delta t = dt$ , we can consider  $H(t)$  to be effectively time-independent over the entire infinitesimal interval  $[t_1, t_2 = t_1 + dt]$ , and so we can say that at any time  $t$ , the “infinitesimal” (here meaning, close to 1) unitary transform  $U'(t)$  applying “at” that time  $t$  can be expressed as

$$\begin{aligned}
 U'(t) &= U(t, t + dt) \\
 &= 1 + iA(t, t + dt) \\
 &= 1 + iA_{H(t)}(dt) \\
 &= 1 + iH(t)dt
 \end{aligned} \tag{5}$$

where  $A_{H(t)}(dt)$  represents the action operator with the “constant” Hamiltonian  $H = H(t)$  applied over an infinitesimal time interval of size  $dt$ , and the equality here being both rigorous and exact.

This simple (and well-known) relationship between  $U$  and  $H$  over infinitesimal time intervals suggests that important characteristics of  $U$  over arbitrarily large intervals can usefully be defined by integrating properties of the infinitesimal unitary  $U'$  over time between  $t_1$  and  $t_2$ , or in other words, by integrating properties of instantaneous  $H(t)$ . Indeed, we will see that this is indeed the case for the property we are interested in, namely the “minimum worst-case effort” of a given unitary, which we can regard as a measure of its computational complexity. Furthermore, we will see that the presence of the imaginary unit  $i$  in eq. (5) ends up playing an important role, and leads us to consider the imaginary part of the inner product in our definition of the effort of an arbitrary trajectory.

In what follows, we will refer to the entire function  $U'(t)$  mapping values of  $t$  in  $[t_1, t_2]$  to infinitesimal unitaries as the *transformation trajectory* of the system between those times. Note that the overall transformation  $U(t_1, t_2)$  can be expressed as the product of all the infinitesimal  $U'(t)$  over the continuum of times  $t$  in the range from  $t_1$  to  $t_2$ . That is, we can write

$$U(t_1, t_2) = \prod_{t=t_1}^{t_2} U'(t). \quad (6)$$

Even though the product operator  $\prod$  is traditionally applied only over discrete countable sets of terms, there is no reason that it can't also be applied to an uncountable set of values that are each infinitesimally close to 1, analogously to how an integral  $\int$  can be viewed as simply a generalization of the sum operator  $\sum$  to a continuous set of terms that are each infinitesimally close to 0.

Note that although the transformation trajectory  $U'(t)$  completely determines  $U(t_1, t_2)$ , the converse is not true: Knowing the total transformation  $U(t_1, t_2)$  for a particular pair of times  $t_1, t_2$  is not sufficient to determine the detailed transformation trajectory  $U'(t)$  even for values of  $t$  falling in the range  $[t_1, t_2]$ , since many possible action operators can exponentiate to the same unitary, and many time-dependent Hamiltonians could integrate to the same action operator.

## 6 Defining Computational Effort

With the above general observations aside, let us now proceed to define our concept of the amount of computational effort performed by a given transformation trajectory  $U'(t)$  between two times, as well as the effort represented by a resulting overall unitary transform  $U$ . We will find it easiest to analyze this by first considering  $U$ 's behavior when operating on its eigenvectors.

Let us first pause and look back at equation (3), the Taylor-expansion of the definition of  $U$  as  $e^{iA}$ , and reflect on it for a moment. We note that this equation immediately implies that all eigenvectors of  $A$  are eigenvectors of  $U$  as well. Why? Let  $Av = av$  (with  $v$  an eigenvector, and  $a$  its eigenvalue). Then, spelling out the steps explicitly,

$$\begin{aligned} Uv &= e^{iA}v \\ &= \left[ \sum_{n=0}^{\infty} \frac{(iA)^n}{n!} \right] \\ &= \sum_{n=0}^{\infty} \frac{i^n A^n v}{n!} \\ &= \sum_{n=0}^{\infty} \frac{i^n a^n v}{n!} \\ &= \left[ \sum_{n=0}^{\infty} \frac{(ia)^n}{n!} \right] v \\ &= e^{ia}v = uv \end{aligned} \quad (7)$$

where  $u$  is  $v$ 's scalar eigenvalue under  $U$ , given by  $u = \sum_{n=0}^{\infty} (ia)^n/n! = e^{ia}$ . Since  $Uv$  is equal to a scalar ( $u$ ) times  $v$ , by definition  $v$  is an eigenvector of  $U$ . Now, since  $U$  and  $A$  are of equal dimensionality, and all eigenvectors of  $A$  are eigenvectors of  $U$ , the converse also holds, and the two operators have identical sets of eigenvectors. Since  $U$  is unitary, it preserves vector length, and so its eigenvectors  $v$  remain unchanged under  $U$  except for a phase rotation, namely a multiplication by  $u = e^{ia}$ , where  $a$  is the eigenvalue of  $A$  corresponding to  $v$ . Note that  $A$  must have real eigenvalues, since it is an integral of  $H$  (which has real eigenvalues since it is Hermitian); also, since we know that  $|u| = 1$  and that  $u = e^{ia}$ , it follows that  $a$  must be real. Thus we can see that the eigenvalues of  $A$  give the angles of phase rotation for the eigenstates of the time evolution unitary. In other words, whenever the action operator is applied to an initial state vector that is unchanged by  $U(t_1, t_2)$  aside from a phase rotation, it simply expands or contracts the length of this vector by a factor that is numerically equal (modulo  $360^\circ$ ) to the angle (in radians) by which those vectors would be phase-rotated if  $U$  were applied to them.

Now, we would like to understand and quantify what happens to other vectors as well when a given transformation trajectory is applied to them. We will see how to do this shortly. First, we will begin by analyzing in a bit more detail what happens to a given eigenvector over time as it is transformed by a given trajectory  $U'(v)$ .

Given any initial vector  $v$  (at time  $t_1$  which without loss of generality we can set equal to 0), we can let  $v(t) = U(t_1, t)v$ . In other words,  $v(t)$  traces out some continuous path on an origin-centered sphere in Hilbert space having some fixed radius  $|v|$  which WLOG we can consider to be 1 (the standard normalization condition).

For simplicity, let us first suppose that  $H$  is time-independent (later, we will see how to remove this restriction). Then  $A(\Delta t) = H\Delta t$  for non-infinitesimal intervals  $\Delta t$ , and  $U(\Delta t) = e^{iH\Delta t}$ , so that for times  $t = t_1 + \Delta t = \Delta t$ , we have  $v(t) = U(\Delta t)v = e^{iHt}v$ . If  $v$  is an eigenvector of  $U$  (thus of  $A$ , and of the time-independent  $H$ ), let its eigenvalue under  $H$  be called  $\omega$ . Then in fact  $v(t) = e^{i\omega t}v$ . In other words,  $v(t)$  simply phase-rotates continuously in the complex plane at a constant angular velocity  $\omega$  (in radians per unit time). Note that the inner product between the initial  $v$  and  $v(t)$ , which we can write  $\langle v|v(t)\rangle$ , has the value  $e^{i\omega t} = \cos(\omega t) + i\sin(\omega t)$ . The imaginary part of the inner product is just  $\sin(\omega t)$ . Note now that for an infinitesimal  $t = dt$ , we have that  $\sin(\omega dt) = \omega dt = da$ , i.e., the infinitesimal increment in angle (or action) accumulated over the time  $dt$ . In other words, over infinitesimal time intervals  $dt$ , the imaginary part of the inner product between the “before” vector  $v(t_1)$  and the “after” vector  $v(t_1 + dt)$  gives exactly the amount of action (in  $\hbar$  units) or phase angle accumulation (in radians) over that time. At least, we have shown that this is the case given a time-independent Hamiltonian  $H$ , and an initial vector  $v$  which is an eigenvector of that Hamiltonian. Let us now see how to generalize this to other cases.

First, suppose that the initial vector  $v$  is not an eigenvector of  $H$ . However, let  $v_i$  be a maximal indexed set of unit-length mutually orthogonal eigenvectors of  $H$ , or in other words, an orthonormal eigenbasis of  $H$ . Then, any arbitrary  $v$  can be

expressed in terms of components in the  $v_i$  basis, that is as  $v = \sum_i c_i v_i$  where the  $c_i$  are complex coefficients.

Of course, since  $U$  is a linear operator, we can express  $Uv$  in terms of its effect on  $v$ 's components in the given basis, *i.e.*,

$$\begin{aligned} v(t) &= U(t)v \\ &= U(t) \sum_i c_i v_i \\ &= \sum_i c_i U(t)v_i \\ &= \sum_i c_i e^{i\omega_i t} v_i \end{aligned} \tag{8}$$

where  $\omega_i$  is just the eigenvalue of  $H$  that is associated with eigenvector  $v_i$ . Now, note that the exponential terms can be absorbed into the coefficients. That is, we can look at the coefficients as being time-dependent quantities,  $c_i(t) = c_i e^{i\omega_i t}$ , and say that always  $v(t) = \sum_i c_i(t) v_i$ . Note that each coefficient, whatever its magnitude, still just phase-rotates in the complex plane with the same angular velocity  $\omega_i$  that is given by the corresponding eigenvalue of  $H$ .

At this point, let us pause to preview the next steps. We are going to study several quantities, and demonstrate the close identities between them:

1. The average rate of phase angle accumulation of the coefficients  $c_i(t)$ , weighted by their squared modulus (magnitude).
2. The quantum average energy of the given vector  $v$  considered as a pure quantum state.
3. The total rate at which the coefficients  $c_i(t)$  sweep out area in the complex plane in the counter-clockwise ( $e^i$ ) direction, relative to the origin.
4. The imaginary component of the inner product between infinitesimally-adjacent state vectors along the trajectory, per infinitesimal time interval.
5. The rate at which the coefficients  $c_j(t)$  in *any* orthonormal basis  $v_j$  sweep out area in the complex plane.

First, let us describe each coefficient  $c_i$  in phase-magnitude representation as  $c_i = m_i e^{i\theta_i}$ , where  $m_i = |c_i| = \sqrt{c_i^* c_i}$  is the modulus (absolute value, magnitude, norm, length) of the complex number  $c_i$ , and  $\theta_i = \arg(c_i)$  is its argument (phase angle). Another notation for this relation is  $c_i = m_i \angle \theta_i$ . Probably the most popular notation in use today is  $c_i = m_i e^{i\theta_i}$ , although the notation  $e^x$  here must not be confused with ordinary complex exponentiation, which is, strictly speaking, multi-valued in the case of non-integer exponents. (*E.g.*, the expression  $1^{1/3}$  technically has 3 distinct complex values, namely  $1$ ,  $\exp[2\pi i/3]$ , and  $\exp[4\pi i/3]$ .)

Let us now consider the following quantity:

$$\bar{\omega} = \sum_i m_i^2 \omega_i \tag{9}$$

Recall that  $\omega_i$  is the eigenvalue of  $H$  corresponding to eigenvector  $v_i$ , and is the rate of phase rotation (or angular velocity) of the coefficient  $c_i$  in the complex

plane. So,  $\bar{\omega}$  is simply the average angular velocity of the coefficients, weighted by their squared moduli  $m_i^2$ . Weighting by the squared moduli of the amplitudes (complex coefficients) of the basis states is the normal procedure for taking the average or mean value of an observable quantity in quantum mechanics, given a pure state that is a complex superposition of the eigenstates of the given observable. Thus, we can say that  $\bar{\omega}$  is simply the average complex-plane angular velocity for the quantum state  $v$ .

We pause here to note that aside from a conversion of units,  $\bar{\omega}$  is also the *energy* of the quantum state  $v$ . For example, if  $\bar{\omega}$  has been implicitly quantified in terms of radians per second, then we can write  $\bar{E} = \bar{\omega}\hbar$ , using some standard physical unit for  $\hbar$  such as Joule-seconds, to obtain the average energy  $\bar{E}$  in a traditional energy unit such as Joules. The constant  $\hbar$  can be considered to represent the angle “1 radian,” and thus serves to make this implicit angle-unit explicit. However, we emphasize that all this is merely a matter of unit-conversion, so that we are justified in saying that  $\bar{\omega}$  is the energy of the state.

As a brief aside, if we are dealing with a quantum mixed state described by a density operator  $\rho$ , we can calculate its energy by diagonalizing it to form a statistical ensemble of orthogonal pure states, and computing the statistical average energy over that ensemble.

Let us now consider the rate at which the complex coefficients sweep out area in the complex plane. To illustrate what we mean by this, refer to figure 1, which illustrates a region of the complex plane centered on the origin. Consider first just one of the coefficients  $c_i$ . At time  $t$ , it has value  $c_i(t)$ , shown as an arrow on the diagram. A short time  $dt$  later, the arrow has rotated to  $c_i(t + dt)$ , and we say that the arrow has “swept out” the region shown in gray in the figure. During this interval, the arrow has rotated by an angle  $d\theta_i = \omega_i dt$ . What is the area of the wedge-shaped region of the disc which was swept out? This is easy to calculate, if we recall that, were we to let the arrow sweep out a full circle, it would rotate by a total angle of  $\theta_i = 2\pi$  radians, while sweeping out an area of  $a_i = \pi m_i^2$ , since  $m_i$  (the magnitude of  $c_i$ ) is the radius of the circle traversed. Thus, for the full disc, we would have  $a_i = \theta_i m_i^2 / 2$ . By symmetry considerations, this same relation between  $a$  and  $\theta$  must hold for each wedge-shaped piece of the disc as well, so we have  $da_i = d\theta_i m_i^2 / 2 = \omega_i m_i^2 dt / 2$ .

Now, to find the *total* area  $da$  swept out by *all* the coefficients  $c_i$  over time  $dt$ , we merely do the same for each of them, and sum them all up:

$$\begin{aligned} da &= \frac{1}{2} \sum_i \omega_i m_i^2 dt \\ &= \frac{1}{2} \bar{\omega} dt \end{aligned} \quad (10)$$

Thus, the total rate  $da/dt$  or  $\dot{a}$  at which area is swept out in the complex plane by all the various coefficients taken together is exactly half of the weighted-average component’s phase velocity, *i.e.*, half the state’s energy  $\bar{\omega} = \bar{E}$ .

This brings us to the fourth item in the preview above, namely the inner product between infinitesimally-adjacent state vectors  $v(t)$  and  $v(t + dt)$ . For conciseness, we will let  $v = v(t)$  and  $v' = v(t + dt)$  and likewise for the coefficients  $c_i$  and

phase angles  $\theta_i$ . The inner product  $v \bullet v' = \langle v | v' \rangle = v^\dagger v'$  (these are three common notations for it) can be defined in terms of the coefficients  $c_i, c'_i$  by:

$$v \bullet v' = \sum_i c_i^* c'_i \quad (11)$$

where the  $*$  denotes complex conjugation of  $c'_i$ . Now, in the phase-magnitude representation,  $c_i^* = (m_i e^{i\theta_i})^* = m_i e^{-i\theta_i}$ . Note that  $m'_i = m_i$  because the complex magnitudes are not changed by phase rotation. Thus,

$$c_i^* c'_i = (m_i e^{-i\theta_i})(m_i e^{i\theta'_i}) = m_i^2 e^{i(\theta'_i - \theta_i)}. \quad (12)$$

But, note that  $\theta'_i = \theta_i + \omega_i dt$ , so we have

$$\begin{aligned} c_i^* c'_i &= m_i^2 e^{\omega_i dt} \\ &= m_i^2 [\cos(\omega_i dt) + i \sin(\omega_i dt)] \\ &= m_i^2 (1 + i\omega_i dt) \end{aligned} \quad (13)$$

where in the last step we are using the identities  $\cos(d\theta) = 1$  and  $\sin(d\theta) = d\theta$  which hold for infinitesimal angles  $d\theta$ , where in our case  $d\theta = \omega dt$ . Now, we just sum equation (13) over the values of the index  $i$  to get the overall inner product. The real part of the inner product is just  $\sum m_i^2 = 1$  always, so it is not very useful, but the imaginary part of the inner product is  $\Im[v \bullet v'] = \sum m_i^2 \omega_i dt = \bar{\omega} dt$ , in other words, it is the average energy times the time increment  $dt$ . Recall that  $\bar{\omega}$  is the average phase velocity or average Hamiltonian energy of the state  $v$ , thus  $dA = \bar{\omega} dt$  is the average increment in phase, or the increment in action over the time  $dt$ . Note that we have  $dA = 2da$ , where recall  $da$  was the increment in area swept out in the complex plane. (The reason why the increment in angle is always double the area increment can be traced back to the fact that it takes an angle of  $2\pi$  radians to sweep out a unit circle having an area of  $\pi$ .)

Of course, in our time-independent scenario, even for a non-infinitesimal time interval  $\Delta t$ , we can obtain the total average accumulation of phase angle  $\Delta A$ , or the total area  $\Delta a$  swept out, by just using the expressions  $\Delta A = \bar{\omega} \Delta t$  and  $\Delta a = \Delta A / 2$ .

As an interesting aside, for any closed trajectory that eventually brings all coefficients back to their initial complex-plane locations simultaneously, it does not even matter where we choose to locate the complex origin for purposes of calculating the area, relative to the geometric curves traced out in the plane by the coefficients. The total area swept out by the points as they travel around the curves remains exactly the same no matter where the ‘‘center’’ for area calculation purposes is chosen. Or more precisely, this is true as long as any retrograde (clockwise) motions are considered to sweep out negative area.

## 7 Generalizing to Arbitrary Bases

The above discussion proceeded under the context of a set of basis vectors  $v_i$  which were taken to be orthonormal eigenvectors of the (temporarily presumed constant)

Hamiltonian operator  $H$ . Now, we will see that this particular choice of basis is in fact unnecessary, and that the same statements concerning the relationship between the area swept out and the action would hold true in any fixed (time-independent) basis.

That this is true is suggested by considering the relationship between  $dA$  (the increment of action, the state energy  $\bar{\omega}$  times  $dt$ ) and the inner product  $v \bullet v' = v(t) \bullet v(t + dt)$  between infinitesimally neighboring vectors along the trajectory. We saw that  $dA = \Im[v \bullet v']$ . However, a fundamental property of the inner product is that it is itself a unitary invariant; that is, it is a product of two complex vectors considered as pure *geometric* objects, and thus it is independent of the particular basis which we use to express those vectors in terms of components. Therefore, this basis-independence also holds for the imaginary part of the inner product. So, if we were to just define  $dA = \Im[v \bullet v']$ , this definition would rely not at all on any particular basis; we do not even have to find the eigenstates of the Hamiltonian in order to determine it. Yet, it is still true that  $dA/dt$  is the energy of the state  $v$ .

Now, however, we would like to see whether the other quantities we investigated that explicitly invoke a choice of basis nevertheless remain the same under a change of basis. In particular, we saw that in the energy basis  $v_i$ , the total area swept out by all the coefficients  $c_i$  in the complex plane was exactly given by half of the action  $A$ , that is,  $a = A/2$ . Does this relation still hold in other bases? We will see that it does.

At first, it may seem non-obvious that the area swept out is still half of the action. Note that our previous arguments for this relied on the fact that in the energy basis  $v_i$ , the coefficients all rotated at uniform angular velocity in a circle in the complex plane, while their individual magnitudes remained constant. In a different basis  $v_j$ , this will no longer be true. Each basis vector  $v_j$  in the new basis is in general some superposition of the  $v_i$ , like

$$v_j = \sum_i u_j^i v_i, \quad (14)$$

where the matrix  $\mathbf{U} = [u_j^i]$  of complex coefficients (with the subscript  $j$  indexing rows, and the superscript  $i$  indexing columns) is, most generally, any unitary matrix. We can also write this equation in matrix-vector form as  $\vec{v}_j = \mathbf{U} \vec{v}_i$ , where the over-arrow here denotes that we are referring to the entire column-ordered sequence of basis vectors,  $\vec{v}_i = \begin{bmatrix} v_1 \\ \vdots \end{bmatrix}$ . Now, a general state vector  $v$  can equally well be expressed as a linear superposition of either set of basis vectors, that is,

$$v = \sum_i c_i v_i \quad (15)$$

$$= \sum_j c_j v_j. \quad (16)$$

But now, we can substitute eq. (14) into eq. (16) and rearrange, as follows:

$$v = \sum_j c_j v_j$$

$$\begin{aligned}
&= \sum_j c_j \sum_i u_j^i v_i \\
&= \sum_{ij} c_j u_j^i v_i \\
&= \sum_i \left( \sum_j c_j u_j^i \right) v_i.
\end{aligned} \tag{17}$$

Now, since the  $v_i$  are linearly independent, the expansion of  $v$  in terms of them must be unique, so we can equate the coefficients on  $v_i$  in equations (15) and (17) to get

$$\begin{aligned}
c_i &= \sum_j u_j^i c_j \\
\vec{c}_i &= \mathbf{U}^T \vec{c}_j,
\end{aligned} \tag{18}$$

where T is matrix transpose. We can easily solve this equation for the  $c_j$  coefficients as follows:

$$\begin{aligned}
\vec{c}_i &= \mathbf{U}^T \vec{c}_j \\
(\mathbf{U}^T)^{-1} \vec{c}_i &= \vec{c}_j \\
(\mathbf{U}^T)^{T*} \vec{c}_i &= \vec{c}_j \\
\mathbf{U}^* \vec{c}_i &= \vec{c}_j \\
c_j &= \sum_i (u_j^i)^* c_i.
\end{aligned} \tag{19}$$

In other words, each complex coefficient in the new basis is just a particular linear combination of what the various complex coefficients were in the old basis. If the coefficients  $c_i$  in the old energy basis are describing perfect circles around the complex origin at a variety of radii and angular velocities, there is no guarantee that the coefficients  $c_j$  in the new basis will still be describing circular paths centered on the origin, although their paths will of course still be continuous. In general, the  $c_j$  will follow complex looping trajectories in the complex plane, generated exactly as if by Ptolemaic planetary epicycles, *i.e.*, as a sum of circularly rotating vectors. A given  $c_j$  will in general return to its initial location in the complex plane only when its components  $c_i$  that have nonzero values of  $u_j^i$  all simultaneously return to their initial locations exactly, which might even take infinitely long, if the corresponding  $\omega_i$  values were relatively irrational.

Anyhow, the important point for our present purposes is that the  $c_j$ s do not, in general, maintain a constant magnitude (distance from the origin), and so the area swept out by the  $c_j$  over a given time is no longer just a section of a circle, which was very easy to analyze. Instead, while  $c_j$ 's phase angle  $\theta_j$  is rotating, simultaneously its magnitude  $m_j$  may also be growing or shrinking. Figure 2 illustrates the situation.

What, now, is the area swept out in this more general situation? First, notice that in the infinitesimal limit, it is exactly half of the area of the parallelogram that

is spanned on two adjacent sides by  $c_j = c_j(t)$  and  $c'_j = c_j(t + dt)$ , considered as vectors in the complex plane. See figure 3.

The parallelogram area, itself, is  $dA_j = m_j m'_j \sin(d\theta_j)$ , where  $m_j$  and  $m'_j$  are the magnitudes of the old and new coefficients, respectively, and  $d\theta_j$  is the increment of phase angle. However, note that the area  $dA_j$  of this parallelogram is also the signed magnitude of the scalar “cross product”  $c_j \times c'_j$  between the coefficients, considered as two-dimensional vectors. (The traditional cross product, defined in three dimensions, would be a vector perpendicular to the complex plane having this value  $dA_j$  as its length.) There is a beautiful identity [16] connecting the cross product and dot product with the conjugate multiplication of complex numbers, namely:

$$a^* b = a \cdot b + i(a \times b), \quad (20)$$

where  $a^*$  means the complex conjugate of  $a$ , and  $a \cdot b$  denotes the real “dot product” between  $a$  and  $b$  considered as vectors, namely  $|a||b| \cos[\arg(b) - \arg(a)]$ , and  $a \times b$  denotes the real “cross product” previously mentioned, namely  $|a||b| \sin[\arg(b) - \arg(a)]$ . The validity of this relation can be shown easily:

$$\begin{aligned} a^* b &= (|a|e^{-i \arg(a)})(|b|e^{i \arg(b)}) \\ &= |a||b|e^{i[\arg(b) - \arg(a)]} \\ &= (|a||b| \cos \theta) + i(|a||b| \sin \theta) \\ &= a \cdot b + i(a \times b) \end{aligned} \quad (21)$$

where in the third line  $\theta = \arg(b) - \arg(a)$ . Applying this identity to our situation, we can see that the area swept out, since it is half the cross product, is half of the imaginary part of the conjugate product  $c_j^* c'_j$  between old and new coefficients, or, in symbols,

$$da_j = dA_j/2 = \Im[c_j^* c'_j]/2. \quad (22)$$

Now, this is just the area swept out by a single component  $c_j$ . To find the total area  $da$  swept out by all components, we merely sum over components:

$$\begin{aligned} da &= \sum_j \Im[c_j^* c'_j]/2 \\ &= \frac{1}{2} \Im \left[ \sum_j c_j^* c'_j \right] \\ &= \frac{1}{2} \Im[v \bullet v'] \\ &= \frac{1}{2} dA. \end{aligned} \quad (23)$$

In other words, *just like in the energy basis*, in an arbitrary basis it is still true that the infinitesimal increment  $da$  in the area swept out by the coefficients is exactly one-half of  $dA$ , the imaginary component of the inner product between infinitesimally adjacent vectors along the trajectory. We saw earlier that  $dA$  was exactly the action of the Hamiltonian over the time increment  $dt$ . Integrating over

time, we see how that the total area  $a$  swept out by the coefficients in any basis is exactly  $A/2$ , where  $A$  is indeed exactly the action of the Hamiltonian, *i.e.*, the quantum average value of the observable operator  $A = H\Delta t$  when applied to the initial state vector  $v$ .

## 8 Generalizing to Time-dependent Hamiltonians

In the above, we established that  $2da = dA = \Im[v \bullet v'] = Hdt$  for infinitesimal changes of the state vector  $v \rightarrow v'$  along its trajectory over infinitesimal time intervals  $dt$  under any *constant* Hamiltonian. But, as long as the Hamiltonian only changes in continuous fashion, it can always be considered essentially “constant” throughout any infinitesimal interval  $dt$ , even if it is varying over non-infinitesimal timescales. Therefore, the above identities still hold true even for a time-dependent Hamiltonian  $H(t)$ , which is what we originally started out our discussion with. Thus, when we integrate over time, it remains true that:

$$\begin{aligned} 2a = A &= \int_{t=t_1}^{t_2} \Im[v(t) \bullet v(t+dt)] \\ &= \int_{t=t_1}^{t_2} \bar{\omega}(t)dt = \int_{t=t_1}^{t_2} H(t)dt. \end{aligned} \quad (24)$$

In words, this says that for any initial state  $v$ , we have that  $2a$  (twice the complex-plane area swept out by the coefficients of  $v$ , in any basis) is equal to  $A = \bar{A}$ , the average action of the Hamiltonian (the average eigenvalue  $\langle v|A|v \rangle$  of the operator  $A(t_1, t_2)$  applied to the initial state  $v$ ), which is equal to the integral along the trajectory  $v(t)$  of the imaginary component of the dot product between neighboring vectors along the trajectory, and to the integral of the average phase velocity of the coefficients, weighted by the instantaneous eigenstate probability  $[m_i(t)]^2$ , and to the integral of the instantaneous Hamiltonian energy  $H(t) = \bar{H}(t)$  (the average eigenvalue  $\langle v(t)|H(t)|v(t) \rangle$  of the operator  $H(t)$  applied to the instantaneous state  $v(t)$ ) over time.

We might even consider the quantity  $A$  above to be a reasonable definition of the geometric *length* of the path that the normalized state vector describes as it drifts along the unit sphere in Hilbert space, except that it could be negative if  $\langle H \rangle$  (the instantaneous average value of  $H$ ) was sometimes negative. However, it is usually possible to normalize  $H$  in such a way that all of its eigenvalues are non-negative, except when it has an infinite spectrum of negative-energy eigenstates.

Anyway, the fact that this measure of “amount of change” which we have explored above is so stable with respect to changes of basis, that there are multiple simple ways of defining it, and that it connects so strongly with fundamental physical concepts such as action and energy, as well as with primitive geometric concepts such as angles and areas, all of these facts motivate us to propose this measure as being the most natural and genuine measure of the “amount of change” that is undergone by a physical quantum state vector  $v$  as it changes dynamically under a (possibly varying) physical influence  $H(t)$ .

Insofar as we can consider all dynamical evolution and change to be an example of “computation,” where this word is construed in a general sense, we can also accept this measure as being an appropriate measure of the *amount of computational work performed* or *amount of computational effort exerted* by the system as it undergoes the given trajectory. So as not to elicit confusion with usual use of the word “work” in mechanics, and the usual use of the word “action” to mean the action of the Lagrangian, we will refer to our quantity as simply the *effort* when we wish to be concise, and abbreviate it with the symbol  $F$ . That is,

$$F [v(t)|_{t=t_1}^{t_2}] \equiv \int_{t=t_1}^{t_2} \Im[v \bullet v'] \quad (25)$$

is a real-valued functional of a state vector trajectory  $v(t)$  taken between two times  $t_1$  and  $t_2$ . Note that the value of  $F$  depends only on the shape of the path. It is independent of the absolute time, the speed at which the trajectory is traversed, and on various other details of the Hamiltonian that generates the trajectory (such as its eigenvalues for eigenstates that are not components of  $v$ ); in general, many different Hamiltonian evolutions can generate the same path, which will always have the same total effort. So, in the above equation, we can consider  $v(t)$  to just be a parameterized curve where  $t$  is now just any *arbitrary* real-valued parameter (not necessarily corresponding to physical time). In other words, interestingly enough, the *effort* quantity does not depend on the precise system of coordinates that is used for measuring the passage of time, but rather only on a pure geometric object, namely the path taken through Hilbert space.

Note that to say that the path length corresponds to computational *effort* is not to imply that all of the physical computation that is occurring in the given system is necessarily being harnessed and applied by humans to meet our calculational needs, only that this is the total amount of raw computational work that is occurring “in nature.” The word effort connotes that effort may be wasted, *i.e.*, not used for anything useful.

The primary caveat to the above conception of computational effort seems to be that the quantity  $F$  (together with the rate of eigenstate phase rotation, and the path length in Hilbert space) is dependent on where we choose to draw our zero of energy. As is well known, energies are only well defined up to an additive constant, and so the total Hamiltonian action or effort is only well defined up to this constant multiplied by the elapsed time  $dt$ .

A natural and widely-used convention is to define the least eigenvalue of the Hamiltonian (the “ground state” energy) to be the zero of energy. In a similar fashion, we can choose to additively shift the Hamiltonian so that the least eigenvalue of the action operator that is obtained by integrating the Hamiltonian is taken to represent zero effort. (Note this approach can even be used when the Hamiltonian itself is time-dependent.)

However, this choice is by no means mandated mathematically, and in fact, in certain pathological cases (such as a time-dependent Hamiltonian with infinitely decreasing eigenvalues, or an infinite-dimensional Hamiltonian with unboundedly negative eigenvalues), there might not even be *any* minimum eigenvalue for the resulting action operator over a given interval. One needs to keep these caveats in

the back of one's mind, although they seemingly end up not very much affecting the potential practical applications of this concept, which we will address in a later section.

Another reason that we might not want to consider the ground state energy to always be zero is if the ground state energy varies, especially if it includes energy that had to be explicitly transferred into the system from some other external subsystem. Thus, energy that is present in system A, even if A is in its ground state, may still represent energy that was transferred from elsewhere and isn't being used for other purposes; *i.e.*, it represents "wasted" computational effort, and we may wish to count it as such, rather than just counting it as zero effort.

Another possible convention would be to count a system's energy as being its total (gravitating) mass-energy, or rest mass-energy, if we want it to be independent of the observer's velocity. One might think this choice is a somewhat less arbitrary than the ground state convention, since mass is a physical observable, but unfortunately, in general relativity, the contribution to the total mass-energy of a local system that is due to its gravitational self-energy isn't actually independent of the coordinate system that is used ([17], p. 62). However, this caveat is usually only important in systems such as neutron stars and black holes, where the gravitational self-energy contributes significantly to the system's total mass.

In any case, for now, we propose to just make a "gentlepersons' agreement" that we will always make sure that the energy eigenvalues of the systems that we consider are always shifted so as to be positive, so that the total effort is always positive, and we don't have to worry about what would be the meaning of a negative "amount of computational work." Unfortunately, this strategy rules out considering certain classes of systems, such as bottomless potential wells, or the infinite Dirac sea of negative-energy fermion states. But resolving this issue will have to wait for future work.

## 9 More Abstract Scenarios

In the above, we have specified a well-defined (at least, up to an additive constant) positive, real-valued measure  $F$  of the amount of computational effort represented by any trajectory of a state vector in Hilbert space.

This raises the question of whether we can assign a measure of computational effort to other physical situations that may be less completely specified. For example, we might not know the exact state trajectory; *e.g.*, although we might know a system's complete Hamiltonian  $H(t)$  and thus its action operator  $A(t_1, t_2)$  for any pairs of times  $(t_1, t_2)$ , we may have specified only a set  $V$  of possible initial states (rather than a single definite state), or we may have a probability distribution or density function  $p : V \rightarrow [0, 1]$  over initial states. In this situation, can we still meaningfully define the amount of computational effort exerted by the system as it undergoes the evolution specified by its Hamiltonian over a given time interval?

Of course we can. Given any particular initial state  $v$  at time  $t_1$ , the Hamiltonian  $H(t)$  determines an entire state trajectory  $v(t)|_{t=t_1}^{t_2}$ , and thus a unique value of  $F_H(v) = F[v(t)]$ ; we thus have a function from initial states  $v$  to the effort they

would exert under the Hamiltonian  $H(t)$  over the interval  $[t_1, t_2]$ . We can therefore always compute the average or expected effort

$$\hat{F} = \text{Ex}[F] = \sum_{v \in V} p(v)F(v) = \langle A \rangle = \text{Tr}(\rho A), \quad (26)$$

where the density operator  $\rho$  describing the initial mixed state is constructed from the probability distribution over pure states  $v$  in the usual fashion, that is,  $\rho = \sum_{v \in V} p(v)vv^\dagger$ . If no probability distribution  $p$  has been provided, we can use a uniform distribution over some natural measure on the set  $V$ .

This then gives us a workable definition of the mean effort exerted by a system over time under a given Hamiltonian, even when the initial state is not exactly known.

In some situations, we might also be particularly interested in the *maximum* effort over the set of possible initial states. For example, suppose we are preparing the initial state of the system, and we want to initialize the system in such a way that it will exert the maximum effort possible. Maximizing over  $V$ , we define the maximum effort  $F_{H,V}^+ \equiv \max_{v \in V} F_H(v)$ . This can be considered to be a measure  $F^+(A)$  of the *potential* computational “strength” of the given action operator  $A$ , expressing that the system’s Hamiltonian  $H(t)$  is a dynamics that *could* exert a given amount of computational effort over the specified interval, given a suitable initial state. Insofar as the actual state that we end up getting *might* be the one that invokes the maximal amount of work, we can say that a system with an unknown or unspecified state is, at least, performing this much “potential” computational work.

Even if the actual state turns out *not* to be the maximal-action one, the system could still be thought of as having “done the work” of determining that the actual state is *not* the one that should have transitioned through the given maximum Hilbert-space distance. (This particular thought should really be credited to Seth Lloyd, who pointed out to me in personal discussions, as an analogy, that an ordinary Boolean gate operation can still be thought of as doing computational work even if the output bit that it is applied to is not actually changed; namely, it is doing the work of determining *that* the bit should not change.)

Similarly to how we defined the maximum effort, we can define the minimum effort over  $V$  as  $F_{H,V}^- \equiv \min_{v \in V} F_H(v)$ , although we should keep in mind that if the ground state of the action operator  $A$  is an available initial state in  $V$ , and if we use the convention that the ground state action is defined to be zero, then  $F^-$  will always be 0, and so will not be very useful.

## 10 Effort to Perform an Operation

Suppose now that we are given *no* information about the situation to be analyzed except for a unitary operator  $U$  on the Hilbert space  $\mathcal{H}$ , and we want to address the following question: How much computational effort is required to physically implement  $U$ , in the sense that  $U$  is the time evolution operator over some interval

that ends up being generated by the dynamics, according to  $U = e^{iA}$  for some action operator  $A$ ? The above framework provides us a way to answer this question.

Assuming we have some freedom of choice in the design of the system, then among the set  $\mathcal{A}$  of all Hermitian operators  $A$  on  $\mathcal{H}$ , or among at least a set  $\aleph \subseteq \mathcal{A}$  of *available* or implementable action operators, we might want to choose the operator  $A$  that generates  $U$  that has the *smallest* value of the maximum or worst-case effort  $F^+(A)$  over the set  $V$  of possible initial state vectors. This  $A$  can be considered to be the “best” action operator for generating the given unitary  $U$ , in the sense that the length of the longest trajectory that would be undergone by any possible state vector  $v \in V$  is minimized. This strategy is analogous to what we do in traditional algorithm design, where we usually choose the algorithm that has the minimum time complexity on worst-case input data. In our case,  $A$  (or more precisely  $H(t)$ ) can be considered to represent the algorithm selected, while the initial vector  $v$  represents the input data. Rather than time complexity, we focus on effort or Hamiltonian action, since we saw earlier that this translates directly to time when a given supply of energy is available to be invested in the system.

In some situations, it may be preferred to choose  $A$  so as to minimize the *expected* effort rather than the worst-case effort, for example, if we want to minimize the total effort exerted over an arbitrarily large set of computations with randomly chosen input states selected from some distribution.

We can thus define the maximum  $F^+$  and expected  $\widehat{F}$  effort of a unitary transform  $U$  as follows:

$$\begin{aligned} F^+(U) &\equiv \min_{A \in \aleph} F^+(A) \\ &= \min_{A \in \aleph} \max_{v \in V} F_A(v) \end{aligned} \quad (27)$$

$$\begin{aligned} \widehat{F}(U) &\equiv \min_{A \in \aleph} \widehat{F}(A) \\ &= \min_{A \in \aleph} \sum_{v \in V} p(v) F(v) \end{aligned} \quad (28)$$

Note that we always still want to minimize over the available action operators, because there is usually no physical reason why indefinitely large action operators (which waste arbitrarily large amounts of effort) could not be constructed to implement a given unitary; maximizing over action operators would thus always give  $\infty$  and would not be meaningful.

A remark about the set of available action operators  $\aleph$ . Typically it would be constrained by what constitutes an “available” dynamics that we are free to choose within a given theoretical, experimental, or manufacturing context. For example,  $\aleph$  might reasonably be constrained to consist only of those action operators that are obtainable by time-integrating instantaneous Hamiltonians  $H(t)$  which are themselves constructed by summing over local interaction terms between neighboring subsystems, or by integrating a Hamiltonian density function that includes only local terms on a field over some topological space, *e.g.*, to reflect the local structure of spacetime in a quantum field theory picture. Or, we might constrain ourselves to action operators that are obtainable from time-independent Hamiltonians only,

*e.g.* if we are designing a self-contained (closed) quantum system. Finally, practical considerations may severely constrain the space of Hamiltonians to ones that can be readily constructed in devices buildable in a specific manufacturing process, although we should note that if scalable universal quantum computers can be built, then any desired local Hamiltonian could be straightforwardly emulated on these machines.

Now, given this notion of the computational effort of a given unitary  $U$ , we can now reinterpret previous results (such as [5, 13]) regarding “quantum speed limits” or minimum times to implement various specific unitary transforms of interest, or classes of transforms, given states of specified average energy above the ground state, as follows: These analyses are implicitly specifying an  $\aleph$  (usually, just all Hermitian operators) and a  $V$  (usually, just the entire Hilbert space), and showing that  $F^+(U)$  for the transform  $U$  has a specific value (or lower bound), assuming the presence of a time-independent Hamiltonian where the ground state energy is usually set to 0. In other words, such analyses show that a certain minimum worst-case effort or Hamiltonian action is required to implement the particular  $U$  in question.

As an example, Margolus and Levitin’s result [5] can be interpreted as telling us that any  $U$  that rotates some state  $v$  to an orthogonal state has a minimum worst-case effort of  $F^+(U) \geq h/4$ , since their result shows that any state of energy  $E$  takes time at least  $h/4E$  (no matter what the Hamiltonian) to accumulate the action needed to take it to an orthogonal state; thus the action  $A = Et$  that is required to carry out such a transition is at least  $h/4$ .

Another result in [5] implies that if there is a  $v$  such that  $(v, Uv, U^2v, \dots, U^{N-1}v, U^Nv = v)$  comprises a cycle of  $N$  states, with each orthogonal to the preceding and succeeding states in the cycle, then  $F^+(U) \geq \frac{h}{2} \frac{N-1}{N}$ , even if we are given complete freedom in constructing the Hamiltonian, aside from a requirement that it be time-independent. For  $N = 2$ , this expression reduces to  $h/4$ , while for  $N \rightarrow \infty$ , it goes to  $h/2$ . Thus, any physical computation that proceeds autonomously through an unbounded sequence of distinct states must exert at least  $h/2$  effort per state transition.

Notice that the Margolus-Levitin theorem is, strictly speaking, only giving us a *lower bound* on the worst-case effort, since it is considering only a particular state  $v$  of interest (namely, one that actually undergoes a transition to an orthogonal state), rather than finding the worst-case potential work to perform the corresponding  $U$ , maximized over all possible initial  $v$  in the Hilbert space. Later, we will see that the actual worst-case effort for an orthogonalizing transformation is actually  $h/2 = \pi$  even in the  $N = 2$  case, and possibly even higher in cases that go through more states.

We anticipate that, armed with the definitions proposed above, it would be a highly useful and worthwhile exercise to systematically go through a variety of the quantum unitary transforms that have already been identified in quantum computing as comprising useful “quantum logic gate” operations, and quantify their worst-case and average computational effort, according to the above definitions, under various physically realistic sets of constraints. This would directly tell us how much physical Hamiltonian action is required to carry out those operations

(given a best-case Hamiltonian implementation, while operating on a worst-case or average-case input state). We can likewise do the same for classical reversible Boolean logic operations embedded within unitary operations, as well as classical irreversible Boolean logic operations embedded within classical reversible operations, with ancilla bits used as needed for carrying away “erased” information to be discarded.

Such an investigation will, for the first time, give us a natural and physically well-founded measure of the physical complexity of logic operations, in terms of Hamiltonian action. This in turn would directly tell us the minimum physical time to perform these operations within any physical system or subsystem using a set of states having a given maximum energy about the ground state, given the known or prespecified constraints on the system’s initial state and its available Hamiltonian dynamics. This new quantification of computational complexity may also allow us to derive lower bounds on the number of quantum gates of a given type that would be required to implement a given larger transformation in terms of smaller ones, and possibly to show that certain constructions of larger gates out of smaller ones are optimal.

In subsequent subsections, we begin carrying out the above-described line of research with some initial investigations of the effort to carry out various operations in situations where the available dynamics is relatively unconstrained, which is the easiest case to analyze.

## 11 Specific Operations

In this section, we explore the amount of computational effort (according to our previous definitions) that is required to implement a variety of important quantum and classical logic operations.

We will begin by considering some educated guesses about the effort to carry out various unitaries. Remember, for each unitary  $U$  we are to imagine implementing it via a particular transformation trajectory  $U'(t)$  (and Hamiltonian  $H(t)$  such that  $U'(t) = e^{iH(t)dt}$ ) that is as “direct” as possible, in the sense of minimizing the Hilbert-space distance through which worst-case states are transported. Intuition tells us that these minimal trajectories should generally be thought of as being “geodesics” in the space of unitaries; in other words, they should be “straight-line” paths, so to speak, that get us to the desired unitary as directly as possible.

### 11.1 General two-dimensional unitaries

Let us begin by considering  $U_2$ , the space of unitary transformations on Hilbert spaces of dimensionality 2. In quantum computing, these correspond to single-qubit quantum logic gates. As is well known (*e.g.*, see [18], eq. 4.9), any such  $U$  can be decomposed as

$$U = e^{i\alpha} R_{\hat{n}}(\theta) \quad (29)$$

where  $\hat{n} = (n_x, n_y, n_z)$  is a real 3D unit vector and  $R_{\hat{n}}(\theta)$  is a Bloch-sphere rotation about this vector by an angle of  $\theta$ , that is,

$$R_{\hat{n}}(\theta) = e^{i(\theta/2)(\hat{n} \cdot \boldsymbol{\sigma})} \quad (30)$$

where  $\boldsymbol{\sigma} = (\sigma_x, \sigma_y, \sigma_z)$  are the Pauli matrices

$$\sigma_x = \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix}, \sigma_y = \begin{bmatrix} 0 & -i \\ i & 0 \end{bmatrix}, \sigma_z = \begin{bmatrix} 1 & 0 \\ 0 & -1 \end{bmatrix}. \quad (31)$$

Let us now consider breaking down  $U$  into its multiplicative factors  $e^{i\alpha}$  and  $R_{\hat{n}}(\theta)$ , which we observe commute with each other, since  $e^{i\alpha}$  is a scalar. Thus, we can consider these two components of  $U$  to be carried out in either order, or even simultaneously if we prefer.

Let's start by looking at  $R_{\hat{n}}(\theta)$ . At first, we might guess that the worst-case effort that is required to perform  $R_{\hat{n}}(\theta)$  for angles  $\theta$  where  $-\pi \leq \theta \leq \pi$  ought to just turn out to be  $|\theta|/2$ , since, for example, a Bloch sphere rotation through an angle of  $\pi$  radians corresponds to inverting a spin in ordinary 3D space through an angle of  $180^\circ$  to point in the opposite direction, which is an orthogonalizing transformation, and we already know from the Margolus-Levitin theorem that any transition to an orthogonal state under a constant Hamiltonian requires a minimum action (given zero ground state energy) for the state in question of  $h/4 = (\pi/2)\hbar = (\pi/2)$  rad, or an area swept out of  $\pi/4$  square units. This is a good first guess, but later, we will see that the actual worst-case action turns out to be twice as large as this. (Our intuition forgot to take into account the fact that the state vector in the Margolus-Levitin theorem isn't actually the worst-case one, as far as the accumulated action is concerned.)

Indeed, for any real unit 3-vector  $\hat{n}$  (the ‘‘axis of rotation’’ for the Bloch sphere), one can easily verify that there is always a corresponding complex state vector

$$v_{\hat{n}}^+ = \frac{1}{\sqrt{2(1+n_z)}} \begin{bmatrix} n_z + 1 \\ n_x + in_y \end{bmatrix} \quad (32)$$

which is a unit eigenvector of  $\hat{n} \cdot \boldsymbol{\sigma}$  having eigenvalue  $+1$ . This state vector is therefore also (see eq. (7)) an eigenstate of  $R_{\hat{n}}(\theta)$ , with eigenvalue  $e^{i(\theta/2)}$ . In other words, in any orthonormal basis that includes  $v_{\hat{n}}^+$  as one of the basis vectors, as  $\theta$  increases from 0 (for now, we'll assume for simplicity that the final value of  $\theta$  is non-negative,  $0 \leq \theta \leq \pi$ ), the coefficient of the  $|v_{\hat{n}}^+\rangle$  component of the state  $v(t) = R_{\hat{n}}(\theta)v_{\hat{n}}^+$  (starting from the initial state  $v_{\hat{n}}^+$ , where the coefficient is 1) describes a circular arc in the complex plane centered on the origin, sweeping out a total angle of  $\theta/2$ , and an origin-centered area of  $\theta/4$ . As we saw earlier, this same measure of the weighted-average accumulated angle and total area accumulated still holds in any basis. So, we have that the effort of  $R_{\hat{n}}(\theta)$  must be at least  $\theta/2$ . Indeed, this is the exact worst-case effort, since  $v_{\hat{n}}^+$ 's eigenvalue is maximal, so no pure energy eigenstate can possibly sweep out a larger angle as  $\theta$  increases, and therefore no superposition of energy eigenstates (*i.e.*, no general state) can do so either.

Now, what about the  $e^{i\alpha}$  factor that's included in the expression for a general  $U \in U_2$ ? Note that this term represents an overall (global) phase factor that applies to all eigenstates. As such, even the ground state  $g$  of whatever Hamiltonian is used to implement  $U$  might still accumulate a phase due to this phase factor. In this case,  $g$  would have nonzero Hamiltonian energy. If we redefine  $g$  to instead have zero energy ( $Hg = 0$ ), then  $g$ 's coefficient would not phase-rotate at all, since the action operator  $A = Ht$  would give  $Ag = 0$  for this state, and  $Ug$  would give  $(e^{iA})g = (e^0)g = g$ , that is,  $g$  would be unchanged by this  $U$ . However, it does not follow that we can always just let  $\alpha$  be zero, as  $g$  may generally have accumulated an additional phase resulting from the  $R_{\hat{n}}(\theta)$  component of  $U$  as well. It is the *total* phase accumulated by the ground state that we wish to define to be zero.

Let us now consider the following: Under the transformation  $R_{\hat{n}}(\theta)$ , as  $\theta$  increases from 0, we notice that  $v_{\hat{n}}^+$  (the eigenvalue +1 eigenstate of  $\hat{n} \cdot \sigma$  which we constructed above) only phase-rotates by an angle  $\theta/2$ . Under  $U = e^{i\alpha} R_{\hat{n}}(\theta)$ ,  $v_{\hat{n}}^+$  therefore undergoes an overall phase-rotation by an angle of  $\alpha + \theta/2$ . We conjecture that the “least potential action” or most efficient way to implement  $U$  is to apply a Hamiltonian that simultaneously sweeps both  $\alpha$  and  $\theta$  forward steadily from 0, at respective rates that are exactly proportional to their intended final values. If this is correct, then  $v_{\hat{n}}^+$  is indeed an eigenstate of that best-case Hamiltonian, with energy  $(\alpha + \theta/2)/t$  (recall that we're using  $\hbar = 1$ ), where  $t$  is the total time taken for  $\alpha$  and  $\theta$  to reach their final values.

However, since the space we are working with is two-dimensional, there must be another energy eigenstate as well. Solving the eigen-equation  $(\hat{n} \cdot \sigma)v = rv$ , we find that the other eigenvalue  $r$  of  $\hat{n} \cdot \sigma$  is  $-1$ , and the other unit-length eigenvector, modulo phase-rotations, is (for  $n_z > 0$ )

$$v_{\hat{n}}^- = \frac{1}{\sqrt{2(1-n_z)}} \begin{bmatrix} n_z - 1 \\ n_x + in_y \end{bmatrix} \quad (33)$$

or, in the special case when  $n_z = 0$ , then instead any normalized column vector  $v_{\hat{n}}^- = [v^0; v^1]$  where  $|v^0| = |v^1| = 2^{-1/2}$  will work, so long as the vector components  $v^0$  and  $v^1$  have the specific obtuse (that is,  $> 90^\circ$ ) relative phase angle that is given by the relation  $v^1 = (-n_x - in_y)v^0$ . (Note that  $|n_x + in_y| = 1$  when  $n_z = 0$ .)

Thus, for any Hamiltonian that smoothly sweeps  $\theta$  forward in a steady transformation  $R_{\hat{n}}(\theta)$  with  $\theta \propto t$ , there will actually be two different energy eigenstates having energies that are negatives of each other, one state in which the accumulated action of the Hamiltonian is  $\theta/2$  (as we saw above), and another state (the ground state) where the action is the negative of this, or  $-\theta/2$ . Together with the global phase-rotation of  $\alpha$ , we have that the total action for  $U$  is  $\alpha + \theta/2$  and  $\alpha - \theta/2$  for these two energy eigenstates, respectively.

Following our convention that the total action in the ground state should be always considered to be zero, we can shift the energy levels upwards in such a way that the lower value  $\alpha - \theta/2$  will be equal to 0, in other words, we can adjust our rate of global phase rotation (which determined  $\alpha$ ) in such a way that we have exactly  $\alpha = \theta/2$ . Now, the total action in the high energy state is  $\alpha + \theta/2 = \theta/2 + \theta/2 = \theta$ .

In other words, starting with any  $U \in U_2$  and decomposing it as  $U = e^{i\alpha} R_{\hat{n}}(\theta)$ , which involves a rotation of the Bloch sphere through an angle of  $\theta$  about an axis  $\hat{n}$ , we can calculate a meaningful effort  $F^+(U)$  by using the convention that the ground state should be considered to have energy 0, and by letting  $F^+(U) = F^+(U_{\hat{n}}(\theta))$ , where we define  $U_{\hat{n}}(\theta) \equiv e^{i\theta/2} R_{\hat{n}}(\theta)$ , that is, ignoring the original value of  $\alpha$  (whatever it was) and instead adjusting  $\alpha$  to have the value  $\alpha = \theta/2$  which assigns the ground state to zero energy. Thus, we can say that the “true” computational/physical effort of  $U$  (given this choice) is exactly  $\theta$  for any single-qubit unitary  $U = e^{i\alpha} R_{\hat{n}}(\theta)$ , regardless of the value of  $\alpha$ . If  $\theta$  is a pure number (implicitly bearing an angle unit of radians), then the worst-case Hamiltonian action to carry out the desired transform using the best-case Hamiltonian (assuming that is indeed what we have managed to characterize above) is  $\theta\hbar$ , in whatever physical units we wish to express  $\hbar$ . That is,  $F^+(U) = \theta$ .

To wrap up this section, let us take a look at the precise form of the Hamiltonian that we are proposing. Note that

$$\hat{n} \cdot \boldsymbol{\sigma} = \begin{bmatrix} n_z & n_x - in_y \\ n_x + in_y & -n_z \end{bmatrix} \quad (34)$$

is itself an Hermitian operator which plays the role of the Hamiltonian operator  $H$  with respect to the Bloch-sphere rotation unitary  $R_{\hat{n}}(\theta) = e^{i(\theta/2)(\hat{n} \cdot \boldsymbol{\sigma})}$ , if the rotation angle  $\theta$  is taken be equal to twice the time  $t$ . Meanwhile, in this scenario, the extra phase-rotation factor  $e^{i\alpha} = e^{i(\theta/2)}$  out front corresponds simply to an additional constant energy of  $+1$ , using the same angular velocity units of  $(\theta/2t)$ . This gives us a total “Hamiltonian” (in quotes because we haven’t introduced an explicit time parameter here yet) of  $H_{\hat{n}}$  that is required to implement a steady rotation about  $\hat{n}$  which is equal to

$$\begin{aligned} H_{\hat{n}} &= 1 + \hat{n} \cdot \boldsymbol{\sigma} \\ &= \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix} + \begin{bmatrix} n_z & n_x - in_y \\ n_x + in_y & -n_z \end{bmatrix} \\ &= \begin{bmatrix} 1 + n_z & n_x - in_y \\ n_x + in_y & 1 - n_z \end{bmatrix}. \end{aligned} \quad (35)$$

With this choice of “Hamiltonian,” you can easily check that the  $v_{\hat{n}}^{\pm}$  are indeed its energy eigenstates, with  $H_{\hat{n}} v_{\hat{n}}^- = 0$  (the ground state has “energy” 0) and  $H_{\hat{n}} v_{\hat{n}}^+ = 2$ , which is what we want since it will cancel out with the 2 in the denominator of the exponent in the rotation unitary  $U_{\hat{n}}(\theta) = e^{i\theta/2} R_{\hat{n}}(\theta) = e^{i(\theta/2)(1 + \hat{n} \cdot \boldsymbol{\sigma})} = e^{i(\theta/2)H_{\hat{n}}}$ .

To generalize the picture slightly, if a rotation through  $\theta$  about an axis  $\hat{n}$  is to take place over an arbitrary amount of time  $t$ , then we require a Hamiltonian (a proper one now, in actual angular-velocity energy units) of

$$H = \frac{\theta}{2t} H_{\hat{n}} = \frac{\theta}{2t} \begin{bmatrix} 1 + n_z & n_x - in_y \\ n_x + in_y & 1 - n_z \end{bmatrix} \quad (36)$$

With this choice of Hamiltonian, note that things works out nicely so that the high-energy eigenstate  $v_{\hat{n}}^+$  phase-rotates at exactly the desired rate  $\omega^+ = \theta/t$ ,

since we have that

$$Hv_{\hat{n}}^+ = \frac{\theta}{2t}H_{\hat{n}}v_{\hat{n}}^+ = \frac{\theta}{2t}2v_{\hat{n}}^+ = \frac{\theta}{t}v_{\hat{n}}^+ = \omega^+v_{\hat{n}}^+. \quad (37)$$

Thus, the action operator  $A = Ht$  comes out exactly equal to the angle operator  $\Omega$  which gives the total angle of phase rotation for both the energy eigenstates  $v_{\hat{n}}^+$  and  $v_{\hat{n}}^-$ , that is,  $Av_{\hat{n}}^- = \Omega v_{\hat{n}}^- = 0v_{\hat{n}}^-$  and  $Av_{\hat{n}}^+ = \Omega v_{\hat{n}}^+ = \theta v_{\hat{n}}^+$ . And for an arbitrary initial state  $v$ , *i.e.*, for any normalized complex superposition of the eigenstates  $v_{\hat{n}}^{\pm}$ ,  $\langle v|A|v\rangle = \langle v|\Omega|v\rangle$  gives the quantum mean angle of phase rotation.

Of course, as usual, if we ever wish to convert from angular-velocity/angle units for energy/action (respectively) back to the usual kinds of physical units, we can simply multiply  $H$  (or  $A$ ) by  $\hbar$ , which makes the implicit angle unit “1 radian” explicit in whatever arbitrary system of units we are using.

Note that in all the above discussion, we have assumed that the rotation angle is non-negative, *i.e.*, that  $0 \leq \theta \leq \pi$  (rad). To complete the picture, note that for values of  $\theta$  between 0 and  $-\pi$ , we can convert them to positive angles by the simple expedient of rotating instead by an angle of  $|\theta| = -\theta$  about the  $-\hat{n}$  axis, which is an exactly equivalent rotation. This has the effect of exchanging the values of the  $v_{\hat{n}}^{\pm}$  eigenstates, as well as the sign of the  $H_{\hat{n}}$  component of  $H$ . Other than that, everything else is the same, with the result that the action  $A$  always comes out non-negative and equal to the absolute value of  $\theta$ . Of course, for the case of absolute angles lying outside the range  $(-\pi, \pi]$ , we can just reduce them to the equivalent angle in  $(-\pi, \pi]$  by adding or subtracting the appropriate multiple of  $2\pi$ .

In the above, although we have not yet quite finished proving rigorously that the specific  $H$  we have given is in fact the one that implements  $U$  with the least possible value of the worst-case action  $A$ , still, we expect that it should already seem highly plausible to the reader that this should in fact be the case, due to the directness and simplicity of our construction, which made use only of the simple fact that any arbitrary  $U \in U_2$  can be decomposed into a single generalized rotation about an arbitrary axis in real three-space, accompanied by a global phase rotation. Of course, a more complete proof of the optimality of this construction would be desirable to have, but it will have to wait for future work.

## 11.2 Specific single-qubit gates

Given the above discussion, to determine the effort of any single-qubit gate  $U$  is a simple matter of finding some unit 3-vector  $\hat{n}$  and angles  $\alpha, \theta \in (-\pi, \pi]$  such that  $U = e^{i\alpha}R_{\hat{n}}(\theta)$ , which is always possible. This then establishes that  $F^+(U) = |\theta|$ , under our ground zero energy convention. Let us look briefly at how this calculation comes out for various single-qubit gates of interest.

1. The Pauli spin-operator “gates”  $X = \sigma_x$  (which is the in-place NOT operation in the computational basis),  $Y = \sigma_y$ , and  $Z = \sigma_z$  all of course involve a rotation angle of  $\theta = \pi$ , since they all square to the identity ( $2\pi$  rotation). Thus,  $F^+(X) = F^+(Y) = F^+(Z) = \pi = \hbar/2$ .

2. The “square root of NOT” gate  $N = \frac{1}{2} \begin{bmatrix} 1+i & 1-i \\ 1-i & 1+i \end{bmatrix}$  of course requires an angle of  $\pi/2$ , since  $N^2 = X$ . Thus,  $F^+(N) = \pi/2 = h/4$ .
3. The Hadamard gate  $N = \frac{1}{\sqrt{2}} \begin{bmatrix} 1 & -1 \\ 1 & 1 \end{bmatrix}$  requires a rotation angle of  $\pi$  about the  $\hat{n} = (1, 0, 1)/\sqrt{2}$  axis, *i.e.*,  $\hat{n} \cdot \boldsymbol{\sigma} = (\sigma_x + \sigma_z)/\sqrt{2}$ . Also note that  $H^2 = 1$  and a rotation through  $2\pi$  is the identity. Thus,  $F^+(H) = \pi = h/2$ .
4. The “phase gate”  $S = \begin{bmatrix} 1 & 0 \\ 0 & i \end{bmatrix}$  requires  $\theta = \pi/2$  since note that  $S^2 = Z$ . So,  $F^+(S) = \pi/2 = h/4$ .
5. The so-called “ $\pi/8$ ” gate  $T = \begin{bmatrix} 1 & 0 \\ 0 & \exp[i\pi/4] \end{bmatrix}$  involves  $\theta = \pi/4$  since note that  $T^4 = Z$ . Thus,  $F^+(T) = \pi/4 = h/8$ .
6. The generalized phase gate  $\text{ph}(\theta) = \begin{bmatrix} 1 & 0 \\ 0 & \exp[i\theta] \end{bmatrix}$  is just a rotation by an angle of  $\theta$  about the  $z$  axis, so  $F^+(\text{ph}(\theta)) = \theta = \theta\hbar$ .

As a point of comparison, the paper [13] studies the time required to perform the specific gate  $U = e^{i\theta} X$  (*i.e.*, NOT with global phase rotation) using an optimal Hamiltonian, and conclude that the minimum time  $\tau$  required (for a specific initial state) is

$$\tau = \frac{h}{4E} \left( 1 + 2\frac{\theta}{\pi} \right). \quad (38)$$

Note that the corresponding action  $A$  or effort  $F$  is

$$\begin{aligned} A = F = E\tau &= \frac{h}{4} + 2\frac{h}{4}\frac{\theta}{\pi} \\ &= \frac{\pi}{2}\hbar + \theta\hbar \\ &= \frac{\pi}{2} + \theta \quad (\text{with } \hbar = 1). \end{aligned} \quad (39)$$

At first glance, this might appear to contradict our claim that the effort to perform such a  $U$  ought to be exactly  $\pi$ . However, we should keep two things in mind. First, in [13], Levitin *et al.* are concerned with the time to carry out  $U$  in the case of a specific subset of initial states which will actually transition to an orthogonal state in the time  $\tau$ . However, these particular states are not the “worst-case” ones from our perspective, and so they don’t determine the maximum effort. Rather, the particular states under consideration in their paper all have a mean energy of only  $\bar{E} = (E_1 + E_2)/2$ , where  $E_1$  and  $E_2$  are the low and high energy eigenvalues of the ideal Hamiltonian, respectively. Letting  $E_1 = 0$  (our ground zero assumption), we have that  $E_2 = 2\bar{E}$ . Since  $E_2$  has the highest energy available given this spectrum, the  $E_2$  energy eigenstate accumulates more action over the time  $\tau$  than any other possible state, in particular, double that of states with energy  $\bar{E} = E_2/2$ , and thus it is the  $E_2$  state that determines the worst-case action, which is twice that of [13], or in other words  $A = \pi$ . The term involving  $\theta$  drops out entirely, since as we already saw earlier, global phase shifts are irrelevant when considering total action, under our convention that the ground state action is always defined to be zero. Levitin *et al.* don’t make this adjustment, because they are assuming that the Hamiltonian has already been arranged in advance to have a desired energy scale.

Thus, the global phase rotation by  $\theta$  leads to an extra additive  $\theta$  in their expression (39) for the action.

### 11.3 Effort required for infidelity

A natural and widely-used measure of the degree of closeness or similarity between two quantum states  $u, v$  is the *fidelity*, which is defined (for pure states) as  $F(u, v) = |\langle u|v\rangle| = |u^\dagger v|$ . (See [18].) Note that if the actual state of a system is  $u$ , and we measure it in a measurement basis that includes  $v$  as a basis vector, the square of the fidelity  $p = F^2$  gives the probability that the measurement operator will project the state down to  $v$ , and that  $v$  will be seen as the “actual” state. (This is a “quantum jump” or “wavefunction collapse” event, or, in the many-worlds picture, it is the subjectively experienced outcome when the state of the observer becomes inextricably entangled with that of the system.) Likewise with the roles of  $u$  and  $v$  reversed. Thus, only when  $F = 0$  are the states  $u$  and  $v$  orthogonal.

We can also define a related quantity, the “infidelity”  $Inf(u, v) \equiv \sqrt{1 - p} = \sqrt{1 - F^2}$ . The squared infidelity between  $u$  and  $v$  is then just the probability  $1 - p$  that if the actual state is  $u$ , then it will *not* be taken to  $v$  by a projective measurement (in a measurement basis that includes  $v$ ), and vice-versa. In other words, if  $v$  is some old state of a system, and  $u$  is its new state, the squared infidelity between  $u$  and  $v$  is the probability that the answer to the question “Is the state different from  $v$  yet?” will be found to be “yes” when this question is asked experimentally by a measurement apparatus that compares the state with  $v$ .

Let us now explore the minimum effort that is required in order for some of the possible state vectors of a system to attain a given degree of infidelity (relative to their initial states), in the case of two-dimensional Hilbert spaces. (Note that not all vectors will achieve infidelity; in particular, the eigenvectors of any time-independent Hamiltonian will always have 0 infidelity.)

We start by recalling from earlier that any 2-dimensional unitary can be considered a rotation of the Bloch sphere about some axis in ordinary (real-valued) 3-D space. Since a simple change of basis suffices to transform any axis to any other, we can without loss of generality presume a rotation about the  $z$  axis, represented by

$$R_{\hat{z}}(\theta) = \begin{bmatrix} e^{-i\theta/2} & 0 \\ 0 & e^{i\theta/2} \end{bmatrix}. \quad (40)$$

We saw earlier that the effort of any such rotation (under the ground-zero convention) is always exactly  $\theta$ . What initial state will gain infidelity most rapidly under this transformation? Until we figure this out, let us allow the initial state to be a general unit vector  $v = [v_0; v_1] = v_0|0\rangle + v_1|1\rangle$  in the basis  $|0\rangle, |1\rangle$ . Then  $u = R_{\hat{z}}(\theta)v = [e^{-i\theta/2}v_0; e^{i\theta/2}v_1]$  as a column vector of complex coefficients. Now the fidelity between  $v$  and  $u$  is

$$\begin{aligned} F(v, u) &= |\langle v|u\rangle| = |\langle v|R_{\hat{z}}(\theta)v\rangle| \\ &= \left| \{v_0^* e^{-i\theta/2} v_0 + v_1^* e^{i\theta/2} v_1\} \right| \end{aligned}$$

$$\begin{aligned}
&= \left| \{e^{-i\theta/2}v_0^*v_0 + e^{i\theta/2}v_1^*v_1\} \right| \\
&= \left| \{e^{-i\theta/2}|v_0|^2 + e^{i\theta/2}|v_1|^2\} \right| \\
&= \left| \left\{ \left[ \cos \frac{\theta}{2} - i \sin \frac{\theta}{2} \right] |v_0|^2 + \left[ \cos \frac{\theta}{2} + i \sin \frac{\theta}{2} \right] |v_1|^2 \right\} \right| \\
&= \left| \left\{ \left( \cos \frac{\theta}{2} \right) (|v_0|^2 + |v_1|^2) + i \left( \sin \frac{\theta}{2} \right) (|v_1|^2 - |v_0|^2) \right\} \right| \\
&= \left| \left\{ \left( \cos \frac{\theta}{2} \right) + i \left( \sin \frac{\theta}{2} \right) (|v_1|^2 - |v_0|^2) \right\} \right|. \tag{41}
\end{aligned}$$

where in the last line we have made use of the fact that  $|v_0|^2 + |v_1|^2 = 1$  for a normalized  $v$ . Now,  $F^2$  is the sum of the squared real and imaginary components of the expression inside the outermost absolute-value delimiters  $||$  above:

$$\begin{aligned}
[F(u, v)]^2 &= \Im^2[\langle v|u \rangle] + \Re^2[\langle v|u \rangle] \\
&= \cos^2 \left( \frac{\theta}{2} \right) + \sin^2 \left( \frac{\theta}{2} \right) (|v_1|^2 - |v_0|^2)^2 \\
&= \cos^2 \left( \frac{\theta}{2} \right) + \sin^2 \left( \frac{\theta}{2} \right) (1 - 4|v_1|^2|v_0|^2) \\
&= 1 - 4 \sin^2 \left( \frac{\theta}{2} \right) |v_1|^2|v_0|^2, \tag{42}
\end{aligned}$$

where in getting from the second to the third line, we have again made use of the fact that  $|v_0|^2 + |v_1|^2 = 1$ . We can reassure ourselves that the last line of (42) is always in the range  $[0, 1]$ , since  $|v_0|^2|v_1|^2 \leq 1/4$  given that  $|v_0|^2 + |v_1|^2 = 1$ . Note also that the fidelity is minimized when  $|v_0|^2 = |v_1|^2 = \frac{1}{2}$ , that is, when the two  $z$ -basis states are in an equal superposition. This is then the “worst case” (worst in terms of “least fidelity”) which we wish to focus on.

So now, the infidelity  $I = Inf(u, v) = \sqrt{1 - F^2(u, v)}$  comes out to be a reasonably simple expression:

$$\begin{aligned}
Inf(u, v) &= \sqrt{1 - [F(u, v)]^2} \\
&= \sqrt{4 \sin^2 \left( \frac{\theta}{2} \right) |v_1|^2|v_0|^2} \tag{43}
\end{aligned}$$

$$= 2 \left( \sin \frac{\theta}{2} \right) |v_0||v_1|. \tag{44}$$

Note that for any given angle of rotation in  $0 < \theta < \pi/2$ , the infidelity is maximized when  $|v_0| = |v_1| = 1/\sqrt{2}$ . For such  $v$ ,  $|v_0||v_1| = \frac{1}{2}$  and so

$$Inf(u, v) = \sin \frac{\theta}{2}. \tag{45}$$

Thus, if we wish that some system initially in state  $v$  should achieve a desired degree  $I$  of infidelity (relative to its initial state) using a transformation of minimum

effort, we must choose a unitary transformation that is a rotation  $R_{\hat{n}}(\theta)$  about an axis  $\hat{n}$  that is “perpendicular” to  $v$ , and rotate by an angle  $\theta = 2 \cdot \arcsin(I)$ . The action accumulated by “worst-case” (that is, maximum-energy) vectors under this transformation is (by definition) the effort of that unitary, and is  $A = 2 \cdot \arcsin(I)$ .

However, the specific initial vector  $v$  that we are dealing with will not have the maximum energy  $E$  (relative to ground) but rather half of this, or  $E/2$ , since half of its probability mass will be in the high-energy state, and half in the zero-energy ground state. Therefore,  $v$ ’s total action (amount of change) along its trajectory will instead be exactly  $A = \arcsin(I)$ , a wonderfully simple expression. This  $A$  is the effort exerted by the specific state  $v$  in achieving an infidelity of  $I = \sin A$  as it traverses a maximally efficient path for achieving such infidelity.

So, for example, suppose we want to cause some given initial state  $v$  to transition to a new state that has only a probability of at most  $p = 1/2$  of being confused with the initial state if it were measured. This is to say that the infidelity between the states should be at least  $I = \sqrt{1-p} = 1/\sqrt{2}$ , which requires the state to traverse a trajectory that has a length of at least  $\theta = \arcsin(I) = \arcsin(1/\sqrt{2}) = \pi/4 = h/8$ , which can be done using a least-effort unitary transform whose worst-case effort is twice as great as this, or  $\pi/2 = h/4$ , meaning that the worst-case (maximum-energy) states of the system would traverse a trajectory of this (greater) length under such a transformation.

Assuming that the actual given initial state in question is assigned an average energy of only  $E$  above the ground state, it will take time at least  $t = h/8E$  to carry out a unitary transformation on this state that achieves a probability above  $1/2$  of distinguishing it from the resulting state; whereas, if we are given that the *maximum* energy state in the qubit spectrum has energy  $E$ , then it will take time at least  $t = h/4E$  to carry out the transform.

In other words, to carry out an operation in time  $t$  that yields a 50% probability (or less) of conflation of some initial states with their successors requires that the initial states in question must have energy at least  $E = h/8t$ , and that states of energy at least  $E = h/4t$  must exist in the spectrum.

Note that the above results are also perfectly consistent with the Margolus-Levitin theorem [5]. That is, plugging in an infidelity of  $I = 1$ , we find that the specific initial state’s effort  $F(v) = \arcsin(1) = \pi/2$  while the worst-case effort for this transform is  $\theta = 2 \arcsin(1) = \pi$ ; these figures are twice that for the previous example. And so for a state to attain a 0% probability of conflation (*i.e.*, to reach an orthogonal state) requires that it have at least twice the energy as the previous scenario, or  $E = h/4t$  (under the Hamiltonian used to carry out the transformation), while other energy levels of at least  $h/2t = \pi/t$  must be present in the spectrum of the Hamiltonian operator being used.

#### 11.4 Higher-dimensional operations

Naturally, we are interested not only in unitaries in  $U_2$ , but also in higher dimensions, in particular, unitaries in the groups  $U_{2^n}$ , which correspond to general “quantum logic gate” operations (really, arbitrary quantum computations) operating on sets of  $n$  qubits.

In particular, let us focus on the “controlled- $U$ ” gates with one target bit, which take the general form (modulo qubit reorderings)

$$U' = C^{n-1}U \equiv \begin{bmatrix} 1 & & & \\ & 1 & & \\ & & \ddots & \\ & & & U \end{bmatrix} \quad (46)$$

where we have  $2^n - 2$  ones along the diagonal, and a rank-2 unitary matrix  $U$  in the lower-right corner. In other words, for computational basis states  $|b_0 b_1 \dots b_{n-1}\rangle$ , whenever the first  $n - 1$  qubits  $b_0 b_1 \dots b_{n-2}$  are not all 1's, the state remains unchanged; otherwise, the unitary  $U$  is performed on the final qubit  $b_{n-1}$ .

We observe immediately that  $F^+(U') \geq F^+(U)$ , since all the input states that undergo any change at all will undergo the exact same transformation (in the subspace associated with the last qubit) that they would if  $U$  were just applied unconditionally. Thus, the worst-case trajectories when conditionally applying  $U$  can be no shorter than the worst-case unconditional trajectories.

Furthermore, if  $U$  by itself would be optimally implemented by the Hamiltonian  $H$ , then it is easy to believe that  $U'$  would likewise be optimally implemented by the Hamiltonian

$$H' = \begin{bmatrix} 0 & & & \\ & 0 & & \\ & & \ddots & \\ & & & H \end{bmatrix} \quad (47)$$

that is, with 0's everywhere except for a copy of  $H$  in the lower-right  $2 \times 2$  submatrix. It is easy to verify that this  $H'$ , when exponentiated, indeed produces the desired  $U'$ . And since its worst-case effort is equal to our lower bound  $F^+(U)$ , it is in fact an optimal  $H'$ , assuming our earlier conjecture about the optimality of  $H$  is correct. In this case, if  $H'$  is actually an available Hamiltonian in the context one is considering, then the effort of  $U'$  is indeed exactly the same as the effort of  $U$ .

We can see from this example that when we consider the full space of mathematically describable Hamiltonians, we are likely to greatly underestimate the effort, compared to what can actually be implemented. The typical known implementations of  $U$  in terms of small local quantum gates would require a number of orthogonalizing operations that is at least linear in  $n$ , whereas in our case above, the effort is constant (upper-bounded by  $\pi$ ). It seems likely that the effort for a physically realistic (*e.g.* field-theory based) Hamiltonian for this class of  $U$ s would have to be more than constant, since the interaction of  $n$  qubits to determine an outcome would appear to necessarily be a non-local process.

In most physical situations of interest, we will not have available Hamiltonians that are of any desired form, such as the form  $H'$  suggested above. Instead, we may only have available a more limited, perhaps parameterized suite of Hamiltonians, perhaps ones that are formed by a sum or time-sequence of specific, controllable, localized couplings having (say) at most 2 qubits each, as is popularly represented

in the quantum computing literature using the schematic notation of quantum logic networks.

Obviously, whenever our space of available Hamiltonians is more restricted than the simple “all Hermitian operations” scenario analyzed above, the resulting values of  $F^+(U)$  will in general become much larger, and probably also much more difficult for us to analytically calculate. To compute  $F^+(U)$  for Hamiltonians that can plausibly be constructed within the context of particular experimental frameworks that are readily physically realizable in the lab (or in a manufactured product, *e.g.*, a someday-hopefully-to-be-realized commercial quantum computer) is clearly a much more complex and difficult task than we have attempted to tackle in this paper. To address this problem more fully will have to wait for future work.

Still, we hope that the present work can at least serve as a fruitful conceptual foundation on which we can proceed to build meaningful analytical and/or numerical analyses of the physical “effort” required to perform various physical/computational operations. We also hope that this work will serve as a helpful stepping stone for future investigators who wish to continue exploring the many deep and rich interconnections between physical and computational concepts.

### *11.5 Classical reversible and irreversible Boolean operations*

Although in the above discussion we have focused on the effort required to carry out quantum gate operations, it is easy to apply the results to classical logic operations as well. Any classical reversible operation is just a special case of a quantum gate where the matrix elements of the unitary are 0 or 1. For example, a reversible Toffoli gate or Controlled-Controlled-NOT (CCNOT) is a special case of the  $C^2U$  gate addressed in §11.4 above. Specifically, since the  $U$  in question is  $X$  (NOT), which has a rotation angle of  $\pi$ , the effort required for Toffoli must be at least  $\pi$ , and indeed is exactly  $\pi$  if arbitrary Hamiltonians can be constructed. Toffoli is a universal gate for classical reversible computation, so a construction of any classical reversible circuit out of Toffoli gates sets an upper bound (as a multiple of  $\pi$ ) on the effort required to carry out that computation, aside from the effort required to step through the desired gate sequence (which could be substantial, but is probably close to linear in the number of operations performed).

As for ordinary irreversible Boolean operations, these can be embedded into reversible operations as follows. Consider, for example, a standard boolean inverter, whose function is irreversible as it is normally specified in an electrical engineering context. The explicit function of an inverter is to destructively overwrite its output node with the logical complement of its input. (Please note that this function is distinct from that of a classical reversible NOT operation, which simply toggles a bit in-place.) Due to Landauer’s principle, the physical information contained in the output node cannot actually be destroyed, but is instead transferred to reside in the environment. So, we can model the ordinary inverter’s function as a sequence of reversible operations as follows:

1. Exchange output bit with an empty bit in the device’s environment

2. Increment an “environment pointer” to refer to the next empty bit in some unbounded list
3. Perform a CNOT between input node and (now empty) output node

The first step can be understood as the emission from the device of the old stored value of the bit, in the form of entropy. The second step can be viewed as implementing the continuous flow of entropy away from the device, to make room for discarding the results of subsequent inverter operations. Finally, the third step carries out the desired logical function. The above breakdown is not necessarily the simplest possible implementation of the classical inverter (although it is probably close), but it at least sets an upper limit on the number of steps that are absolutely required.

The first step can be carried out by a unitary SWAP operation between the two bits in question. The second step can be carried out by an annihilate/create pair of operations that moves a “particle” by one position to point to the next empty location in the environment; this corresponds to a unitary operation that increments the state vector  $|i\rangle$  of some subsystem that specifies the integer location  $i$  of the environment pointer. Finally, the third step is just an ordinary CNOT, with an effort of  $\pi$ . In principle, we could calculate and add up the effort for all these steps, together with the effort needed to update a part of the machine state that keeps track of which step we are on, to arrive at an upper bound on the effort required to implement a classical inverter operation. However, this calculation might not be very meaningful unless we did more work to specify a detailed physical setup that would allow us to confirm that such a bound was achievable in a practical hardware implementation.

## 12 Conclusion

In this paper, we have shown that any continuous trajectory of a normalized state vector can be measured by a real-valued quantity which we call the *effort*, which is given by the line integral, along the trajectory, of the imaginary component of the inner product between adjacent states along the trajectory. This quantity is basis-independent, and is numerically equal to the probability-weighted average phase angle accumulated by the basis state coefficients (in radians), and to twice the area swept out by the coefficients in the complex plane, and also to the action of the time-dependent system Hamiltonian in units of  $\hbar$ . This notion of effort can be easily extended to apply also to transformation trajectories  $U'(t)$  over time, as well as to an overall resulting unitary transform  $U$ , where it measures the minimum effort (minimizing over available trajectories) required to implement the desired transform in the worst case (maximizing over the possible initial states). Our framework can be used to easily rederive a variety of related results obtained by earlier papers for various more specialized cases.

The major implication of these results is that there is indeed a very definite sense in which we can say that the physical concept of energy does indeed precisely correspond to the computational concept of the rate of computation, that is, we can validly say that energy *is* (the rate of) physical computing activity, defined

as the rate of change of the state vector, according to the measure that we have emphasized in this paper. Furthermore, we can validly say that physical action *is* (the amount of) computation, defined as the total amount of change of the state vector, in the sense we have defined.


What about different specific types of energy, and specific types of action? Later papers along this line of research will survey how different types of energy and action might validly be identified with computational activity that is engaged in different types of processes. For example, heat may be identified with energy whose detailed configuration information is unknown (is entropy), rest mass-energy can be identified with energy that is engaged in updating a system's internal state in its rest frame, potential energy with phase rotation due to emission/absorption of virtual particles, *etc.*. It turns out that we can even make our computational interpretation consistent with special relativity by subdividing the energy of a moving body (in a given observer frame) into the *functional* energy  $\Phi$  that is associated with updating the body's internal state (this turns out to be just the negative Lagrangian  $-L = H - pv$ ) and a *motional* part  $M = pv$  (not quite the same as kinetic energy) that is associated with conveying the body through space; relativistic momentum then turns out to be the motional computational effort expended per unit distance traversed. Future papers will elaborate on these related themes in more depth.

It is hoped that the long-term outcome of this line of thought will be to eventually show how *all* physical concepts and quantities can be rigorously understood in a well-defined mathematical framework that is also simultaneously well-suited for describing physical implementations of desired computational processes. That is, we seek an eventual unifying mathematical foundation that is appropriate for not only physical science, but also for device-level computer engineering and for physics-based computer science. We expect that such a unifying perspective should greatly facilitate the future design and development of maximally efficient computers constructed from nanoscale (and perhaps, someday, even smaller) components, machines that attempt to harness the underlying computational resources provided by physics in the most efficient possible fashion.


## References

1. Claude E. Shannon. A mathematical theory of communication. *Bell System Tech. J.*, 27:379–423, 623–656, 1948.
2. Rolf Landauer. Irreversibility and heat generation in the computing process. *IBM J. Res. Dev.*, 5:183, 1961.
3. Charles H. Bennett. Logical reversibility of computation. *IBM J. Res. Dev.*, 17(6):525–32, 1973.
4. Charles H. Bennett. Demons, engines, and the second law. *Sci. Am.*, 295(5):108, 1987.
5. Norman H. Margolus and Lev B. Levitin. The maximum speed of dynamical evolution. *Physica D*, 120:188–195, 1998. quant-ph/9710043.
6. Seth Lloyd. Ultimate physical limits to computation. *Nature*, 406(1047-1054), Aug. 31 2000. quant-ph/9908043.
7. Seth Lloyd. Computational capacity of the universe. *Physical Review Letters*, 88(23), Jun. 10 2002. article 237901Z, quant-ph/0110141.


8. Seth Lloyd and Y. Jack Ng. Black hole computers. *Sci. Am.*, 291(5):52–61, 2004.
9. Rudolph Clausius. Über verschiedene für die anwendung bequeme formen der hauptgleichungen der mechanischen wärmetheorie. *Poggendorff's Annalen*, 125:353.
10. Ludwig Boltzmann. Weitere studien über das wärmegleichgewicht unter gasmolekülen. *Sitzungsberichte der Akademie der Wissenschaften, Wien, II*, 66:275–370, 1872. English translation in S.G. Brush, *Kinetic theory*, Vol. 2, *Irreversible processes*, pp. 88–175, Pergamon Press, Oxford, 1966.
11. Carlo Cercignani. *Ludwig Boltzmann: The Man Who Trusted Atoms*. Oxford University Press, 1998.
12. Max Tegmark. Is “the theory of everything” merely the ultimate ensemble theory? *Annals of Physics*, 270:1–51, 1998.
13. Lev B. Levitin, Tommaso Toffoli, and Zachary Walton. Operation time of quantum gates. arXiv:quant-ph/0210076, Oct. 2002.
14. Vittorio Giovannetti, Seth Lloyd, and Lorenzo Maccone. Quantum limits to dynamical evolution. *Phys. Rev. A*, 67:052109, 2003.
15. V. Giovannetti, S. Lloyd, and L. Maccone. The quantum speed limit. *Proc. SPIE*, 5111:1–6, 2003.
16. Tristan Needham. *Visual Complex Analysis*. Oxford University Press, 1997.
17. P.A.M. Dirac. *General Theory of Relativity*. Wiley, 1975. Reprinted in 1996 by Princeton University Press.
18. Michael A. Nielsen and Isaac L. Chuang. *Quantum Computation and Quantum Information*. Cambridge University Press, 2000.



**Figure 1.** A complex coefficient  $c_i$  sweeps out a small wedge-shaped area (shown exaggerated) in the complex plane over an infinitesimal time interval  $dt$ .



**Figure 2.** Area swept out (exaggerated) by a coefficient  $c_j$  (in a basis other than the energy eigenbasis) over an infinitesimal time interval  $dt$ . Note that both its phase and magnitude change, in general.



**Figure 3.** The infinitesimal area  $da_j$  swept out approaches one-half the parallelogram area  $m_j m'_j \sin d\theta$ .