

Measuring OpenSHMEM Communication Routines with SKaMPI-OpenSHMEM User's manual

Camille Coti and Allen D. Malony

May 2021

Contents

1	Introduction	2
1.1	Installation	2
1.2	Measuring routines	3
1.3	Notes specific to OpenSHMEM	3
2	New function	3
2.1	Set unit	3
3	Point to point communications	4
3.1	Put	4
3.2	Non-blocking put	6
3.3	Get	7
3.4	Non-blocking get	8
4	Collective communications	9
4.1	Broadcast	10
4.2	Reduce	11
4.3	Collect	11
4.4	All to all	11
4.5	Barrier	12
4.6	Sync	12

5	Memory management routines	13
6	Communication management routines	13
6.1	Create a communication context	13
6.2	Destroy a communication context	13
7	Memory ordering routines	14
8	Distributed locking routines	14
8.1	Take a lock	14
8.2	Release a lock	15
8.3	Test a lock	15

1 Introduction

This document presents the OpenSHMEM extension for the Special Karlsruhe MPI benchmark. This extension features:

- Measurement routines for the OpenSHMEM interface
- The SKaMPI measurement infrastructure using OpenSHMEM

The SKaMPI measurement infrastructure was originally written in MPI [2]. However, some OpenSHMEM libraries and run-time environments might not support MPI. For this case, we are providing the measurement infrastructure implemented in OpenSHMEM.

1.1 Installation

The configuration and installation is done using the autotools:

```
./configure
make -j
sudo make install
```

Available options are:

- `--disable-mpi`: disable MPI (measurement and infrastructure). MPI is enabled by default.

- `--enable-openshmem`: enable OpenSHMEM (measurement and, if MPI is disabled, infrastructure). OpenSHMEM is disabled by default.
- `--enable-papi`: enable measurements using PAPI. PAPI is disabled by default.

The measurement infrastructure is using MPI by default; if MPI is disabled, it uses OpenSHMEM.

1.2 Measuring routines

This extended version of SKaMPI is used exactly like SKaMPI:

```
mpiexec -n $NP --machinefile $MACHINEFILE ./skampi -i input.ski
```

Example of input files are provided in the `ski` directory of the package distribution.

1.3 Notes specific to OpenSHMEM

There is no such thing as communicators in OpenSHMEM as of version 1.4. Therefore, all the measurements must be done in `MPI_COMM_WORLD`:

```
comm_pt2pt = MPI_COMM_WORLD
measure comm_pt2pt : Shmem_Put_Simple(10, 5)
```

2 New function

2.1 Set unit

```
set_unit(1000000000)
```

This function is useful to get more precise results (in case of very fast communications). Default value: 1000000 (1e6: measurements given in microseconds). Scientific notation is not supported yet.

3 Point to point communications

The time taken by point-to-point communications can refer to several time intervals, according to the OpenSHMEM communication model. We provide several measurement routines in order to make it possible to measure them. In particular, the OpenSHMEM standard states that "these routines (put-based routines) start the remote transfer and may return before the data is delivered to the remote PE". Hence, we give the possibility to measure the time to post the communication and the total time to ensure its completion.

3.1 Put

- **Shmem_Put_Simple**

Measures the time to perform a simple put operation between process 0 and process 1. Process 0 only measures the time. The time measurement step includes a call to `shmem_quiet` in order to ensure completion of the data transfer. Outside of the data transfer measurement, we are measuring the time to complete an "empty" `shmem_quiet` and subtracting this time from the total time.

```
Shmem_Put_Simple( int count, int iterations )
```

- **Shmem_Pingpong_Put_Put**

Processes 0 and 1 simultaneously put data on each other. Like `Shmem_Put_Simple`, the time to perform an empty `shmem_quiet` is subtracted from the total time.

```
Shmem_Pingpong_Put_Put( int count, int iterations )
```

- **Shmem_Put_Round**

Processes are putting data into their +1 neighbor's memory in a round fashion. Like `Shmem_Put_Simple`, the time to perform an empty `shmem_quiet` is subtracted from the total time.

```
Shmem_Put_Round( int count, int iterations )
```

- **Shmem_Put_Full**

Processes are putting data into their +1 neighbor's memory in a round fashion. Unlike the previous measurement routines, this routine counts the time to perform `shmem_quiet`.

```
Shmem_Put_Full( int count, int iterations )
```

- `Shmem_Iput_Round`

Measures the time to perform a strided put operation between processes that communicate in a ring fashion. Like `Shmem_Put_Simple`, the time to perform an empty `shmem_quiet` is subtracted from the total time.

```
Shmem_Iput_Round( int count, int stride, int iterations )
```

Attention: the size of the buffer used for communications is set by SKaMPI by:

```
set_skampi_buffer( MAXSIZE )
```

Therefore, the *strided* data must fit in this buffer!

```
begin measurement "Iput_Round"
  stride = 16
  for count = 1 to MAXSIZE/stride step *sqrt(2) do
    measure comm_pt2pt : Shmem_Iput_Round(count, stride, 5)
  od
end measurement
```

- `Shmem_P_Simple`

Measures the time to perform a `shmem_p` from process 0 to process 1. Process 0 only measures the time. The time measurement step includes a call to `shmem_quiet` in order to ensure completion of the data transfer. Outside of the data transfer measurement, we are measuring the time to complete an "empty" `shmem_quiet` and subtracting this time from the total time.

```
Shmem_P_Simple( int iterations )
```

- `Shmem_P_Round`

Measures the time to perform a `shmem_p` operation between processes that communicate in a ring fashion. The time measurement step includes a call to `shmem_quiet` in order to ensure completion of the data transfer. Outside of the data transfer measurement, we are measuring the time to complete an "empty" `shmem_quiet` and subtracting this time from the total time.

```
Shmem_P_Round( int iterations )
```

3.2 Non-blocking put

- `Shmem_Put_Nonblocking_Post`

Measures the time to post a non-blocking `shmem_put_nbi`, and only the posting. Completion is ensured with `shmem_quiet`, which happens outside of the timing. Processes communicate in a ring fashion.

```
Shmem_Put_Nonblocking_Post( int count, int iterations )
```

- `Shmem_Put_Nonblocking_Quiet`

Measures the time to perform the `shmem_quiet` call that follows a call to a non-blocking put (happens outside of the timing). Processes communicate in a ring fashion. Since `shmem_quiet` is used to ensure completion of the (non-blocking) put operations issued before, this function is used to measure how long it takes to complete a previously posted non-blocking put operation.

```
Shmem_Put_Nonblocking_Quiet( int count, int iterations )
```

- `Shmem_Put_Nonblocking_Full`

Measures the time to post a non-blocking `shmem_put_nbi` and its completion with `shmem_quiet`. Processes communicate in a ring fashion.

```
Shmem_Put_Nonblocking_Full( int count, int iterations );
```

- `Shmem_Put_Nonblocking_Overlap`

This routine can be used to measure the percentage of overlap achieved. First, it measures the time taken by blocking operations. Then it posts a non-blocking put, and sleeps during 2x the time to perform the blocking operation. Then the time spent in `shmem_quiet` is measured. It returns the time spent in `shmem_quiet`. The overlap can be obtained by the ratio between the time spent in posting the operation and waiting for it to complete (returned here) and the time to perform the blocking operation. Processes communicate in a ring fashion.

```
Shmem_Put_Nonblocking_Overlap( int count, int iterations )
```

3.3 Get

Get-based routines are more straightforward to measure because the routine returns when the communication has completed and the data is available in the destination memory.

- `Shmem_Get_Simple`

Measures the time to perform a simple get operation between process 0 and process 1: process 0 pulls data from process 1. Process 0 only measures the time.

```
Shmem_Get_Simple( int count, int iterations )
```

- `Shmem_Get_Round`

Measures the time to perform a get operation between processes that communicate in a ring fashion.

```
Shmem_Get_Round( int count, int iterations )
```

- `Shmem_Iget_Round`

Measures the time to perform a strided get operation between processes that communicate in a ring fashion.

```
Shmem_Iget_Round( int count, int stride, int iterations )
```

Attention: the size of the buffer used for communications is set by SKaMPI by:

```
set_skampi_buffer( MAXSIZE )
```

Therefore, the *strided* data must fit in this buffer!

```
begin measurement "Iget_Round"  
  stride = 16  
  for count = 1 to MAXSIZE/stride step *sqrt(2) do  
    measure comm_pt2pt : Shmem_Iget_Round(count, stride, 5)  
  od  
end measurement
```

- Shmem_G_Simple

Measures the time to perform a `shmem_g` from process 0 to process 1. Process 0 only measures the time.

```
Shmem_G_Simple( int iterations )
```

- Shmem_G_Round

Measures the time to perform a `shmem_g` operation between processes that communicate in a ring fashion.

```
Shmem_G_Round( int iterations )
```

3.4 Non-blocking get

- Shmem_Get_Nonblocking_Post

Measures the time to post a non-blocking `shmem_get_nbi`, and only the posting. Completion is ensured with `shmem_quiet`, which happens outside of the timing. Processes communicate in a ring fashion.

```
Shmem_Get_Nonblocking_Post( int count, int iterations )
```

- Shmem_Get_Nonblocking_Full

Measures the time to post a non-blocking `shmem_get_nbi` and its completion with `shmem_quiet`. Processes communicate in a ring fashion.


```
Shmem_Get_Nonblocking_Full( int count, int iterations )
```

- Shmem_Get_Nonblocking_Quiet

Measures the time to perform the `shmem_quiet` call that follows a call to a non-blocking get (happens outside of the timing). Processes communicate in a ring fashion. Since `shmem_quiet` is used to ensure completion of the (non-blocking) get operations issued before, this function is used to measure how long it takes to complete a previously posted non-blocking get operation.

```
Shmem_Get_Nonblocking_Quiet( int count, int iterations )
```

- Shmem_Get_Nonblocking_Overlap

This routine can be used to measure the percentage of overlap achieved. First, it measures the time taken by blocking operations. Then it posts a non-blocking get, and sleeps during 2x the time to perform the blocking operation. Then the time spent in `shmem_quiet` is measured. It returns the time spent in `shmem_quiet`. The overlap can be obtained by the ratio between the time spent in posting the operation and waiting for it to complete (returned here) and the time to perform the blocking operation. Processes communicate in a ring fashion.

```
Shmem_Get_Nonblocking_Overlap( int count, int iterations )
```

4 Collective communications

Measuring collective communication routines is not trivial. Consecutive calls can be pipelined, for instance in the case of tree-based topology. However, the time to participate to a broadcast and exit, in a pipelined scheme, might be something we want to measure. Hence, we are providing measurement routines for *consecutive* calls. Otherwise, calls can be synchronized by *barriers* or by SKaMPI's internal *synchronization mechanism*.

4.1 Broadcast

- Shmem_Bcast_All

This routine measures the time to perform one `shmem_broadcast` between all the processes, using `count` bytes and providing the root of the broadcast. This measurement is performed on processes synchronized using SKaMPI's internal synchronization mechanism.

It runs only once, and takes the size of the buffers to use (`count` bytes) and the root of the broadcast.

```
Shmem_Bcast_All( int count, int root )
```

- Shmem_Bcast_All_Rounds

This benchmark method is called the *broadcast rounds* benchmark method: each rank of the communicator / team initiates a broadcast. There is still a possibility of pipelining, depending on the order used to cycle over the tasks.

It runs only once, and takes the size of the buffers to use (`count` bytes) and the root of the broadcast.

```
Bcast_All_Rounds( int count, int root )
```

- Shmem_Bcast_All_SK

This benchmark uses an adapted version of the algorithm by Bronis de Supinski and Nicholas Karonis that acknowledges participation to the broadcast, for each process [1].

It runs only once, and takes the size of the buffers to use (`count` bytes) and the root of the broadcast.

```
Shmem_Bcast_All_SK( int count, int root )
```

- Shmem_Bcast_All_Synchro

This method relies on SKaMPI's internal repetition and synchronization mechanisms.

It runs only once, and takes the size of the buffers to use (`count` bytes) and the root of the broadcast.

```
Shmem_Bcast_All_Synchro( int count, int root )
```

4.2 Reduce

Reductions can be measured in a consecutive fashion (with potential for inter-call pipelining), using barriers and using SKaMPI's internal synchronization mechanisms.

These routines take the number of iterations to measure on, the size of the buffers to use (`count` bytes) and the root of the reduction.

```
Shmem_Reduce_And_Consecutive(int iterations, int count)
Shmem_Reduce_And_Barrier(int iterations, int count)
Shmem_Reduce_And_Synchro(int count)
```

4.3 Collect

Collect and fcollect can be measured in a consecutive fashion (with potential for inter-call pipelining), using barriers and using SKaMPI's internal synchronization mechanisms.

These routines take the number of iterations to measure on and the size of the buffers to use (`count` bytes).

```
Shmem_Collect_Consecutive(int iterations, int count)
Shmem_Fcollect_Consecutive(int iterations, int count)
Shmem_Collect_Barrier(int iterations, int count)
Shmem_Fcollect_Barrier(int iterations, int count)
Shmem_Collect_Synchro(int count)
Shmem_Fcollect_Synchro(int count)
```

4.4 All to all

Alltoall and alltoalls can be measured in a consecutive fashion (with potential for inter-call pipelining), using barriers and using SKaMPI's internal synchronization mechanisms.

These routines take the number of iterations to measure on and the size of the buffers to use (`count` bytes).

```
Shmem_Alltoall_Consecutive( int iterations, int count )
Shmem_Alltoalls_Consecutive( int iterations, int count )
Shmem_Alltoall_Barrier( int iterations, int count )
Shmem_Alltoalls_Barrier( int iterations, int count )
Shmem_Alltoall_Synchro( int count )
Shmem_Alltoalls_Synchro( int count )
```

4.5 Barrier

- `Shmem_Barrier`

This routine measures the time taken by a single barrier, using SKaMPI's internal synchronization mechanisms.

```
Shmem_Barrier()
```

- `Shmem_Barrier_Consecutive`

This routine performs several consecutive barriers, allowing for potential pipeline. However, since the semantics of the barrier states that no process can exit the barrier before all the processes have entered it, the barrier should not have an important imbalance between processes and the potential for inter-call pipelining is not as important as with operations that can rely on a single tree topology, such as broadcasts and reductions. Processes are synchronized before the beginning of the measurement using SKaMPI's internal synchronization mechanisms.

This routines takes the number of iterations to measure on.

```
Shmem_Barrier_Consecutive( int iterations )
```

- `Shmem_Barrier_Half`, `Shmem_Barrier_Half_Consecutive`

These routines perform the same measurements on half of the processes.

```
Shmem_Barrier_Half()  
Shmem_Barrier_Half_Consecutive( int iterations )
```

4.6 Sync

These routines perform the same measurements with `shmem_sync`.

```
Shmem_Sync()  
Shmem_Sync_Consecutive( int iterations )  
Shmem_Sync_Half()  
Shmem_Sync_Half_Consecutive( int iterations )
```

5 Memory management routines

Memory management routines take the number of repetitions and, when relevant, the size of the buffer to allocate. `Shmem_Align` aligns the buffer on 2. `Shmem_Realloc` allocates half of the requested size using `shmem_malloc`, and reallocates to the requested size using `shmem_realloc`. The initial allocation is not counted in the returned time.

```
Shmem_Malloc( int iterations, int count )
Shmem_Free( int iterations )
Shmem_Realloc( int iterations, int count )
Shmem_Align( int iterations, int count )
Shmem_Calloc( int iterations, int nb, int count )
```

6 Communication management routines

6.1 Create a communication context

Contexts can be created with three options: `SHMEM_CTX_SERIALIZED`, `SHMEM_CTX_PRIVATE` and `SHMEM_CTX_NOSTORE`. A measurement function exists for each of these possibilities:

- `Shmem_Ctx_Create_Serialized`
- `Shmem_Ctx_Create_Private`
- `Shmem_Ctx_Create_Nostore`

For example:

```
Shmem_Ctx_Create_Serialized()
```

6.2 Destroy a communication context

In a similar way, three measurement functions exist for context destruction:

- `Shmem_Ctx_Destroy_Serialized`
- `Shmem_Ctx_Destroy_Private`

- `Shmem_Ctx_Destroy_Nostore`

For example:

```
Shmem_Ctx_Destroy_Private()
```

We recommend calling creation and destruction context measurement routines of the same type in order rather than interleaved, otherwise the execution may crash during the finalization of the OpenSHMEM library.

```
Shmem_Ctx_Create_Serialized()
Shmem_Ctx_Destroy_Serialized()
Shmem_Ctx_Create_Private()
Shmem_Ctx_Destroy_Private()
Shmem_Ctx_Create_Nostore()
Shmem_Ctx_Destroy_Nostore()
```

7 Memory ordering routines

We provide measurement routines for memory ordering functions.

```
Shmem_Quiet( int count )
Shmem_Fence( int count )
Shmem_Wait_Until( int count )
Shmem_Test( int count )
```

`shmem_fence` does not guarantee delivery of the previously posted communications but it guarantees they will be delivered in order. It might have a different cost when posted after a communication (such as a put). Hence, we are providing `Shmem_Fence_Put` that measures the cost of a `shmem_fence` following a `shmem_put`. The time to post `shmem_put` is not included in the measured time. These routines take the number of iterations and the number of bytes to send in the put.

```
Shmem_Quiet_Put( int count, int nb )
Shmem_Fence_Put( int count, int nb )
```

8 Distributed locking routines

8.1 Take a lock

Measure the time to take a lock: `Shmem_Set_Lock`.

```
Shmem_Set_Lock()
```

8.2 Release a lock

Measure the time to release a lock: `Shmem_Clear_Lock`. The lock is taken outside of the measured part.

```
Shmem_Clear_Lock()
```

8.3 Test a lock

- `Shmem_Lock_Test_Busy`

Process 1 takes the lock, holds it for a while (10 times the time to perform a barrier), process 0 tests it. In order to make sure that process 1 has taken the lock before process 0 tests it, we are performing a barrier after the call to `shmem_set_lock` on process 1 and before the call to `shmem_test_lock` on process 0.

Using this version, only process 0 will measure time. It also depends on the topology used by the underlying collective operation.

```
Shmem_Lock_Test_Busy()
```

- `Shmem_Lock_Test_Busy_All`

To address this last issue, a given process (the last one) is taking the lock during the initialization and all the other ones are testing it. They can test it in turns or concurrently. In this function, they are *all* testing the lock concurrently.

```
Shmem_Lock_Test_Busy_All()
```

- `Shmem_Lock_Test_Busy_Turns`

Same but in turns instead of concurrently.

```
Shmem_Lock_Test_Busy_Turns()
```

- `Shmem_Lock_Test_Busy_Round`

Since the time might depend on the topology and concurrent tests might flood the PEs' access to their symmetric heap,

- Each process becomes the locker, in turns
- For each turn, the locker locks
- All the other processes, in turns, test the lock
- The function returns the average.

Barriers ensure that no two processes are testing the lock concurrently.

<code>Shmem_Lock_Test_Busy_Round()</code>

References

- [1] Bronis R De Supinski and Nicholas T Karonis. Accurately measuring mpi broadcasts in a computational grid. In *Proceedings. The Eighth International Symposium on High Performance Distributed Computing (Cat. No. 99TH8469)*, pages 29–37. IEEE, 1999.
- [2] Thomas Worsch, Ralf Reussner, and Werner Augustin. Benchmarking collective operations with skampi. In *High Performance Computing in Science and Engineering'02*, pages 491–502. Springer, 2003.